

User Documentation for IDA v4.0.2 (SUNDIALS v4.0.2)

Alan C. Hindmarsh, Radu Serban, and Aaron Collier
Center for Applied Scientific Computing
Lawrence Livermore National Laboratory

January 22, 2019



UCRL-SM-208112

DISCLAIMER

This document was prepared as an account of work sponsored by an agency of the United States government. Neither the United States government nor Lawrence Livermore National Security, LLC, nor any of their employees makes any warranty, expressed or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States government or Lawrence Livermore National Security, LLC. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States government or Lawrence Livermore National Security, LLC, and shall not be used for advertising or product endorsement purposes.

This work was performed under the auspices of the U.S. Department of Energy by Lawrence Livermore National Laboratory under Contract DE-AC52-07NA27344.

Contents

| | |
|--|-----------|
| List of Tables | ix |
| List of Figures | xi |
| 1 Introduction | 1 |
| 1.1 Changes from previous versions | 2 |
| 1.2 Reading this User Guide | 9 |
| 1.3 SUNDIALS Release License | 10 |
| 1.3.1 BSD 3-Clause License | 10 |
| 1.3.2 Additional Notice | 11 |
| 1.3.3 SUNDIALS Release Numbers | 11 |
| 2 Mathematical Considerations | 13 |
| 2.1 IVP solution | 13 |
| 2.2 Preconditioning | 17 |
| 2.3 Rootfinding | 17 |
| 3 Code Organization | 19 |
| 3.1 SUNDIALS organization | 19 |
| 3.2 IDA organization | 19 |
| 4 Using IDA for C Applications | 25 |
| 4.1 Access to library and header files | 25 |
| 4.2 Data types | 26 |
| 4.2.1 Floating point types | 26 |
| 4.2.2 Integer types used for vector and matrix indices | 26 |
| 4.3 Header files | 27 |
| 4.4 A skeleton of the user's main program | 28 |
| 4.5 User-callable functions | 31 |
| 4.5.1 IDA initialization and deallocation functions | 32 |
| 4.5.2 IDA tolerance specification functions | 32 |
| 4.5.3 Linear solver interface functions | 34 |
| 4.5.4 Nonlinear solver interface function | 36 |
| 4.5.5 Initial condition calculation function | 36 |
| 4.5.6 Rootfinding initialization function | 37 |
| 4.5.7 IDA solver function | 38 |
| 4.5.8 Optional input functions | 39 |
| 4.5.8.1 Main solver optional input functions | 39 |
| 4.5.8.2 Linear solver interface optional input functions | 45 |
| 4.5.8.3 Initial condition calculation optional input functions | 48 |
| 4.5.8.4 Rootfinding optional input functions | 50 |
| 4.5.9 Interpolated output function | 51 |
| 4.5.10 Optional output functions | 52 |

| | | |
|----------|--|-----------|
| 4.5.10.1 | SUNDIALS version information | 52 |
| 4.5.10.2 | Main solver optional output functions | 54 |
| 4.5.10.3 | Initial condition calculation optional output functions | 59 |
| 4.5.10.4 | Rootfinding optional output functions | 60 |
| 4.5.10.5 | IDALS linear solver interface optional output functions | 61 |
| 4.5.11 | IDA reinitialization function | 65 |
| 4.6 | User-supplied functions | 66 |
| 4.6.1 | Residual function | 66 |
| 4.6.2 | Error message handler function | 66 |
| 4.6.3 | Error weight function | 67 |
| 4.6.4 | Rootfinding function | 67 |
| 4.6.5 | Jacobian construction (matrix-based linear solvers) | 68 |
| 4.6.6 | Jacobian-vector product (matrix-free linear solvers) | 70 |
| 4.6.7 | Jacobian-vector product setup (matrix-free linear solvers) | 70 |
| 4.6.8 | Preconditioner solve (iterative linear solvers) | 71 |
| 4.6.9 | Preconditioner setup (iterative linear solvers) | 72 |
| 4.7 | A parallel band-block-diagonal preconditioner module | 73 |
| 5 | FIDA, an Interface Module for FORTRAN Applications | 79 |
| 5.1 | Important note on portability | 79 |
| 5.2 | Fortran Data Types | 79 |
| 5.3 | FIDA routines | 80 |
| 5.4 | Usage of the FIDA interface module | 82 |
| 5.5 | FIDA optional input and output | 89 |
| 5.6 | Usage of the FIDAROOT interface to rootfinding | 92 |
| 5.7 | Usage of the FIDABBD interface to IDABBDPRE | 93 |
| 6 | Description of the NVECTOR module | 97 |
| 6.1 | NVECTOR functions used by IDA | 106 |
| 6.2 | The NVECTOR_SERIAL implementation | 107 |
| 6.2.1 | NVECTOR_SERIAL accessor macros | 108 |
| 6.2.2 | NVECTOR_SERIAL functions | 108 |
| 6.2.3 | NVECTOR_SERIAL Fortran interfaces | 112 |
| 6.3 | The NVECTOR_PARALLEL implementation | 112 |
| 6.3.1 | NVECTOR_PARALLEL accessor macros | 112 |
| 6.3.2 | NVECTOR_PARALLEL functions | 113 |
| 6.3.3 | NVECTOR_PARALLEL Fortran interfaces | 116 |
| 6.4 | The NVECTOR_OPENMP implementation | 117 |
| 6.4.1 | NVECTOR_OPENMP accessor macros | 117 |
| 6.4.2 | NVECTOR_OPENMP functions | 118 |
| 6.4.3 | NVECTOR_OPENMP Fortran interfaces | 121 |
| 6.5 | The NVECTOR_PTHREADS implementation | 122 |
| 6.5.1 | NVECTOR_PTHREADS accessor macros | 122 |
| 6.5.2 | NVECTOR_PTHREADS functions | 123 |
| 6.5.3 | NVECTOR_PTHREADS Fortran interfaces | 126 |
| 6.6 | The NVECTOR_PARHYP implementation | 127 |
| 6.6.1 | NVECTOR_PARHYP functions | 127 |
| 6.7 | The NVECTOR_PETSC implementation | 130 |
| 6.7.1 | NVECTOR_PETSC functions | 131 |
| 6.8 | The NVECTOR_CUDA implementation | 134 |
| 6.8.1 | NVECTOR_CUDA functions | 134 |
| 6.9 | The NVECTOR_RAJA implementation | 139 |
| 6.9.1 | NVECTOR_RAJA functions | 140 |
| 6.10 | The NVECTOR_OPENMPDEV implementation | 144 |

| | | |
|----------|--|------------|
| 6.10.1 | NVECTOR_OPENMPDEV accessor macros | 144 |
| 6.10.2 | NVECTOR_OPENMPDEV functions | 145 |
| 6.11 | NVECTOR Examples | 148 |
| 7 | Description of the SUNMatrix module | 153 |
| 7.1 | SUNMatrix functions used by IDA | 156 |
| 7.2 | The SUNMatrix_Dense implementation | 156 |
| 7.2.1 | SUNMatrix_Dense accessor macros | 157 |
| 7.2.2 | SUNMatrix_Dense functions | 158 |
| 7.2.3 | SUNMatrix_Dense Fortran interfaces | 159 |
| 7.3 | The SUNMatrix_Band implementation | 160 |
| 7.3.1 | SUNMatrix_Band accessor macros | 162 |
| 7.3.2 | SUNMatrix_Band functions | 163 |
| 7.3.3 | SUNMatrix_Band Fortran interfaces | 165 |
| 7.4 | The SUNMatrix_Sparse implementation | 166 |
| 7.4.1 | SUNMatrix_Sparse accessor macros | 169 |
| 7.4.2 | SUNMatrix_Sparse functions | 170 |
| 7.4.3 | SUNMatrix_Sparse Fortran interfaces | 172 |
| 8 | Description of the SUNLinearSolver module | 175 |
| 8.1 | The SUNLinearSolver API | 176 |
| 8.1.1 | SUNLinearSolver core functions | 176 |
| 8.1.2 | SUNLinearSolver set functions | 178 |
| 8.1.3 | SUNLinearSolver get functions | 179 |
| 8.1.4 | Functions provided by SUNDIALS packages | 180 |
| 8.1.5 | SUNLinearSolver return codes | 181 |
| 8.1.6 | The generic SUNLinearSolver module | 182 |
| 8.2 | Compatibility of SUNLinearSolver modules | 183 |
| 8.3 | Implementing a custom SUNLinearSolver module | 183 |
| 8.3.1 | Intended use cases | 184 |
| 8.4 | IDA SUNLinearSolver interface | 185 |
| 8.4.1 | Lagged matrix information | 186 |
| 8.4.2 | Iterative linear solver tolerance | 186 |
| 8.5 | The SUNLinearSolver_Dense implementation | 187 |
| 8.5.1 | SUNLinearSolver_Dense description | 187 |
| 8.5.2 | SUNLinearSolver_Dense functions | 187 |
| 8.5.3 | SUNLinearSolver_Dense Fortran interfaces | 188 |
| 8.5.4 | SUNLinearSolver_Dense content | 189 |
| 8.6 | The SUNLinearSolver_Band implementation | 190 |
| 8.6.1 | SUNLinearSolver_Band description | 190 |
| 8.6.2 | SUNLinearSolver_Band functions | 190 |
| 8.6.3 | SUNLinearSolver_Band Fortran interfaces | 191 |
| 8.6.4 | SUNLinearSolver_Band content | 192 |
| 8.7 | The SUNLinearSolver_LapackDense implementation | 192 |
| 8.7.1 | SUNLinearSolver_LapackDense description | 192 |
| 8.7.2 | SUNLinearSolver_LapackDense functions | 193 |
| 8.7.3 | SUNLinearSolver_LapackDense Fortran interfaces | 193 |
| 8.7.4 | SUNLinearSolver_LapackDense content | 194 |
| 8.8 | The SUNLinearSolver_LapackBand implementation | 194 |
| 8.8.1 | SUNLinearSolver_LapackBand description | 195 |
| 8.8.2 | SUNLinearSolver_LapackBand functions | 195 |
| 8.8.3 | SUNLinearSolver_LapackBand Fortran interfaces | 196 |
| 8.8.4 | SUNLinearSolver_LapackBand content | 197 |
| 8.9 | The SUNLinearSolver_KLU implementation | 197 |

| | | |
|----------|--|------------|
| 8.9.1 | SUNLinearSolver_KLU description | 197 |
| 8.9.2 | SUNLinearSolver_KLU functions | 198 |
| 8.9.3 | SUNLinearSolver_KLU Fortran interfaces | 200 |
| 8.9.4 | SUNLinearSolver_KLU content | 202 |
| 8.10 | The SUNLinearSolver_SuperLUMT implementation | 202 |
| 8.10.1 | SUNLinearSolver_SuperLUMT description | 203 |
| 8.10.2 | SUNLinearSolver_SuperLUMT functions | 203 |
| 8.10.3 | SUNLinearSolver_SuperLUMT Fortran interfaces | 205 |
| 8.10.4 | SUNLinearSolver_SuperLUMT content | 206 |
| 8.11 | The SUNLinearSolver_SPGMR implementation | 207 |
| 8.11.1 | SUNLinearSolver_SPGMR description | 207 |
| 8.11.2 | SUNLinearSolver_SPGMR functions | 207 |
| 8.11.3 | SUNLinearSolver_SPGMR Fortran interfaces | 209 |
| 8.11.4 | SUNLinearSolver_SPGMR content | 212 |
| 8.12 | The SUNLinearSolver_SPCGMR implementation | 213 |
| 8.12.1 | SUNLinearSolver_SPCGMR description | 213 |
| 8.12.2 | SUNLinearSolver_SPCGMR functions | 214 |
| 8.12.3 | SUNLinearSolver_SPCGMR Fortran interfaces | 216 |
| 8.12.4 | SUNLinearSolver_SPCGMR content | 218 |
| 8.13 | The SUNLinearSolver_SPCGMR implementation | 220 |
| 8.13.1 | SUNLinearSolver_SPCGMR description | 220 |
| 8.13.2 | SUNLinearSolver_SPCGMR functions | 220 |
| 8.13.3 | SUNLinearSolver_SPCGMR Fortran interfaces | 222 |
| 8.13.4 | SUNLinearSolver_SPCGMR content | 224 |
| 8.14 | The SUNLinearSolver_SPTFQMR implementation | 225 |
| 8.14.1 | SUNLinearSolver_SPTFQMR description | 225 |
| 8.14.2 | SUNLinearSolver_SPTFQMR functions | 226 |
| 8.14.3 | SUNLinearSolver_SPTFQMR Fortran interfaces | 227 |
| 8.14.4 | SUNLinearSolver_SPTFQMR content | 229 |
| 8.15 | The SUNLinearSolver_PCG implementation | 230 |
| 8.15.1 | SUNLinearSolver_PCG description | 231 |
| 8.15.2 | SUNLinearSolver_PCG functions | 232 |
| 8.15.3 | SUNLinearSolver_PCG Fortran interfaces | 233 |
| 8.15.4 | SUNLinearSolver_PCG content | 235 |
| 8.16 | SUNLinearSolver Examples | 236 |
| 9 | Description of the SUNNonlinearSolver module | 239 |
| 9.1 | The SUNNonlinearSolver API | 239 |
| 9.1.1 | SUNNonlinearSolver core functions | 239 |
| 9.1.2 | SUNNonlinearSolver set functions | 241 |
| 9.1.3 | SUNNonlinearSolver get functions | 242 |
| 9.1.4 | Functions provided by SUNDIALS integrators | 243 |
| 9.1.5 | SUNNonlinearSolver return codes | 245 |
| 9.1.6 | The generic SUNNonlinearSolver module | 245 |
| 9.1.7 | Usage with sensitivity enabled integrators | 246 |
| 9.1.8 | Implementing a Custom SUNNonlinearSolver Module | 248 |
| 9.2 | The SUNNonlinearSolver_Newton implementation | 248 |
| 9.2.1 | SUNNonlinearSolver_Newton description | 248 |
| 9.2.2 | SUNNonlinearSolver_Newton functions | 249 |
| 9.2.3 | SUNNonlinearSolver_Newton Fortran interfaces | 250 |
| 9.2.4 | SUNNonlinearSolver_Newton content | 251 |
| 9.3 | The SUNNonlinearSolver_FixedPoint implementation | 251 |
| 9.3.1 | SUNNonlinearSolver_FixedPoint description | 251 |
| 9.3.2 | SUNNonlinearSolver_FixedPoint functions | 252 |

| | | |
|----------|--|------------|
| 9.3.3 | SUNNonlinearSolver_FixedPoint Fortran interfaces | 253 |
| 9.3.4 | SUNNonlinearSolver_FixedPoint content | 254 |
| A | SUNDIALS Package Installation Procedure | 257 |
| A.1 | CMake-based installation | 258 |
| A.1.1 | Configuring, building, and installing on Unix-like systems | 258 |
| A.1.2 | Configuration options (Unix/Linux) | 260 |
| A.1.3 | Configuration examples | 267 |
| A.1.4 | Working with external Libraries | 267 |
| A.1.5 | Testing the build and installation | 269 |
| A.2 | Building and Running Examples | 270 |
| A.3 | Configuring, building, and installing on Windows | 270 |
| A.4 | Installed libraries and exported header files | 270 |
| B | IDA Constants | 277 |
| B.1 | IDA input constants | 277 |
| B.2 | IDA output constants | 277 |
| | Bibliography | 279 |
| | Index | 281 |

List of Tables

| | | |
|-----|--|-----|
| 4.1 | SUNDIALS linear solver interfaces and vector implementations that can be used for each. | 31 |
| 4.2 | Optional inputs for IDA and IDALS | 40 |
| 4.3 | Optional outputs from IDA and IDALS | 53 |
| 5.1 | Keys for setting FIDA optional inputs | 90 |
| 5.2 | Description of the FIDA optional output arrays IOUT and ROUT | 91 |
| 6.1 | Vector Identifications associated with vector kernels supplied with SUNDIALS. | 99 |
| 6.2 | Description of the NVECTOR operations | 100 |
| 6.3 | Description of the NVECTOR fused operations | 103 |
| 6.4 | Description of the NVECTOR vector array operations | 104 |
| 6.5 | List of vector functions usage by IDA code modules | 107 |
| 7.1 | Identifiers associated with matrix kernels supplied with SUNDIALS. | 154 |
| 7.2 | Description of the SUNMatrix operations | 154 |
| 7.3 | SUNDIALS matrix interfaces and vector implementations that can be used for each. . . | 155 |
| 7.4 | List of matrix functions usage by IDA code modules | 156 |
| 8.1 | Description of the SUNLinearSolver error codes | 182 |
| 8.2 | SUNDIALS matrix-based linear solvers and matrix implementations that can be used for each. | 183 |
| 8.3 | List of linear solver function usage in the IDALS interface | 186 |
| 9.1 | Description of the SUNNonlinearSolver return codes | 245 |
| A.1 | SUNDIALS libraries and header files | 272 |

List of Figures

| | | |
|-----|--|-----|
| 3.1 | High-level diagram of the SUNDIALS suite | 20 |
| 3.2 | Organization of the SUNDIALS suite | 21 |
| 3.3 | Overall structure diagram of the IDA package | 22 |
| 7.1 | Diagram of the storage for a SUNMATRIX_BAND object | 161 |
| 7.2 | Diagram of the storage for a compressed-sparse-column matrix | 168 |
| A.1 | Initial <i>ccmake</i> configuration screen | 259 |
| A.2 | Changing the <i>instdir</i> | 260 |

Chapter 1

Introduction

IDA is part of a software family called SUNDIALS: SUite of Nonlinear and Differential/ALgebraic equation Solvers [23]. This suite consists of CVODE, ARKODE, KINSOL, and IDA, and variants of these with sensitivity analysis capabilities, CVODES and IDAS.

IDA is a general purpose solver for the initial value problem (IVP) for systems of differential-algebraic equations (DAEs). The name IDA stands for Implicit Differential-Algebraic solver. IDA is based on DASPK [7, 8], but is written in ANSI-standard C rather than FORTRAN77. Its most notable features are that, (1) in the solution of the underlying nonlinear system at each time step, it offers a choice of Newton/direct methods and a choice of Inexact Newton/Krylov (iterative) methods; and (2) it is written in a *data-independent* manner in that it acts on generic vectors and matrices without any assumptions on the underlying organization of the data. Thus IDA shares significant modules previously written within CASC at LLNL to support the ordinary differential equation (ODE) solvers CVODE [24, 13] and PVODE [11, 12], and also the nonlinear system solver KINSOL [14].

At present, IDA may utilize a variety of Krylov methods provided in SUNDIALS that can be used in conjunction with Newton iteration: these include the GMRES (Generalized Minimal RESidual) [33], FGMRES (Flexible Generalized Minimum RESidual) [32], Bi-CGStab (Bi-Conjugate Gradient Stabilized) [34], TFQMR (Transpose-Free Quasi-Minimal Residual) [20], and PCG (Preconditioned Conjugate Gradient) [21] linear iterative methods. As Krylov methods, these require little matrix storage for solving the Newton equations as compared to direct methods. However, the algorithms allow for a user-supplied preconditioner matrix, and, for most problems, preconditioning is essential for an efficient solution.

For very large DAE systems, the Krylov methods are preferable over direct linear solver methods, and are often the only feasible choice. Among the Krylov methods in SUNDIALS, we recommend GMRES as the best overall choice. However, users are encouraged to compare all options, especially if encountering convergence failures with GMRES. Bi-CGStab and TFQMR have an advantage in storage requirements, in that the number of workspace vectors they require is fixed, while that number for GMRES depends on the desired Krylov subspace size. FGMRES has an advantage in that it is designed to support preconditioners that vary between iterations (e.g. iterative methods). PCG exhibits rapid convergence and minimal workspace vectors, but only works for symmetric linear systems.

There are several motivations for choosing the C language for IDA. First, a general movement away from FORTRAN and toward C in scientific computing was apparent. Second, the pointer, structure, and dynamic memory allocation features in C are extremely useful in software of this complexity, with the great variety of method options offered. Finally, we prefer C over C++ for IDA because of the wider availability of C compilers, the potentially greater efficiency of C, and the greater ease of interfacing the solver to applications written in extended FORTRAN.

1.1 Changes from previous versions

Changes in v4.0.2

Moved definitions of DLS and SPILS backwards compatibility functions to a source file. The symbols are now included in the IDA library, `libsundials_ida`.

Changes in v4.0.1

No changes were made in this release.

Changes in v4.0.0

IDA's previous direct and iterative linear solver interfaces, IDADLS and IDASPILS, have been merged into a single unified linear solver interface, IDALS, to support any valid SUNLINSOL module. This includes the "DIRECT" and "ITERATIVE" types as well as the new "MATRIX_ITERATIVE" type. Details regarding how IDALS utilizes linear solvers of each type as well as discussion regarding intended use cases for user-supplied SUNLINSOL implementations are included in Chapter 8. All IDA example programs and the standalone linear solver examples have been updated to use the unified linear solver interface.

The unified interface for the new IDALS module is very similar to the previous IDADLS and IDASPILS interfaces. To minimize challenges in user migration to the new names, the previous C and FORTRAN routine names may still be used; these will be deprecated in future releases, so we recommend that users migrate to the new names soon. Additionally, we note that FORTRAN users, however, may need to enlarge their `iout` array of optional integer outputs, and update the indices that they query for certain linear-solver-related statistics.

The names of all constructor routines for SUNDIALS-provided SUNLINSOL implementations have been updated to follow the naming convention `SUNLinSol.*` where `*` is the name of the linear solver. The new names are `SUNLinSol_Band`, `SUNLinSol_Dense`, `SUNLinSol_KLU`, `SUNLinSol_LapackBand`, `SUNLinSol_LapackDense`, `SUNLinSol_PCG`, `SUNLinSol_SPBCGS`, `SUNLinSol_SPFQMR`, `SUNLinSol_SPGMR`, `SUNLinSol_SPTFQMR`, and `SUNLinSol_SuperLUMT`. Solver-specific "set" routine names have been similarly standardized. To minimize challenges in user migration to the new names, the previous routine names may still be used; these will be deprecated in future releases, so we recommend that users migrate to the new names soon. All IDA example programs and the standalone linear solver examples have been updated to use the new naming convention.

The `SUNBandMatrix` constructor has been simplified to remove the storage upper bandwidth argument.

SUNDIALS integrators have been updated to utilize generic nonlinear solver modules defined through the `SUNNONLINSOL` API. This API will ease the addition of new nonlinear solver options and allow for external or user-supplied nonlinear solvers. The `SUNNONLINSOL` API and SUNDIALS provided modules are described in Chapter 9 and follow the same object oriented design and implementation used by the `NVECTOR`, `SUNMATRIX`, and `SUNLINSOL` modules. Currently two `SUNNONLINSOL` implementations are provided, `SUNNONLINSOL_NEWTON` and `SUNNONLINSOL_FIXEDPOINT`. These replicate the previous integrator specific implementations of a Newton iteration and a fixed-point iteration (previously referred to as a functional iteration), respectively. Note the `SUNNONLINSOL_FIXEDPOINT` module can optionally utilize Anderson's method to accelerate convergence. Example programs using each of these nonlinear solver modules in a standalone manner have been added and all IDA example programs have been updated to use generic `SUNNONLINSOL` modules.

By default IDA uses the `SUNNONLINSOL_NEWTON` module. Since IDA previously only used an internal implementation of a Newton iteration no changes are required to user programs and functions for setting the nonlinear solver options (e.g., `IDASetMaxNonlinIters`) or getting nonlinear solver statistics (e.g., `IDAGetNumNonlinSolvIters`) remain unchanged and internally call generic `SUNNONLINSOL` functions as needed. While SUNDIALS includes a fixed-point nonlinear solver module, it is not currently supported in IDA. For details on attaching a user-supplied nonlinear solver to IDA see Chapter 4.

Additionally, the example program `idaRoberts_dns.c` explicitly creates and attaches a `SUNNONLINSOL_NEWTON` object to demonstrate the process of creating and attaching a nonlinear solver module (note this is not necessary in general as IDA uses the `SUNNONLINSOL_NEWTON` module by default).

Three fused vector operations and seven vector array operations have been added to the `NVECTOR` API. These *optional* operations are disabled by default and may be activated by calling vector specific routines after creating an `NVECTOR` (see Chapter 6 for more details). The new operations are intended to increase data reuse in vector operations, reduce parallel communication on distributed memory systems, and lower the number of kernel launches on systems with accelerators. The fused operations are `N_VLinearCombination`, `N_VScaleAddMulti`, and `N_VDotProdMulti` and the vector array operations are `N_VLinearCombinationVectorArray`, `N_VScaleVectorArray`, `N_VConstVectorArray`, `N_VWrmsNormVectorArray`, `N_VWrmsNormMaskVectorArray`, `N_VScaleAddMultiVectorArray`, and `N_VLinearCombinationVectorArray`. If an `NVECTOR` implementation defines any of these operations as `NULL`, then standard `NVECTOR` operations will automatically be called as necessary to complete the computation.

Multiple updates to `NVECTOR_CUDA` were made:

- Changed `N_VGetLength_Cuda` to return the global vector length instead of the local vector length.
- Added `N_VGetLocalLength_Cuda` to return the local vector length.
- Added `N_VGetMPIComm_Cuda` to return the MPI communicator used.
- Removed the accessor functions in the namespace `suncudavec`.
- Changed the `N_VMake_Cuda` function to take a host data pointer and a device data pointer instead of an `N_VectorContent_Cuda` object.
- Added the ability to set the `cudaStream_t` used for execution of the `NVECTOR_CUDA` kernels. See the function `N_VSetCudaStreams_Cuda`.
- Added `N_VNewManaged_Cuda`, `N_VMakeManaged_Cuda`, and `N_VIsManagedMemory_Cuda` functions to accommodate using managed memory with the `NVECTOR_CUDA`.

Multiple changes to `NVECTOR_RAJA` were made:

- Changed `N_VGetLength_Raja` to return the global vector length instead of the local vector length.
- Added `N_VGetLocalLength_Raja` to return the local vector length.
- Added `N_VGetMPIComm_Raja` to return the MPI communicator used.
- Removed the accessor functions in the namespace `suncudavec`.

A new `NVECTOR` implementation for leveraging OpenMP 4.5+ device offloading has been added, `NVECTOR_OPENMPDEV`. See §6.10 for more details.

Changes in v3.2.1

The changes in this minor release include the following:

- Fixed a bug in the `CUDA` `NVECTOR` where the `N_VInvTest` operation could write beyond the allocated vector data.
- Fixed library installation path for multiarch systems. This fix changes the default library installation path to `CMAKE_INSTALL_PREFIX/CMAKE_INSTALL_LIBDIR` from `CMAKE_INSTALL_PREFIX/lib`. `CMAKE_INSTALL_LIBDIR` is automatically set, but is available as a CMake option that can be modified.

Changes in v3.2.0

Fixed a problem with setting `sunindextype` which would occur with some compilers (e.g. `armclang`) that did not define `__STDC_VERSION__`.

Added hybrid MPI/CUDA and MPI/RAJA vectors to allow use of more than one MPI rank when using a GPU system. The vectors assume one GPU device per MPI rank.

Changed the name of the RAJA NVECTOR library to `libsundials_nveccudaraja.lib` from `libsundials_nvecraja.lib` to better reflect that we only support CUDA as a backend for RAJA currently.

Several changes were made to the build system:

- CMake 3.1.3 is now the minimum required CMake version.
- Deprecate the behavior of the `SUNDIALS_INDEX_TYPE` CMake option and added the `SUNDIALS_INDEX_SIZE` CMake option to select the `sunindextype` integer size.
- The native CMake FindMPI module is now used to locate an MPI installation.
- If MPI is enabled and MPI compiler wrappers are not set, the build system will check if `CMAKE_<language>_COMPILER` can compile MPI programs before trying to locate and use an MPI installation.
- The previous options for setting MPI compiler wrappers and the executable for running MPI programs have been deprecated. The new options that align with those used in native CMake FindMPI module are `MPI_C_COMPILER`, `MPI_CXX_COMPILER`, `MPI_Fortran_COMPILER`, and `MPIEXEC_EXECUTABLE`.
- When a Fortran name-mangling scheme is needed (e.g., `LAPACK_ENABLE` is `ON`) the build system will infer the scheme from the Fortran compiler. If a Fortran compiler is not available or the inferred or default scheme needs to be overridden, the advanced options `SUNDIALS_F77_FUNC_CASE` and `SUNDIALS_F77_FUNC_UNDERSCORES` can be used to manually set the name-mangling scheme and bypass trying to infer the scheme.
- Parts of the main `CMakeLists.txt` file were moved to new files in the `src` and `example` directories to make the CMake configuration file structure more modular.

Changes in v3.1.2

The changes in this minor release include the following:

- Updated the minimum required version of CMake to 2.8.12 and enabled using `rpath` by default to locate shared libraries on OSX.
- Fixed Windows specific problem where `sunindextype` was not correctly defined when using 64-bit integers for the `SUNDIALS` index type. On Windows `sunindextype` is now defined as the MSVC basic type `__int64`.
- Added sparse SUNMatrix “Reallocate” routine to allow specification of the nonzero storage.
- Updated the KLU SUNLinearSolver module to set constants for the two reinitialization types, and fixed a bug in the full reinitialization approach where the sparse SUNMatrix pointer would go out of scope on some architectures.
- Updated the “ScaleAdd” and “ScaleAddI” implementations in the sparse SUNMatrix module to more optimally handle the case where the target matrix contained sufficient storage for the sum, but had the wrong sparsity pattern. The sum now occurs in-place, by performing the sum

backwards in the existing storage. However, it is still more efficient if the user-supplied Jacobian routine allocates storage for the sum $I + \gamma J$ manually (with zero entries if needed).

- Changed the LICENSE install path to `instdir/include/sundials`.

Changes in v3.1.1

The changes in this minor release include the following:

- Fixed a potential memory leak in the SPGMR and SPFGMR linear solvers: if “Initialize” was called multiple times then the solver memory was reallocated (without being freed).
- Updated KLU SUNLINSOL module to use a `typedef` for the precision-specific solve function to be used (to avoid compiler warnings).
- Added missing typecasts for some `(void*)` pointers (again, to avoid compiler warnings).
- Bugfix in `sunmatrix_sparse.c` where we had used `int` instead of `sunindextype` in one location.
- Added missing `#include <stdio.h>` in NVECTOR and SUNMATRIX header files.
- Added missing prototype for `IDASpilsGetNumJTSetupEvals`.
- Fixed an indexing bug in the CUDA NVECTOR implementation of `N_VWrmsNormMask` and revised the RAJA NVECTOR implementation of `N_VWrmsNormMask` to work with mask arrays using values other than zero or one. Replaced `double` with `realtype` in the RAJA vector test functions.
- Fixed compilation issue with GCC 7.3.0 and Fortran programs that do not require a SUNMATRIX module (e.g., iterative linear solvers).

In addition to the changes above, minor corrections were also made to the example programs, build system, and user documentation.

Changes in v3.1.0

Added NVECTOR print functions that write vector data to a specified file (e.g., `N_VPrintFile_Serial`).

Added `make test` and `make test_install` options to the build system for testing SUNDIALS after building with `make` and installing with `make install` respectively.

Changes in v3.0.0

All interfaces to matrix structures and linear solvers have been reworked, and all example programs have been updated. The goal of the redesign of these interfaces was to provide more encapsulation and to ease interfacing of custom linear solvers and interoperability with linear solver libraries. Specific changes include:

- Added generic SUNMATRIX module with three provided implementations: dense, banded and sparse. These replicate previous SUNDIALS Dls and SlS matrix structures in a single object-oriented API.
- Added example problems demonstrating use of generic SUNMATRIX modules.
- Added generic `SUNLinearSolver` module with eleven provided implementations: SUNDIALS native dense, SUNDIALS native banded, LAPACK dense, LAPACK band, KLU, SuperLU_MT, SPGMR, SPBCGS, SPTFQMR, SPFGMR, and PCG. These replicate previous SUNDIALS generic linear solvers in a single object-oriented API.
- Added example problems demonstrating use of generic `SUNLinearSolver` modules.

- Expanded package-provided direct linear solver (Dls) interfaces and scaled, preconditioned, iterative linear solver (Spils) interfaces to utilize generic `SUNMATRIX` and `SUNLinearSolver` objects.
- Removed package-specific, linear solver-specific, solver modules (e.g. `CVDENSE`, `KINBAND`, `IDAKLU`, `ARKSPGMR`) since their functionality is entirely replicated by the generic Dls/Spils interfaces and `SUNLinearSolver`/`SUNMATRIX` modules. The exception is `CVDIAG`, a diagonal approximate Jacobian solver available to `CVODE` and `CVODES`.
- Converted all `SUNDIALS` example problems and files to utilize the new generic `SUNMATRIX` and `SUNLinearSolver` objects, along with updated Dls and Spils linear solver interfaces.
- Added Spils interface routines to `ARKODE`, `CVODE`, `CVODES`, `IDA`, and `IDAS` to allow specification of a user-provided "JTSetup" routine. This change supports users who wish to set up data structures for the user-provided Jacobian-times-vector ("JTTimes") routine, and where the cost of one JTSetup setup per Newton iteration can be amortized between multiple JTTimes calls.

Two additional `NVECTOR` implementations were added – one for `CUDA` and one for `RAJA` vectors. These vectors are supplied to provide very basic support for running on GPU architectures. Users are advised that these vectors both move all data to the GPU device upon construction, and speedup will only be realized if the user also conducts the right-hand-side function evaluation on the device. In addition, these vectors assume the problem fits on one GPU. Further information about `RAJA`, users are referred to the web site, <https://software.llnl.gov/RAJA/>. These additions are accompanied by additions to various interface functions and to user documentation.

All indices for data structures were updated to a new `sunindextype` that can be configured to be a 32- or 64-bit integer data index type. `sunindextype` is defined to be `int32_t` or `int64_t` when portable types are supported, otherwise it is defined as `int` or `long int`. The Fortran interfaces continue to use `long int` for indices, except for their sparse matrix interface that now uses the new `sunindextype`. This new flexible capability for index types includes interfaces to `PETSc`, `hypre`, `SuperLU_MT`, and `KLU` with either 32-bit or 64-bit capabilities depending how the user configures `SUNDIALS`.

To avoid potential namespace conflicts, the macros defining `booleantype` values `TRUE` and `FALSE` have been changed to `SUNTRUE` and `SUNFALSE` respectively.

Temporary vectors were removed from preconditioner setup and solve routines for all packages. It is assumed that all necessary data for user-provided preconditioner operations will be allocated and stored in user-provided data structures.

The file `include/sundials_fconfig.h` was added. This file contains `SUNDIALS` type information for use in Fortran programs.

The build system was expanded to support many of the `xSDK`-compliant keys. The `xSDK` is a movement in scientific software to provide a foundation for the rapid and efficient production of high-quality, sustainable extreme-scale scientific applications. More information can be found at, <https://xsdk.info>.

Added functions `SUNDIALSGetVersion` and `SUNDIALSGetVersionNumber` to get `SUNDIALS` release version information at runtime.

In addition, numerous changes were made to the build system. These include the addition of separate `BLAS_ENABLE` and `BLAS_LIBRARIES` CMake variables, additional error checking during CMake configuration, minor bug fixes, and renaming CMake options to enable/disable examples for greater clarity and an added option to enable/disable Fortran 77 examples. These changes included changing `EXAMPLES_ENABLE` to `EXAMPLES_ENABLE_C`, changing `CXX_ENABLE` to `EXAMPLES_ENABLE_CXX`, changing `F90_ENABLE` to `EXAMPLES_ENABLE_F90`, and adding an `EXAMPLES_ENABLE_F77` option.

A bug fix was done to add a missing prototype for `IDASSetMaxBacksIC` in `ida.h`.

Corrections and additions were made to the examples, to installation-related files, and to the user documentation.

Changes in v2.9.0

Two additional NVECTOR implementations were added – one for Hypre (parallel) ParVector vectors, and one for PETSc vectors. These additions are accompanied by additions to various interface functions and to user documentation.

Each NVECTOR module now includes a function, `NVGetVectorID`, that returns the NVECTOR module name.

An optional input function was added to set a maximum number of linesearch backtracks in the initial condition calculation. Also, corrections were made to three Fortran interface functions.

For each linear solver, the various solver performance counters are now initialized to 0 in both the solver specification function and in solver `linit` function. This ensures that these solver counters are initialized upon linear solver instantiation as well as at the beginning of the problem solution.

A memory leak was fixed in the banded preconditioner interface. In addition, updates were done to return integers from linear solver and preconditioner 'free' functions.

The Krylov linear solver Bi-CGstab was enhanced by removing a redundant dot product. Various additions and corrections were made to the interfaces to the sparse solvers KLU and SuperLU_MT, including support for CSR format when using KLU.

New examples were added for use of the OpenMP vector.

Minor corrections and additions were made to the IDA solver, to the Fortran interfaces, to the examples, to installation-related files, and to the user documentation.

Changes in v2.8.0

Two major additions were made to the linear system solvers that are available for use with the IDA solver. First, in the serial case, an interface to the sparse direct solver KLU was added. Second, an interface to SuperLU_MT, the multi-threaded version of SuperLU, was added as a thread-parallel sparse direct solver option, to be used with the serial version of the NVECTOR module. As part of these additions, a sparse matrix (CSC format) structure was added to IDA.

Otherwise, only relatively minor modifications were made to IDA:

In `IDARootfind`, a minor bug was corrected, where the input array `rootdir` was ignored, and a line was added to break out of root-search loop if the initial interval size is below the tolerance `ttol`.

In `IDALapackBand`, the line `smu = MIN(N-1,mu+ml)` was changed to `smu = mu + ml` to correct an illegal input error for `DGBTRF/DGBTRS`.

A minor bug was fixed regarding the testing of the input `tstop` on the first call to `IDASolve`.

In order to avoid possible name conflicts, the mathematical macro and function names `MIN`, `MAX`, `SQR`, `RAbs`, `RSqrt`, `RExp`, `RPowerI`, and `RPowerR` were changed to `SUNMIN`, `SUNMAX`, `SUNSQR`, `SUNRabs`, `SUNRSqrt`, `SUNRexp`, `SRpowerI`, and `SUNRpowerR`, respectively. These names occur in both the solver and in various example programs.

In the FIDA optional input routines `FIDASETIIN`, `FIDASETRIN`, and `FIDASETVIN`, the optional fourth argument `key_length` was removed, with hardcoded key string lengths passed to all `strncmp` tests.

In all FIDA examples, integer declarations were revised so that those which must match a C type `long int` are declared `INTEGER*8`, and a comment was added about the type match. All other integer declarations are just `INTEGER`. Corresponding minor corrections were made to the user guide.

Two new NVECTOR modules have been added for thread-parallel computing environments — one for OpenMP, denoted `NVECTOR.OPENMP`, and one for Pthreads, denoted `NVECTOR.PTHREADS`.

With this version of SUNDIALS, support and documentation of the Autotools mode of installation is being dropped, in favor of the CMake mode, which is considered more widely portable.

Changes in v2.7.0

One significant design change was made with this release: The problem size and its relatives, bandwidth parameters, related internal indices, pivot arrays, and the optional output `lsflag` have all been changed from type `int` to type `long int`, except for the problem size and bandwidths in user

calls to routines specifying BLAS/LAPACK routines for the dense/band linear solvers. The function `NewIntArray` is replaced by a pair `NewIntArray/NewLintArray`, for `int` and `long int` arrays, respectively.

A large number of minor errors have been fixed. Among these are the following: After the solver memory is created, it is set to zero before being filled. To be consistent with IDAS, IDA uses the function `IDAGetDky` for optional output retrieval. In each linear solver interface function, the linear solver memory is freed on an error return, and the `**Free` function now includes a line setting to NULL the main memory pointer to the linear solver memory. A memory leak was fixed in two of the `IDASp***Free` functions. In the rootfinding functions `IDARcheck1`/`IDARcheck2`, when an exact zero is found, the array `glo` of g values at the left endpoint is adjusted, instead of shifting the t location `tlo` slightly. In the installation files, we modified the treatment of the macro `SUNDIALS_USE_GENERIC_MATH`, so that the parameter `GENERIC_MATH_LIB` is either defined (with no value) or not defined.

Changes in v2.6.0

Two new features were added in this release: (a) a new linear solver module, based on BLAS and LAPACK for both dense and banded matrices, and (b) option to specify which direction of zero-crossing is to be monitored while performing rootfinding.

The user interface has been further refined. Some of the API changes involve: (a) a reorganization of all linear solver modules into two families (besides the already present family of scaled preconditioned iterative linear solvers, the direct solvers, including the new LAPACK-based ones, were also organized into a *direct* family); (b) maintaining a single pointer to user data, optionally specified through a `Set`-type function; (c) a general streamlining of the band-block-diagonal preconditioner module distributed with the solver.

Changes in v2.5.0

The main changes in this release involve a rearrangement of the entire SUNDIALS source tree (see §3.1). At the user interface level, the main impact is in the mechanism of including SUNDIALS header files which must now include the relative path (e.g. `#include <cvode/cvode.h>`). Additional changes were made to the build system: all exported header files are now installed in separate subdirectories of the installation *include* directory.

A bug was fixed in the internal difference-quotient dense and banded Jacobian approximations, related to the estimation of the perturbation (which could have led to a failure of the linear solver when zero components with sufficiently small absolute tolerances were present).

The user interface to the consistent initial conditions calculations was modified. The `IDACalcIC` arguments `t0`, `yy0`, and `yp0` were removed and a new function, `IDAGetconsistentIC` is provided (see §4.5.5 and §4.5.10.3 for details).

The functions in the generic dense linear solver (`sundials_dense` and `sundials_smalldense`) were modified to work for rectangular $m \times n$ matrices ($m \leq n$), while the factorization and solution functions were renamed to `DenseGETRF`/`denGETRF` and `DenseGETRS`/`denGETRS`, respectively. The factorization and solution functions in the generic band linear solver were renamed `BandGBTRF` and `BandGBTRS`, respectively.

Changes in v2.4.0

FIDA, a FORTRAN-C interface module, was added (for details see Chapter 5).

IDASPCBG and IDASPTFQMR modules have been added to interface with the Scaled Preconditioned Bi-CGstab (SPBCGS) and Scaled Preconditioned Transpose-Free Quasi-Minimal Residual (SPTFQMR) linear solver modules, respectively (for details see Chapter 4). At the same time, function type names for Scaled Preconditioned Iterative Linear Solvers were added for the user-supplied Jacobian-times-vector and preconditioner setup and solve functions.

The rootfinding feature was added, whereby the roots of a set of given functions may be computed during the integration of the DAE system.

A user-callable routine was added to access the estimated local error vector.

The deallocation functions now take as arguments the address of the respective memory block pointer.

To reduce the possibility of conflicts, the names of all header files have been changed by adding unique prefixes (`ida_` and `sundials_`). When using the default installation procedure, the header files are exported under various subdirectories of the target `include` directory. For more details see [Appendix A](#).

Changes in v2.3.0

The user interface has been further refined. Several functions used for setting optional inputs were combined into a single one. An optional user-supplied routine for setting the error weight vector was added. Additionally, to resolve potential variable scope issues, all SUNDIALS solvers release user data right after its use. The build systems has been further improved to make it more robust.

Changes in v2.2.2

Minor corrections and improvements were made to the build system. A new chapter in the User Guide was added — with constants that appear in the user interface.

Changes in v2.2.1

The changes in this minor SUNDIALS release affect only the build system.

Changes in v2.2.0

The major changes from the previous version involve a redesign of the user interface across the entire SUNDIALS suite. We have eliminated the mechanism of providing optional inputs and extracting optional statistics from the solver through the `iopt` and `ropt` arrays. Instead, IDA now provides a set of routines (with prefix `IDASet`) to change the default values for various quantities controlling the solver and a set of extraction routines (with prefix `IDAGet`) to extract statistics after return from the main solver routine. Similarly, each linear solver module provides its own set of `Set`- and `Get`-type routines. For more details see [§4.5.8](#) and [§4.5.10](#).

Additionally, the interfaces to several user-supplied routines (such as those providing Jacobians and preconditioner information) were simplified by reducing the number of arguments. The same information that was previously accessible through such arguments can now be obtained through `Get`-type functions.

Installation of IDA (and all of SUNDIALS) has been completely redesigned and is now based on configure scripts.

1.2 Reading this User Guide

The structure of this document is as follows:

- In [Chapter 2](#), we give short descriptions of the numerical methods implemented by IDA for the solution of initial value problems for systems of DAEs, along with short descriptions of preconditioning ([§2.2](#)) and rootfinding ([§2.3](#)).
- The following chapter describes the structure of the SUNDIALS suite of solvers ([§3.1](#)) and the software organization of the IDA solver ([§3.2](#)).
- [Chapter 4](#) is the main usage document for IDA for C applications. It includes a complete description of the user interface for the integration of DAE initial value problems.

- In Chapter 5, we describe FIDA, an interface module for the use of IDA with FORTRAN applications.
- Chapter 6 gives a brief overview of the generic NVECTOR module shared among the various components of SUNDIALS, as well as details on the NVECTOR implementations provided with SUNDIALS.
- Chapter 7 gives a brief overview of the generic SUNMATRIX module shared among the various components of SUNDIALS, and details on the SUNMATRIX implementations provided with SUNDIALS: a dense implementation (§7.2), a banded implementation (§7.3) and a sparse implementation (§7.4).
- Chapter 8 gives a brief overview of the generic SUNLINSOL module shared among the various components of SUNDIALS. This chapter contains details on the SUNLINSOL implementations provided with SUNDIALS. The chapter also contains details on the SUNLINSOL implementations provided with SUNDIALS that interface with external linear solver libraries.
- Chapter 9 describes the SUNNONLINSOL API and nonlinear solver implementations shared among the various components of SUNDIALS.
- Finally, in the appendices, we provide detailed instructions for the installation of IDA, within the structure of SUNDIALS (Appendix A), as well as a list of all the constants used for input to and output from IDA functions (Appendix B).

Finally, the reader should be aware of the following notational conventions in this user guide: program listings and identifiers (such as `IDAInit`) within textual explanations appear in typewriter type style; fields in C structures (such as *content*) appear in italics; and packages or modules, such as IDADLS, are written in all capitals. Usage and installation instructions that constitute important warnings are marked with a triangular symbol in the margin.



Acknowledgments. We wish to acknowledge the contributions to previous versions of the IDA code and user guide of Allan G. Taylor.

1.3 SUNDIALS Release License

All SUNDIALS packages are released open source, under the BSD 3-Clause license. The only requirements of the license are preservation of copyright and a standard disclaimer of liability. The full text of the license and an additional notice are provided below and may also be found in the LICENSE and NOTICE files provided with all SUNDIALS packages.



If you are using SUNDIALS with any third party libraries linked in (e.g., LAPACK, KLU, SuperLU_MT, PETSc, or *hypre*), be sure to review the respective license of the package as that license may have more restrictive terms than the SUNDIALS license. For example, if someone builds SUNDIALS with a statically linked KLU, the build is subject to terms of the LGPL license (which is what KLU is released with) and *not* the SUNDIALS BSD license anymore.

1.3.1 BSD 3-Clause License

Copyright (c) 2002-2019, Lawrence Livermore National Security and Southern Methodist University. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

* Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

1.3.2 Additional Notice

This work was produced under the auspices of the U.S. Department of Energy by Lawrence Livermore National Laboratory under Contract DE-AC52-07NA27344.

This work was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor Lawrence Livermore National Security, LLC, nor any of their employees makes any warranty, expressed or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights.

Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or Lawrence Livermore National Security, LLC.

The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or Lawrence Livermore National Security, LLC, and shall not be used for advertising or product endorsement purposes.

1.3.3 SUNDIALS Release Numbers

LLNL-CODE-667205 (ARKODE)
UCRL-CODE-155951 (CVODE)
UCRL-CODE-155950 (CVODES)
UCRL-CODE-155952 (IDA)
UCRL-CODE-237203 (IDAS)
LLNL-CODE-665877 (KINSOL)

Chapter 2

Mathematical Considerations

IDA solves the initial-value problem (IVP) for a DAE system of the general form

$$F(t, y, \dot{y}) = 0, \quad y(t_0) = y_0, \quad \dot{y}(t_0) = \dot{y}_0, \quad (2.1)$$

where y , \dot{y} , and F are vectors in \mathbf{R}^N , t is the independent variable, $\dot{y} = dy/dt$, and initial values y_0 , \dot{y}_0 are given. (Often t is time, but it certainly need not be.)

2.1 IVP solution

Prior to integrating a DAE initial-value problem, an important requirement is that the pair of vectors y_0 and \dot{y}_0 are both initialized to satisfy the DAE residual $F(t_0, y_0, \dot{y}_0) = 0$. For a class of problems that includes so-called semi-explicit index-one systems, IDA provides a routine that computes consistent initial conditions from a user's initial guess [8]. For this, the user must identify sub-vectors of y (not necessarily contiguous), denoted y_d and y_a , which are its differential and algebraic parts, respectively, such that F depends on \dot{y}_d but not on any components of \dot{y}_a . The assumption that the system is “index one” means that for a given t and y_d , the system $F(t, y, \dot{y}) = 0$ defines y_a uniquely. In this case, a solver within IDA computes y_a and \dot{y}_d at $t = t_0$, given y_d and an initial guess for y_a . A second available option with this solver also computes all of $y(t_0)$ given $\dot{y}(t_0)$; this is intended mainly for quasi-steady-state problems, where $\dot{y}(t_0) = 0$ is given. In both cases, IDA solves the system $F(t_0, y_0, \dot{y}_0) = 0$ for the unknown components of y_0 and \dot{y}_0 , using Newton iteration augmented with a line search global strategy. In doing this, it makes use of the existing machinery that is to be used for solving the linear systems during the integration, in combination with certain tricks involving the step size (which is set artificially for this calculation). For problems that do not fall into either of these categories, the user is responsible for passing consistent values, or risks failure in the numerical integration.

The integration method used in IDA is the variable-order, variable-coefficient BDF (Backward Differentiation Formula), in fixed-leading-coefficient form [4]. The method order ranges from 1 to 5, with the BDF of order q given by the multistep formula

$$\sum_{i=0}^q \alpha_{n,i} y_{n-i} = h_n \dot{y}_n, \quad (2.2)$$

where y_n and \dot{y}_n are the computed approximations to $y(t_n)$ and $\dot{y}(t_n)$, respectively, and the step size is $h_n = t_n - t_{n-1}$. The coefficients $\alpha_{n,i}$ are uniquely determined by the order q , and the history of the step sizes. The application of the BDF (2.2) to the DAE system (2.1) results in a nonlinear algebraic system to be solved at each step:

$$G(y_n) \equiv F \left(t_n, y_n, h_n^{-1} \sum_{i=0}^q \alpha_{n,i} y_{n-i} \right) = 0. \quad (2.3)$$

By default IDA solves (2.3) with a Newton iteration but IDA also allows for user-defined nonlinear solvers (see Chapter 9). Each Newton iteration requires the solution of a linear system of the form

$$J[y_{n(m+1)} - y_{n(m)}] = -G(y_{n(m)}), \quad (2.4)$$

where $y_{n(m)}$ is the m -th approximation to y_n . Here J is some approximation to the system Jacobian

$$J = \frac{\partial G}{\partial y} = \frac{\partial F}{\partial y} + \alpha \frac{\partial F}{\partial \dot{y}}, \quad (2.5)$$

where $\alpha = \alpha_{n,0}/h_n$. The scalar α changes whenever the step size or method order changes.

For the solution of the linear systems within the Newton iteration, IDA provides several choices, including the option of a user-supplied linear solver module (see Chapter 8). The linear solver modules distributed with SUNDIALS are organized in two families, a *direct* family comprising direct linear solvers for dense, banded, or sparse matrices and a *spils* family comprising scaled preconditioned iterative (Krylov) linear solvers. The methods offered through these modules are as follows:

- dense direct solvers, using either an internal implementation or a BLAS/LAPACK implementation (serial or threaded vector modules only),
- band direct solvers, using either an internal implementation or a BLAS/LAPACK implementation (serial or threaded vector modules only),
- sparse direct solver interfaces, using either the KLU sparse solver library [15, 1], or the thread-enabled SuperLU_MT sparse solver library [29, 17, 2] (serial or threaded vector modules only) [Note that users will need to download and install the KLU or SUPERLUMT packages independent of IDA],
- SPGMR, a scaled preconditioned GMRES (Generalized Minimal Residual method) solver without restarts,
- SPFGMR, a scaled preconditioned FGMRES (Flexible Generalized Minimal Residual method) solver,
- SPBCGS, a scaled preconditioned Bi-CGStab (Bi-Conjugate Gradient Stable method) solver,
- SPTFQMR, a scaled preconditioned TFQMR (Transpose-Free Quasi-Minimal Residual method) solver, or
- PCG, a scaled preconditioned CG (Conjugate Gradient method) solver.

For large stiff systems, where direct methods are not feasible, the combination of a BDF integrator and a preconditioned Krylov method yields a powerful tool because it combines established methods for stiff integration, nonlinear iteration, and Krylov (linear) iteration with a problem-specific treatment of the dominant source of stiffness, in the form of the user-supplied preconditioner matrix [6]. For the *spils* linear solvers with IDA, preconditioning is allowed only on the left (see §2.2). Note that the dense, band, and sparse direct linear solvers can only be used with serial and threaded vector representations.

In the process of controlling errors at various levels, IDA uses a weighted root-mean-square norm, denoted $\|\cdot\|_{\text{WRMS}}$, for all error-like quantities. The multiplicative weights used are based on the current solution and on the relative and absolute tolerances input by the user, namely

$$W_i = 1/[\text{RTOL} \cdot |y_i| + \text{ATOL}_i]. \quad (2.6)$$

Because $1/W_i$ represents a tolerance in the component y_i , a vector whose norm is 1 is regarded as “small.” For brevity, we will usually drop the subscript WRMS on norms in what follows.

In the case of a matrix-based linear solver, the default Newton iteration is a Modified Newton iteration, in that the Jacobian J is fixed (and usually out of date) throughout the nonlinear iterations, with a coefficient $\bar{\alpha}$ in place of α in J . However, in the case that a matrix-free iterative linear solver is

used, the default Newton iteration is an Inexact Newton iteration, in which J is applied in a matrix-free manner, with matrix-vector products Jv obtained by either difference quotients or a user-supplied routine. In this case, the linear residual $J\Delta y + G$ is nonzero but controlled. With the default Newton iteration, the matrix J and preconditioner matrix P are updated as infrequently as possible to balance the high costs of matrix operations against other costs. Specifically, this matrix update occurs when:

- starting the problem,
- the value $\bar{\alpha}$ at the last update is such that $\alpha/\bar{\alpha} < 3/5$ or $\alpha/\bar{\alpha} > 5/3$, or
- a non-fatal convergence failure occurred with an out-of-date J or P .

The above strategy balances the high cost of frequent matrix evaluations and preprocessing with the slow convergence due to infrequent updates. To reduce storage costs on an update, Jacobian information is always reevaluated from scratch.

The default stopping test for nonlinear solver iterations in IDA ensures that the iteration error $y_n - y_{n(m)}$ is small relative to y itself. For this, we estimate the linear convergence rate at all iterations $m > 1$ as

$$R = \left(\frac{\delta_m}{\delta_1} \right)^{\frac{1}{m-1}},$$

where the $\delta_m = y_{n(m)} - y_{n(m-1)}$ is the correction at iteration $m = 1, 2, \dots$. The nonlinear solver iteration is halted if $R > 0.9$. The convergence test at the m -th iteration is then

$$S\|\delta_m\| < 0.33, \quad (2.7)$$

where $S = R/(R-1)$ whenever $m > 1$ and $R \leq 0.9$. The user has the option of changing the constant in the convergence test from its default value of 0.33. The quantity S is set to $S = 20$ initially and whenever J or P is updated, and it is reset to $S = 100$ on a step with $\alpha \neq \bar{\alpha}$. Note that at $m = 1$, the convergence test (2.7) uses an old value for S . Therefore, at the first nonlinear solver iteration, we make an additional test and stop the iteration if $\|\delta_1\| < 0.33 \cdot 10^{-4}$ (since such a δ_1 is probably just noise and therefore not appropriate for use in evaluating R). We allow only a small number (default value 4) of nonlinear iterations. If convergence fails with J or P current, we are forced to reduce the step size h_n , and we replace h_n by $h_n/4$. The integration is halted after a preset number (default value 10) of convergence failures. Both the maximum number of allowable nonlinear iterations and the maximum number of nonlinear convergence failures can be changed by the user from their default values.

When an iterative method is used to solve the linear system, to minimize the effect of linear iteration errors on the nonlinear and local integration error controls, we require the preconditioned linear residual to be small relative to the allowed error in the nonlinear iteration, i.e., $\|P^{-1}(Jx+G)\| < 0.05 \cdot 0.33$. The safety factor 0.05 can be changed by the user.

When the Jacobian is stored using either dense or band SUNMATRIX objects, the Jacobian J defined in (2.5) can be either supplied by the user or have IDA compute one internally by difference quotients. In the latter case, we use the approximation

$$J_{ij} = [F_i(t, y + \sigma_j e_j, \dot{y} + \alpha \sigma_j e_j) - F_i(t, y, \dot{y})]/\sigma_j, \text{ with} \\ \sigma_j = \sqrt{U} \max\{|y_j|, |h\dot{y}_j|, 1/W_j\} \text{sign}(h\dot{y}_j),$$

where U is the unit roundoff, h is the current step size, and W_j is the error weight for the component y_j defined by (2.6). We note that with sparse and user-supplied SUNMATRIX objects, the Jacobian *must* be supplied by a user routine.

In the case of an iterative linear solver, if a routine for Jv is not supplied, such products are approximated by

$$Jv = [F(t, y + \sigma v, \dot{y} + \alpha \sigma v) - F(t, y, \dot{y})]/\sigma,$$

where the increment $\sigma = \sqrt{N}$. As an option, the user can specify a constant factor that is inserted into this expression for σ .

During the course of integrating the system, IDA computes an estimate of the local truncation error, LTE, at the n -th time step, and requires this to satisfy the inequality

$$\|\text{LTE}\|_{\text{WRMS}} \leq 1.$$

Asymptotically, LTE varies as h^{q+1} at step size h and order q , as does the predictor-corrector difference $\Delta_n \equiv y_n - y_{n(0)}$. Thus there is a constant C such that

$$\text{LTE} = C\Delta_n + O(h^{q+2}),$$

and so the norm of LTE is estimated as $|C| \cdot \|\Delta_n\|$. In addition, IDA requires that the error in the associated polynomial interpolant over the current step be bounded by 1 in norm. The leading term of the norm of this error is bounded by $\bar{C}\|\Delta_n\|$ for another constant \bar{C} . Thus the local error test in IDA is

$$\max\{|C|, \bar{C}\}\|\Delta_n\| \leq 1. \quad (2.8)$$

A user option is available by which the algebraic components of the error vector are omitted from the test (2.8), if these have been so identified.

In IDA, the local error test is tightly coupled with the logic for selecting the step size and order. First, there is an initial phase that is treated specially; for the first few steps, the step size is doubled and the order raised (from its initial value of 1) on every step, until (a) the local error test (2.8) fails, (b) the order is reduced (by the rules given below), or (c) the order reaches 5 (the maximum). For step and order selection on the general step, IDA uses a different set of local error estimates, based on the asymptotic behavior of the local error in the case of fixed step sizes. At each of the orders q' equal to q , $q-1$ (if $q > 1$), $q-2$ (if $q > 2$), or $q+1$ (if $q < 5$), there are constants $C(q')$ such that the norm of the local truncation error at order q' satisfies

$$\text{LTE}(q') = C(q')\|\phi(q'+1)\| + O(h^{q'+2}),$$

where $\phi(k)$ is a modified divided difference of order k that is retained by IDA (and behaves asymptotically as h^k). Thus the local truncation errors are estimated as $\text{ELTE}(q') = C(q')\|\phi(q'+1)\|$ to select step sizes. But the choice of order in IDA is based on the requirement that the scaled derivative norms, $\|h^k y^{(k)}\|$, are monotonically decreasing with k , for k near q . These norms are again estimated using the $\phi(k)$, and in fact

$$\|h^{q'+1} y^{(q'+1)}\| \approx T(q') \equiv (q'+1)\text{ELTE}(q').$$

The step/order selection begins with a test for monotonicity that is made even *before* the local error test is performed. Namely, the order is reset to $q' = q-1$ if (a) $q = 2$ and $T(1) \leq T(2)/2$, or (b) $q > 2$ and $\max\{T(q-1), T(q-2)\} \leq T(q)$; otherwise $q' = q$. Next the local error test (2.8) is performed, and if it fails, the step is redone at order $q \leftarrow q'$ and a new step size h' . The latter is based on the h^{q+1} asymptotic behavior of $\text{ELTE}(q)$, and, with safety factors, is given by

$$\eta = h'/h = 0.9/[2\text{ELTE}(q)]^{1/(q+1)}.$$

The value of η is adjusted so that $0.25 \leq \eta \leq 0.9$ before setting $h \leftarrow h' = \eta h$. If the local error test fails a second time, IDA uses $\eta = 0.25$, and on the third and subsequent failures it uses $q = 1$ and $\eta = 0.25$. After 10 failures, IDA returns with a give-up message.

As soon as the local error test has passed, the step and order for the next step may be adjusted. No such change is made if $q' = q-1$ from the prior test, if $q = 5$, or if q was increased on the previous step. Otherwise, if the last $q+1$ steps were taken at a constant order $q < 5$ and a constant step size, IDA considers raising the order to $q+1$. The logic is as follows: (a) If $q = 1$, then reset $q = 2$ if $T(2) < T(1)/2$. (b) If $q > 1$ then

- reset $q \leftarrow q-1$ if $T(q-1) \leq \min\{T(q), T(q+1)\}$;
- else reset $q \leftarrow q+1$ if $T(q+1) < T(q)$;

- leave q unchanged otherwise [then $T(q-1) > T(q) \leq T(q+1)$].

In any case, the new step size h' is set much as before:

$$\eta = h'/h = 1/[2 \text{ELTE}(q)]^{1/(q+1)}.$$

The value of η is adjusted such that (a) if $\eta > 2$, η is reset to 2; (b) if $\eta \leq 1$, η is restricted to $0.5 \leq \eta \leq 0.9$; and (c) if $1 < \eta < 2$ we use $\eta = 1$. Finally h is reset to $h' = \eta h$. Thus we do not increase the step size unless it can be doubled. See [4] for details.

IDA permits the user to impose optional inequality constraints on individual components of the solution vector y . Any of the following four constraints can be imposed: $y_i > 0$, $y_i < 0$, $y_i \geq 0$, or $y_i \leq 0$. The constraint satisfaction is tested after a successful nonlinear system solution. If any constraint fails, we declare a convergence failure of the nonlinear iteration and reduce the step size. Rather than cutting the step size by some arbitrary factor, IDA estimates a new step size h' using a linear approximation of the components in y that failed the constraint test (including a safety factor of 0.9 to cover the strict inequality case). These additional constraints are also imposed during the calculation of consistent initial conditions.

Normally, IDA takes steps until a user-defined output value $t = t_{\text{out}}$ is overtaken, and then computes $y(t_{\text{out}})$ by interpolation. However, a “one step” mode option is available, where control returns to the calling program after each step. There are also options to force IDA not to integrate past a given stopping point $t = t_{\text{stop}}$.

2.2 Preconditioning

When using a nonlinear solver that requires the solution of a linear system of the form $J\Delta y = -G$ (e.g., the default Newton iteration), IDA makes repeated use of a linear solver. If this linear system solve is done with one of the scaled preconditioned iterative linear solvers supplied with SUNDIALS, these solvers are rarely successful if used without preconditioning; it is generally necessary to precondition the system in order to obtain acceptable efficiency. A system $Ax = b$ can be preconditioned on the left, on the right, or on both sides. The Krylov method is then applied to a system with the matrix $P^{-1}A$, or AP^{-1} , or $P_L^{-1}AP_R^{-1}$, instead of A . However, within IDA, preconditioning is allowed *only* on the left, so that the iterative method is applied to systems $(P^{-1}J)\Delta y = -P^{-1}G$. Left preconditioning is required to make the norm of the linear residual in the nonlinear iteration meaningful; in general, $\|J\Delta y + G\|$ is meaningless, since the weights used in the WRMS-norm correspond to y .

In order to improve the convergence of the Krylov iteration, the preconditioner matrix P should in some sense approximate the system matrix A . Yet at the same time, in order to be cost-effective, the matrix P should be reasonably efficient to evaluate and solve. Finding a good point in this tradeoff between rapid convergence and low cost can be very difficult. Good choices are often problem-dependent (for example, see [6] for an extensive study of preconditioners for reaction-transport systems).

Typical preconditioners used with IDA are based on approximations to the iteration matrix of the systems involved; in other words, $P \approx \frac{\partial F}{\partial y} + \alpha \frac{\partial F}{\partial \dot{y}}$, where α is a scalar inversely proportional to the integration step size h . Because the Krylov iteration occurs within a nonlinear solver iteration and further also within a time integration, and since each of these iterations has its own test for convergence, the preconditioner may use a very crude approximation, as long as it captures the dominant numerical feature(s) of the system. We have found that the combination of a preconditioner with the Newton-Krylov iteration, using even a fairly poor approximation to the Jacobian, can be surprisingly superior to using the same matrix without Krylov acceleration (i.e., a modified Newton iteration), as well as to using the Newton-Krylov method with no preconditioning.

2.3 Rootfinding

The IDA solver has been augmented to include a rootfinding feature. This means that, while integrating the Initial Value Problem (2.1), IDA can also find the roots of a set of user-defined functions $g_i(t, y, \dot{y})$ that depend on t , the solution vector $y = y(t)$, and its t -derivative $\dot{y}(t)$. The number of these root

functions is arbitrary, and if more than one g_i is found to have a root in any given interval, the various root locations are found and reported in the order that they occur on the t axis, in the direction of integration.

Generally, this rootfinding feature finds only roots of odd multiplicity, corresponding to changes in sign of $g_i(t, y(t), \dot{y}(t))$, denoted $g_i(t)$ for short. If a user root function has a root of even multiplicity (no sign change), it will probably be missed by IDA. If such a root is desired, the user should reformulate the root function so that it changes sign at the desired root.

The basic scheme used is to check for sign changes of any $g_i(t)$ over each time step taken, and then (when a sign change is found) to home in on the root (or roots) with a modified secant method [22]. In addition, each time g is computed, IDA checks to see if $g_i(t) = 0$ exactly, and if so it reports this as a root. However, if an exact zero of any g_i is found at a point t , IDA computes g at $t + \delta$ for a small increment δ , slightly further in the direction of integration, and if any $g_i(t + \delta) = 0$ also, IDA stops and reports an error. This way, each time IDA takes a time step, it is guaranteed that the values of all g_i are nonzero at some past value of t , beyond which a search for roots is to be done.

At any given time in the course of the time-stepping, after suitable checking and adjusting has been done, IDA has an interval $(t_{lo}, t_{hi}]$ in which roots of the $g_i(t)$ are to be sought, such that t_{hi} is further ahead in the direction of integration, and all $g_i(t_{lo}) \neq 0$. The endpoint t_{hi} is either t_n , the end of the time step last taken, or the next requested output time t_{out} if this comes sooner. The endpoint t_{lo} is either t_{n-1} , or the last output time t_{out} (if this occurred within the last step), or the last root location (if a root was just located within this step), possibly adjusted slightly toward t_n if an exact zero was found. The algorithm checks g at t_{hi} for zeros and for sign changes in (t_{lo}, t_{hi}) . If no sign changes are found, then either a root is reported (if some $g_i(t_{hi}) = 0$) or we proceed to the next time interval (starting at t_{hi}). If one or more sign changes were found, then a loop is entered to locate the root to within a rather tight tolerance, given by

$$\tau = 100 * U * (|t_n| + |h|) \quad (U = \text{unit roundoff}) .$$

Whenever sign changes are seen in two or more root functions, the one deemed most likely to have its root occur first is the one with the largest value of $|g_i(t_{hi})|/|g_i(t_{hi}) - g_i(t_{lo})|$, corresponding to the closest to t_{lo} of the secant method values. At each pass through the loop, a new value t_{mid} is set, strictly within the search interval, and the values of $g_i(t_{mid})$ are checked. Then either t_{lo} or t_{hi} is reset to t_{mid} according to which subinterval is found to have the sign change. If there is none in (t_{lo}, t_{mid}) but some $g_i(t_{mid}) = 0$, then that root is reported. The loop continues until $|t_{hi} - t_{lo}| < \tau$, and then the reported root location is t_{hi} .

In the loop to locate the root of $g_i(t)$, the formula for t_{mid} is

$$t_{mid} = t_{hi} - (t_{hi} - t_{lo})g_i(t_{hi})/[g_i(t_{hi}) - \alpha g_i(t_{lo})] ,$$

where α a weight parameter. On the first two passes through the loop, α is set to 1, making t_{mid} the secant method value. Thereafter, α is reset according to the side of the subinterval (low vs high, i.e. toward t_{lo} vs toward t_{hi}) in which the sign change was found in the previous two passes. If the two sides were opposite, α is set to 1. If the two sides were the same, α is halved (if on the low side) or doubled (if on the high side). The value of t_{mid} is closer to t_{lo} when $\alpha < 1$ and closer to t_{hi} when $\alpha > 1$. If the above value of t_{mid} is within $\tau/2$ of t_{lo} or t_{hi} , it is adjusted inward, such that its fractional distance from the endpoint (relative to the interval size) is between .1 and .5 (.5 being the midpoint), and the actual distance from the endpoint is at least $\tau/2$.

Chapter 3

Code Organization

3.1 SUNDIALS organization

The family of solvers referred to as SUNDIALS consists of the solvers CVODE and ARKODE (for ODE systems), KINSOL (for nonlinear algebraic systems), and IDA (for differential-algebraic systems). In addition, SUNDIALS also includes variants of CVODE and IDA with sensitivity analysis capabilities (using either forward or adjoint methods), called CVODES and IDAS, respectively.

The various solvers of this family share many subordinate modules. For this reason, it is organized as a family, with a directory structure that exploits that sharing (see Figs. 3.1 and 3.2). The following is a list of the solver packages presently available, and the basic functionality of each:

- CVODE, a solver for stiff and nonstiff ODE systems $dy/dt = f(t, y)$ based on Adams and BDF methods;
- CVODES, a solver for stiff and nonstiff ODE systems with sensitivity analysis capabilities;
- ARKODE, a solver for ODE systems $Mdy/dt = f_E(t, y) + f_I(t, y)$ based on additive Runge-Kutta methods;
- IDA, a solver for differential-algebraic systems $F(t, y, \dot{y}) = 0$ based on BDF methods;
- IDAS, a solver for differential-algebraic systems with sensitivity analysis capabilities;
- KINSOL, a solver for nonlinear algebraic systems $F(u) = 0$.

3.2 IDA organization

The IDA package is written in the ANSI C language. The following summarizes the basic structure of the package, although knowledge of this structure is not necessary for its use.

The overall organization of the IDA package is shown in Figure 3.3. The central integration module, implemented in the files `ida.h`, `ida_impl.h`, and `ida.c`, deals with the evaluation of integration coefficients, estimation of local error, selection of stepsize and order, and interpolation to user output points, among other issues.

IDA utilizes generic linear and nonlinear solver modules defined by the SUNLINSOL API (see Chapter 8) and SUNNONLINSOL API (see Chapter 9) respectively. As such, IDA has no knowledge of the method being used to solve the linear and nonlinear systems that arise in each time step. For any given user problem, there exists a single nonlinear solver interface and, if necessary, a linear system solver interface is specified, and invoked as needed during the integration. While SUNDIALS includes a fixed-point nonlinear solver module, it is not currently supported in IDA (note the fixed-point module is listed in Figure 3.1 but not Figure 3.3).

IDA now has a single unified linear solver interface, IDALS, supporting both direct and iterative linear solvers built using the generic SUNLINSOL API (see Chapter 8). These solvers may utilize a




Figure 3.1: High-level diagram of the SUNDIALS suite

SUNMATRIX object (see Chapter 7) for storing Jacobian information, or they may be matrix-free. Since IDA can operate on any valid SUNLINSOL implementation, the set of linear solver modules available to IDA will expand as new SUNLINSOL modules are developed.

For users employing dense or banded Jacobian matrices, IDALS includes algorithms for their approximation through difference quotients, but the user also has the option of supplying the Jacobian (or an approximation to it) directly. This user-supplied routine is required when using sparse or user-supplied Jacobian matrices.


For users employing matrix-free iterative linear solvers, IDALS includes an algorithm for the approximation by difference quotients of the product between the Jacobian matrix and a vector, Jv . Again, the user has the option of providing routines for this operation, in two phases: setup (preprocessing of Jacobian data) and multiplication.

For preconditioned iterative methods, the preconditioning must be supplied by the user, again in two phases: setup and solve. While there is no default choice of preconditioner analogous to the difference-quotient approximation in the direct case, the references [6, 10], together with the example and demonstration programs included with IDA, offer considerable assistance in building preconditioners.


IDA's linear solver interface consists of four primary routines, devoted to (1) memory allocation and initialization, (2) setup of the matrix data involved, (3) solution of the system, and (4) freeing of memory. The setup and solution phases are separate because the evaluation of Jacobians and preconditioners is done only periodically during the integration, as required to achieve convergence. The call list within the central IDA module to each of the four associated functions is fixed, thus allowing the central module to be completely independent of the linear system method.

IDA also provides a preconditioner module, IDABBDPRE, for use with any of the Krylov iterative linear solvers. It works in conjunction with NVECTOR_PARALLEL and generates a preconditioner that is a block-diagonal matrix with each block being a banded matrix.

All state information used by IDA to solve a given problem is saved in a structure, and a pointer to that structure is returned to the user. There is no global data in the IDA package, and so, in this



(a) Directory structure of the SUNDIALS source tree



(b) Directory structure of the SUNDIALS examples

Figure 3.2: Organization of the SUNDIALS suite




Figure 3.3: Overall structure diagram of the IDA package. Modules specific to IDA begin with “IDA” (IDALS, IDABBDPRE, and IDANLS), all other items correspond to generic solver and auxiliary modules. Note also that the LAPACK, KLU and SUPERLUMT support is through interfaces to external packages. Users will need to download and compile those packages independently.

respect, it is reentrant. State information specific to the linear solver is saved in a separate structure, a pointer to which resides in the IDA memory structure. The reentrancy of IDA was motivated by the situation where two or more problems are solved by intermixed calls to the package from one user program.

Chapter 4

Using IDA for C Applications

This chapter is concerned with the use of IDA for the integration of DAEs in a C language setting. The following sections treat the header files, the layout of the user's main program, description of the IDA user-callable functions, and description of user-supplied functions.

The sample programs described in the companion document [25] may also be helpful. Those codes may be used as templates (with the removal of some lines involved in testing), and are included in the IDA package.

Users with applications written in FORTRAN should see Chapter 5, which describes the FORTRAN/C interface module.

The user should be aware that not all SUNLINSOL and SUNMATRIX modules are compatible with all NVECTOR implementations. Details on compatibility are given in the documentation for each SUNMATRIX module (Chapter 7) and each SUNLINSOL module (Chapter 8). For example, NVECTOR_PARALLEL is not compatible with the dense, banded, or sparse SUNMATRIX types, or with the corresponding dense, banded, or sparse SUNLINSOL modules. Please check Chapters 7 and 8 to verify compatibility between these modules. In addition to that documentation, we note that the preconditioner module IDABBDPRE can only be used with NVECTOR_PARALLEL. It is not recommended to use a threaded vector module with SuperLU_MT unless it is the NVECTOR_OPENMP module, and SuperLU_MT is also compiled with OpenMP.

IDA uses various constants for both input and output. These are defined as needed in this chapter, but for convenience are also listed separately in Appendix B.

4.1 Access to library and header files

At this point, it is assumed that the installation of IDA, following the procedure described in Appendix A, has been completed successfully.

Regardless of where the user's application program resides, its associated compilation and load commands must make reference to the appropriate locations for the library and header files required by IDA. The relevant library files are

- *libdir/libsundials_ida.lib*,
- *libdir/libsundials_nvec*.lib*,

where the file extension *.lib* is typically *.so* for shared libraries and *.a* for static libraries. The relevant header files are located in the subdirectories

- *incdir/include/ida*
- *incdir/include/sundials*
- *incdir/include/nvector*

- `incdir/include/sunmatrix`
- `incdir/include/sunlinsol`
- `incdir/include/sunnonlinsol`

The directories `libdir` and `incdir` are the install library and include directories, respectively. For a default installation, these are `instdir/lib` and `instdir/include`, respectively, where `instdir` is the directory where SUNDIALS was installed (see Appendix A).

Note that an application cannot link to both the IDA and IDAS libraries because both contain user-callable functions with the same names (to ensure that IDAS is backward compatible with IDA). Therefore, applications that contain both DAE problems and DAEs with sensitivity analysis, should use IDAS.

4.2 Data types

The `sundials_types.h` file contains the definition of the type `realtype`, which is used by the SUNDIALS solvers for all floating-point data, the definition of the integer type `sunindextype`, which is used for vector and matrix indices, and `booleantype`, which is used for certain logic operations within SUNDIALS.

4.2.1 Floating point types

The type `realtype` can be `float`, `double`, or `long double`, with the default being `double`. The user can change the precision of the SUNDIALS solvers arithmetic at the configuration stage (see §A.1.2).

Additionally, based on the current precision, `sundials_types.h` defines `BIG_REAL` to be the largest value representable as a `realtype`, `SMALL_REAL` to be the smallest value representable as a `realtype`, and `UNIT_ROUNDOFF` to be the difference between 1.0 and the minimum `realtype` greater than 1.0.

Within SUNDIALS, real constants are set by way of a macro called `RCONST`. It is this macro that needs the ability to branch on the definition `realtype`. In ANSI C, a floating-point constant with no suffix is stored as a `double`. Placing the suffix “F” at the end of a floating point constant makes it a `float`, whereas using the suffix “L” makes it a `long double`. For example,

```
#define A 1.0
#define B 1.0F
#define C 1.0L
```

defines `A` to be a `double` constant equal to 1.0, `B` to be a `float` constant equal to 1.0, and `C` to be a `long double` constant equal to 1.0. The macro call `RCONST(1.0)` automatically expands to `1.0` if `realtype` is `double`, to `1.0F` if `realtype` is `float`, or to `1.0L` if `realtype` is `long double`. SUNDIALS uses the `RCONST` macro internally to declare all of its floating-point constants.

A user program which uses the type `realtype` and the `RCONST` macro to handle floating-point constants is precision-independent except for any calls to precision-specific standard math library functions. (Our example programs use both `realtype` and `RCONST`.) Users can, however, use the type `double`, `float`, or `long double` in their code (assuming that this usage is consistent with the typedef for `realtype`). Thus, a previously existing piece of ANSI C code can use SUNDIALS without modifying the code to use `realtype`, so long as the SUNDIALS libraries use the correct precision (for details see §A.1.2).

4.2.2 Integer types used for vector and matrix indices

The type `sunindextype` can be either a 32- or 64-bit *signed* integer. The default is the portable `int64_t` type, and the user can change it to `int32_t` at the configuration stage. The configuration system will detect if the compiler does not support portable types, and will replace `int32_t` and `int64_t` with `int` and `long int`, respectively, to ensure use of the desired sizes on Linux, Mac OS X,

and Windows platforms. SUNDIALS currently does not support *unsigned* integer types for vector and matrix indices, although these could be added in the future if there is sufficient demand.

A user program which uses `sunindextype` to handle vector and matrix indices will work with both index storage types except for any calls to index storage-specific external libraries. (Our C and C++ example programs use `sunindextype`.) Users can, however, use any one of `int`, `long int`, `int32_t`, `int64_t` or `long long int` in their code, assuming that this usage is consistent with the typedef for `sunindextype` on their architecture). Thus, a previously existing piece of ANSI C code can use SUNDIALS without modifying the code to use `sunindextype`, so long as the SUNDIALS libraries use the appropriate index storage type (for details see §A.1.2).

4.3 Header files

The calling program must include several header files so that various macros and data types can be used. The header file that is always required is:

- `ida/ida.h`, the header file for IDA, which defines the several types and various constants, and includes function prototypes. This includes the header file for IDALS, `ida/ida_ls.h`.

Note that `ida.h` includes `sundials_types.h`, which defines the types `realtype`, `sunindextype`, and `booleantype` and the constants `SUNFALSE` and `SUNTRUE`.

The calling program must also include an `NVECTOR` implementation header file, of the form `nvector/nvector_***.h`. See Chapter 6 for the appropriate name. This file in turn includes the header file `sundials_nvector.h` which defines the abstract `N_Vector` data type.

If using a non-default nonlinear solver module, or when interacting with a `SUNNONLINSOL` module directly, the calling program must also include a `SUNNONLINSOL` implementation header file, of the form `sunnonlinsol/sunnonlinsol_***.h` where `***` is the name of the nonlinear solver module (see Chapter 9 for more information). This file in turn includes the header file `sundials_nonlinearsolver.h` which defines the abstract `SUNNonlinearSolver` data type.

If using a nonlinear solver that requires the solution of a linear system of the form (2.4) (e.g., the default Newton iteration), a linear solver module header file is also required. The header files corresponding to the various SUNDIALS-provided linear solver modules available for use with IDA are:

- Direct linear solvers:
 - `sunlinsol/sunlinsol_dense.h`, which is used with the dense linear solver module, `SUNLINSOL_DENSE`;
 - `sunlinsol/sunlinsol_band.h`, which is used with the banded linear solver module, `SUNLINSOL_BAND`;
 - `sunlinsol/sunlinsol_lapackdense.h`, which is used with the LAPACK dense linear solver module, `SUNLINSOL_LAPACKDENSE`;
 - `sunlinsol/sunlinsol_lapackband.h`, which is used with the LAPACK banded linear solver module, `SUNLINSOL_LAPACKBAND`;
 - `sunlinsol/sunlinsol_klu.h`, which is used with the KLU sparse linear solver module, `SUNLINSOL_KLU`;
 - `sunlinsol/sunlinsol_superlunt.h`, which is used with the SUPERLUNT sparse linear solver module, `SUNLINSOL_SUPERLUNT`;
- Iterative linear solvers:
 - `sunlinsol/sunlinsol_spgmr.h`, which is used with the scaled, preconditioned GMRES Krylov linear solver module, `SUNLINSOL_SPGMR`;
 - `sunlinsol/sunlinsol_spfgmr.h`, which is used with the scaled, preconditioned FGMRES Krylov linear solver module, `SUNLINSOL_SPFGMR`;

- `sunlinsol/sunlinsol.spbcgs.h`, which is used with the scaled, preconditioned Bi-CGStab Krylov linear solver module, `SUNLINSOL_SPBCGS`;
- `sunlinsol/sunlinsol.sptfqmr.h`, which is used with the scaled, preconditioned TFQMR Krylov linear solver module, `SUNLINSOL_SPTFQMR`;
- `sunlinsol/sunlinsol.pcg.h`, which is used with the scaled, preconditioned CG Krylov linear solver module, `SUNLINSOL_PCG`;

The header files for the `SUNLINSOL_DENSE` and `SUNLINSOL_LAPACKDENSE` linear solver modules include the file `sunmatrix/sunmatrix.dense.h`, which defines the `SUNMATRIX_DENSE` matrix module, as well as various functions and macros acting on such matrices.

The header files for the `SUNLINSOL_BAND` and `SUNLINSOL_LAPACKBAND` linear solver modules include the file `sunmatrix/sunmatrix.band.h`, which defines the `SUNMATRIX_BAND` matrix module, as well as various functions and macros acting on such matrices.

The header files for the `SUNLINSOL_KLU` and `SUNLINSOL_SUPERLUMT` sparse linear solvers include the file `sunmatrix/sunmatrix.sparse.h`, which defines the `SUNMATRIX_SPARSE` matrix module, as well as various functions and macros acting on such matrices.

The header files for the Krylov iterative solvers include the file `sundials/sundials.iterative.h`, which enumerates the kind of preconditioning, and (for the `SPGMR` and `SPFGMR` solvers) the choices for the Gram-Schmidt process.

Other headers may be needed, according to the choice of preconditioner, etc. For example, in the `idaFoodWeb_kry_p` example (see [25]), preconditioning is done with a block-diagonal matrix. For this, even though the `SUNLINSOL_SPGMR` linear solver is used, the header `sundials/sundials.dense.h` is included for access to the underlying generic dense matrix arithmetic routines.

4.4 A skeleton of the user's main program

The following is a skeleton of the user's main program (or calling program) for the integration of a DAE IVP. Most of the steps are independent of the `NVECTOR`, `SUNMATRIX`, `SUNLINSOL`, and `SUNNONLINSOL` implementations used. For the steps that are not, refer to Chapter 6, 7, 8, and 9 for the specific name of the function to be called or macro to be referenced.

1. Initialize parallel or multi-threaded environment, if appropriate

For example, call `MPI_Init` to initialize MPI if used, or set `num_threads`, the number of threads to use within the threaded vector functions, if used.

2. Set problem dimensions etc.

This generally includes the problem size `N`, and may include the local vector length `Nlocal`.

Note: The variables `N` and `Nlocal` should be of type `sunindextype`.

3. Set vectors of initial values

To set the vectors `y0` and `yp0` to initial values for y and \dot{y} , use the appropriate functions defined by the particular `NVECTOR` implementation.

For native `SUNDIALS` vector implementations (except the `CUDA` and `RAJA`-based ones), use a call of the form `y0 = N_VMake_***(..., ydata)` if the `realtype` array `ydata` containing the initial values of y already exists. Otherwise, create a new vector by making a call of the form `y0 = N_VNew_***(...)`, and then set its elements by accessing the underlying data with a call of the form `ydata = N_VGetArrayPointer(y0)`. See §6.2-6.5 for details.

For the `hypr` and `PETSc` vector wrappers, first create and initialize the underlying vector and then create an `NVECTOR` wrapper with a call of the form `y0 = N_VMake_***(yvec)`, where `yvec` is a `hypr` or `PETSc` vector. Note that calls like `N_VNew_***(...)` and `N_VGetArrayPointer(...)` are not available for these vector wrappers. See §6.6 and §6.7 for details.

If using either the CUDA- or RAJA-based vector implementations use a call of the form `y0 = N_VMake_***(..., c)` where `c` is a pointer to a `suncudavec` or `sunrajavec` vector class if this class already exists. Otherwise, create a new vector by making a call of the form `y0 = N_VNew_***(...)`, and then set its elements by accessing the underlying data where it is located with a call of the form `N_VGetDeviceArrayPointer_***` or `N_VGetHostArrayPointer_***`. Note that the vector class will allocate memory on both the host and device when instantiated. See §6.8-6.9 for details.

Set the vector `yp0` of initial conditions for y similarly.

4. Create IDA object

Call `ida_mem = IDACreate()` to create the IDA memory block. `IDACreate` returns a pointer to the IDA memory structure. See §4.5.1 for details. This `void *` pointer must then be passed as the first argument to all subsequent IDA function calls.

5. Initialize IDA solver

Call `IDAInit(...)` to provide required problem specifications (residual function, initial time, and initial conditions), allocate internal memory for IDA, and initialize IDA. `IDAInit` returns an error flag to indicate success or an illegal argument value. See §4.5.1 for details.

6. Specify integration tolerances

Call `IDASSStolerances(...)` or `IDASVStolerances(...)` to specify, respectively, a scalar relative tolerance and scalar absolute tolerance, or a scalar relative tolerance and a vector of absolute tolerances. Alternatively, call `IDAWFStolerances` to specify a function which sets directly the weights used in evaluating WRMS vector norms. See §4.5.2 for details.

7. Create matrix object

If a nonlinear solver requiring a linear solver will be used (e.g., the default Newton iteration) and the linear solver will be a matrix-based linear solver, then a template Jacobian matrix must be created by calling the appropriate constructor function defined by the particular SUNMATRIX implementation.

For the SUNDIALS-supplied SUNMATRIX implementations, the matrix object may be created using a call of the form

```
SUNMatrix J = SUNBandMatrix(...);
```

or

```
SUNMatrix J = SUNDenseMatrix(...);
```

or

```
SUNMatrix J = SUNSparseMatrix(...);
```

NOTE: The dense, banded, and sparse matrix objects are usable only in a serial or threaded environment.

8. Create linear solver object

If a nonlinear solver requiring a linear solver is chosen (e.g., the default Newton iteration), then the desired linear solver object must be created by calling the appropriate constructor function defined by the particular SUNLINSOL implementation.

For any of the SUNDIALS-supplied SUNLINSOL implementations, the linear solver object may be created using a call of the form

```
SUNLinearSolver LS = SUNLinSol_*(...);
```

where `*` can be replaced with “Dense”, “SPGMR”, or other options, as discussed in §4.5.3 and Chapter 8.

9. Set linear solver optional inputs

Call `*Set*` functions from the selected linear solver module to change optional inputs specific to that linear solver. See the documentation for each SUNLINSOL module in Chapter 8 for details.

10. Attach linear solver module

If a nonlinear solver requiring a linear solver is chosen (e.g., the default Newton iteration), then initialize the IDALS linear solver interface by attaching the linear solver object (and matrix object, if applicable) with the following call (for details see §4.5.3):

```
ier = IDASetLinearSolver(...);
```

11. Set optional inputs

Optionally, call `IDASet*` functions to change from their default values any optional inputs that control the behavior of IDA. See §4.5.8.1 and §4.5.8 for details.

12. Create nonlinear solver object (*optional*)

If using a non-default nonlinear solver (see §4.5.4), then create the desired nonlinear solver object by calling the appropriate constructor function defined by the particular SUNNONLINSOL implementation (e.g., `NLS = SUNNonlinSol_***(...)`; where `***` is the name of the nonlinear solver (see Chapter 9 for details).

13. Attach nonlinear solver module (*optional*)

If using a non-default nonlinear solver, then initialize the nonlinear solver interface by attaching the nonlinear solver object by calling `ier = IDASetNonlinearSolver(ida_mem, NLS)`; (see §4.5.4 for details).

14. Set nonlinear solver optional inputs (*optional*)

Call the appropriate set functions for the selected nonlinear solver module to change optional inputs specific to that nonlinear solver. These *must* be called after `IDAInit` if using the default nonlinear solver or after attaching a new nonlinear solver to IDA, otherwise the optional inputs will be overridden by IDA defaults. See Chapter 9 for more information on optional inputs.

15. Correct initial values

Optionally, call `IDACalcIC` to correct the initial values `y0` and `yp0` passed to `IDAInit`. See §4.5.5. Also see §4.5.8.3 for relevant optional input calls.

16. Specify rootfinding problem

Optionally, call `IDARootInit` to initialize a rootfinding problem to be solved during the integration of the DAE system. See §4.5.6 for details, and see §4.5.8.4 for relevant optional input calls.

17. Advance solution in time

For each point at which output is desired, call `flag = IDASolve(ida_mem, tout, &tret, yret, ypret, itask)`. Here `itask` specifies the return mode. The vector `yret` (which can be the same as the vector `y0` above) will contain $y(t)$, while the vector `ypret` (which can be the same as the vector `yp0` above) will contain $\dot{y}(t)$. See §4.5.7 for details.

18. Get optional outputs

Call `IDA*Get*` functions to obtain optional output. See §4.5.10 for details.

19. Deallocate memory for solution vectors

Upon completion of the integration, deallocate memory for the vectors `yret` and `ypret` (or `y` and `yp`) by calling the appropriate destructor function defined by the NVECTOR implementation:

`N_VDestroy(yret);`

and similarly for `ypret`.

20. Free solver memory

`IDAFree(&ida_mem)` to free the memory allocated for IDA.

21. Free nonlinear solver memory (*optional*)

If a non-default nonlinear solver was used, then call `SUNNonlinSolFree(NLS)` to free any memory allocated for the `SUNNONLINSOL` object.

22. Free linear solver and matrix memory

Call `SUNLinSolFree` and `SUNMatDestroy` to free any memory allocated for the linear solver and matrix objects created above.

23. Finalize MPI, if used

Call `MPI_Finalize()` to terminate MPI.

SUNDIALS provides some linear solvers only as a means for users to get problems running and not as highly efficient solvers. For example, if solving a dense system, we suggest using the LAPACK solvers if the size of the linear system is $> 50,000$. (Thanks to A. Nicolai for his testing and recommendation.) Table 4.1 shows the linear solver interfaces available as `SUNLINSOL` modules and the vector implementations required for use. As an example, one cannot use the dense direct solver interfaces with the MPI-based vector implementation. However, as discussed in Chapter 8 the SUNDIALS packages operate on generic `SUNLINSOL` objects, allowing a user to develop their own solvers should they so desire.

Table 4.1: SUNDIALS linear solver interfaces and vector implementations that can be used for each.

| Linear Solver | Serial | Parallel (MPI) | OpenMP | pThreads | hypr | PETSc | CUDA | RAJA | User Supp. |
|---------------|--------|----------------|--------|----------|------|-------|------|------|------------|
| Dense | ✓ | | ✓ | ✓ | | | | | ✓ |
| Band | ✓ | | ✓ | ✓ | | | | | ✓ |
| LapackDense | ✓ | | ✓ | ✓ | | | | | ✓ |
| LapackBand | ✓ | | ✓ | ✓ | | | | | ✓ |
| KLU | ✓ | | ✓ | ✓ | | | | | ✓ |
| SUPERLUMT | ✓ | | ✓ | ✓ | | | | | ✓ |
| SPGMR | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |
| SPFGMR | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |
| SPBCGS | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |
| SPTFQMR | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |
| PCG | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |
| User Supp. | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |

4.5 User-callable functions

This section describes the IDA functions that are called by the user to set up and solve a DAE. Some of these are required. However, starting with §4.5.8, the functions listed involve optional inputs/outputs or restarting, and those paragraphs can be skipped for a casual use of IDA. In any case, refer to §4.4 for the correct order of these calls.

On an error, each user-callable function returns a negative value and sends an error message to the error handler routine, which prints the message on `stderr` by default. However, the user can set a file as error output or can provide his own error handler function (see §4.5.8.1).

4.5.1 IDA initialization and deallocation functions

The following three functions must be called in the order listed. The last one is to be called only after the DAE solution is complete, as it frees the IDA memory block created and allocated by the first two calls.

IDACreate

Call `ida_mem = IDACreate();`

Description The function `IDACreate` instantiates an IDA solver object.

Arguments `IDACreate` has no arguments.

Return value If successful, `IDACreate` returns a pointer to the newly created IDA memory block (of type `void *`). Otherwise it returns `NULL`.

IDAInit

Call `flag = IDAInit(ida_mem, res, t0, y0, yp0);`

Description The function `IDAInit` provides required problem and solution specifications, allocates internal memory, and initializes IDA.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block returned by `IDACreate`.

`res` (`IDAResFn`) is the C function which computes the residual function F in the DAE. This function has the form `res(t, yy, yp, resval, user_data)`. For full details see §4.6.1.

`t0` (`realtype`) is the initial value of t .

`y0` (`N_Vector`) is the initial value of y .

`yp0` (`N_Vector`) is the initial value of \dot{y} .

Return value The return value `flag` (of type `int`) will be one of the following:

`IDA_SUCCESS` The call to `IDAInit` was successful.

`IDA_MEM_NULL` The IDA memory block was not initialized through a previous call to `IDACreate`.

`IDA_MEM_FAIL` A memory allocation request has failed.

`IDA_ILL_INPUT` An input argument to `IDAInit` has an illegal value.

Notes If an error occurred, `IDAInit` also sends an error message to the error handler function.

IDAFree

Call `IDAFree(&ida_mem);`

Description The function `IDAFree` frees the pointer allocated by a previous call to `IDACreate`.

Arguments The argument is the pointer to the IDA memory block (of type `void *`).

Return value The function `IDAFree` has no return value.

4.5.2 IDA tolerance specification functions

One of the following three functions must be called to specify the integration tolerances (or directly specify the weights used in evaluating WRMS vector norms). Note that this call must be made after the call to `IDAInit`.

IDASStolerances

Call `flag = IDASStolerances(ida_mem, reltol, abstol);`

Description The function `IDASStolerances` specifies scalar relative and absolute tolerances.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block returned by `IDACreate`.
`reltol` (`realtype`) is the scalar relative error tolerance.
`abstol` (`realtype`) is the scalar absolute error tolerance.

Return value The return value `flag` (of type `int`) will be one of the following:

- `IDA_SUCCESS` The call to `IDASStolerances` was successful.
- `IDA_MEM_NULL` The IDA memory block was not initialized through a previous call to `IDACreate`.
- `IDA_NO_MALLOC` The allocation function `IDAINIT` has not been called.
- `IDA_ILL_INPUT` One of the input tolerances was negative.

IDASVtolerances

Call `flag = IDASVtolerances(ida_mem, reltol, abstol);`

Description The function `IDASVtolerances` specifies scalar relative tolerance and vector absolute tolerances.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block returned by `IDACreate`.
`reltol` (`realtype`) is the scalar relative error tolerance.
`abstol` (`N_Vector`) is the vector of absolute error tolerances.

Return value The return value `flag` (of type `int`) will be one of the following:

- `IDA_SUCCESS` The call to `IDASVtolerances` was successful.
- `IDA_MEM_NULL` The IDA memory block was not initialized through a previous call to `IDACreate`.
- `IDA_NO_MALLOC` The allocation function `IDAINIT` has not been called.
- `IDA_ILL_INPUT` The relative error tolerance was negative or the absolute tolerance had a negative component.

Notes This choice of tolerances is important when the absolute error tolerance needs to be different for each component of the state vector y .

IDAWFtolerances

Call `flag = IDAWFtolerances(ida_mem, efun);`

Description The function `IDAWFtolerances` specifies a user-supplied function `efun` that sets the multiplicative error weights W_i for use in the weighted RMS norm, which are normally defined by Eq. (2.6).

Arguments `ida_mem` (`void *`) pointer to the IDA memory block returned by `IDACreate`.
`efun` (`IDAwtFn`) is the C function which defines the `ewt` vector (see §4.6.3).

Return value The return value `flag` (of type `int`) will be one of the following:

- `IDA_SUCCESS` The call to `IDAWFtolerances` was successful.
- `IDA_MEM_NULL` The IDA memory block was not initialized through a previous call to `IDACreate`.
- `IDA_NO_MALLOC` The allocation function `IDAINIT` has not been called.

General advice on choice of tolerances. For many users, the appropriate choices for tolerance values in `reltol` and `abstol` are a concern. The following pieces of advice are relevant.

(1) The scalar relative tolerance `reltol` is to be set to control relative errors. So `reltol`= 10^{-4} means that errors are controlled to .01%. We do not recommend using `reltol` larger than 10^{-3} .

On the other hand, `reltol` should not be so small that it is comparable to the unit roundoff of the machine arithmetic (generally around 10^{-15}).

(2) The absolute tolerances `abstol` (whether scalar or vector) need to be set to control absolute errors when any components of the solution vector `y` may be so small that pure relative error control is meaningless. For example, if `y[i]` starts at some nonzero value, but in time decays to zero, then pure relative error control on `y[i]` makes no sense (and is overly costly) after `y[i]` is below some noise level. Then `abstol` (if scalar) or `abstol[i]` (if a vector) needs to be set to that noise level. If the different components have different noise levels, then `abstol` should be a vector. See the example `idaRoberts_dns` in the IDA package, and the discussion of it in the IDA Examples document [25]. In that problem, the three components vary between 0 and 1, and have different noise levels; hence the `abstol` vector. It is impossible to give any general advice on `abstol` values, because the appropriate noise levels are completely problem-dependent. The user or modeler hopefully has some idea as to what those noise levels are.

(3) Finally, it is important to pick all the tolerance values conservatively, because they control the error committed on each individual time step. The final (global) errors are a sort of accumulation of those per-step errors. A good rule of thumb is to reduce the tolerances by a factor of .01 from the actual desired limits on errors. So if you want .01% accuracy (globally), a good choice is `reltol`= 10^{-6} . But in any case, it is a good idea to do a few experiments with the tolerances to see how the computed solution values vary as tolerances are reduced.

Advice on controlling unphysical negative values. In many applications, some components in the true solution are always positive or non-negative, though at times very small. In the numerical solution, however, small negative (hence unphysical) values can then occur. In most cases, these values are harmless, and simply need to be controlled, not eliminated. The following pieces of advice are relevant.

(1) The way to control the size of unwanted negative computed values is with tighter absolute tolerances. Again this requires some knowledge of the noise level of these components, which may or may not be different for different components. Some experimentation may be needed.

(2) If output plots or tables are being generated, and it is important to avoid having negative numbers appear there (for the sake of avoiding a long explanation of them, if nothing else), then eliminate them, but only in the context of the output medium. Then the internal values carried by the solver are unaffected. Remember that a small negative value in `yret` returned by IDA, with magnitude comparable to `abstol` or less, is equivalent to zero as far as the computation is concerned.

(3) The user's residual routine `res` should never change a negative value in the solution vector `yy` to a non-negative value, as a "solution" to this problem. This can cause instability. If the `res` routine cannot tolerate a zero or negative value (e.g. because there is a square root or log of it), then the offending value should be changed to zero or a tiny positive number in a temporary variable (not in the input `yy` vector) for the purposes of computing $F(t, y, \dot{y})$.

(4) IDA provides the option of enforcing positivity or non-negativity on components. Also, such constraints can be enforced by use of the recoverable error return feature in the user-supplied residual function. However, because these options involve some extra overhead cost, they should only be exercised if the use of absolute tolerances to control the computed values is unsuccessful.

4.5.3 Linear solver interface functions

As previously explained, if the nonlinear solver requires the solution of linear systems of the form (2.4) (e.g., the default Newton iteration), then solution of these linear systems is handled with the IDALS linear solver interface. This interface supports all valid SUNLINSOL modules. Here, matrix-based SUNLINSOL modules utilize SUNMATRIX objects to store the Jacobian matrix $J = \partial F / \partial y + \alpha \partial F / \partial \dot{y}$ and factorizations used throughout the solution process. Conversely, matrix-free SUNLINSOL modules instead use iterative methods to solve the linear systems of equations, and only require the *action* of the Jacobian on a vector, Jv .

With most iterative linear solvers, preconditioning can be done on the left only, on the right only, on both the left and the right, or not at all. The exceptions to this rule are SPFGMR that supports

right preconditioning only and PCG that performs symmetric preconditioning. However, in IDA only left preconditioning is supported. For the specification of a preconditioner, see the iterative linear solver sections in §4.5.8 and §4.6. A preconditioner matrix P must approximate the Jacobian J , at least crudely.

To specify a generic linear solver to IDA, after the call to `IDACreate` but before any calls to `IDASolve`, the user's program must create the appropriate `SUNLINSOL` object and call the function `IDASetLinearSolver`, as documented below. To create the `SUNLinearSolver` object, the user may call one of the SUNDIALS-packaged `SUNLINSOL` module constructor routines via a call of the form

```
SUNLinearSolver LS = SUNLinSol_*(...);
```

The current list of such constructor routines includes `SUNLinSol_Dense`, `SUNLinSol_Band`, `SUNLinSol_LapackDense`, `SUNLinSol_LapackBand`, `SUNLinSol_KLU`, `SUNLinSol_SuperLUMT`, `SUNLinSol_SPGMR`, `SUNLinSol_SPFGRM`, `SUNLinSol_SPBCGS`, `SUNLinSol_SPTFQMR`, and `SUNLinSol_PCG`.

Alternately, a user-supplied `SUNLinearSolver` module may be created and used instead. The use of each of the generic linear solvers involves certain constants, functions and possibly some macros, that are likely to be needed in the user code. These are available in the corresponding header file associated with the specific `SUNMATRIX` or `SUNLINSOL` module in question, as described in Chapters 7 and 8.

Once this solver object has been constructed, the user should attach it to IDA via a call to `IDASetLinearSolver`. The first argument passed to this function is the IDA memory pointer returned by `IDACreate`; the second argument is the desired `SUNLINSOL` object to use for solving systems. The third argument is an optional `SUNMATRIX` object to accompany matrix-based `SUNLINSOL` inputs (for matrix-free linear solvers, the third argument should be `NULL`). A call to this function initializes the IDALS linear solver interface, linking it to the main IDA integrator, and allows the user to specify additional parameters and routines pertinent to their choice of linear solver.

`IDASetLinearSolver`

| | |
|--------------|--|
| Call | <code>flag = IDASetLinearSolver(ida_mem, LS, J);</code> |
| Description | The function <code>IDASetLinearSolver</code> attaches a generic <code>SUNLINSOL</code> object <code>LS</code> and corresponding template Jacobian <code>SUNMATRIX</code> object <code>J</code> (if applicable) to IDA, initializing the IDALS linear solver interface. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>LS</code> (<code>SUNLinearSolver</code>) <code>SUNLINSOL</code> object to use for solving linear systems of the form (2.4).</p> <p><code>J</code> (<code>SUNMatrix</code>) <code>SUNMATRIX</code> object for used as a template for the Jacobian (or <code>NULL</code> if not applicable).</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDALS_SUCCESS</code> The IDALS initialization was successful.</p> <p><code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code>.</p> <p><code>IDALS_ILL_INPUT</code> The IDALS interface is not compatible with the <code>LS</code> or <code>J</code> input objects or is incompatible with the current <code>NVECTOR</code> module.</p> <p><code>IDALS_SUNLS_FAIL</code> A call to the <code>LS</code> object failed.</p> <p><code>IDALS_MEM_FAIL</code> A memory allocation request failed.</p> |
| Notes | <p>If <code>LS</code> is a matrix-based linear solver, then the template Jacobian matrix <code>J</code> will be used in the solve process, so if additional storage is required within the <code>SUNMATRIX</code> object (e.g. for factorization of a banded matrix), ensure that the input object is allocated with sufficient size (see the documentation of the particular <code>SUNMATRIX</code> type in Chapter 7 for further information).</p> <p>The previous routines <code>IDADlsSetLinearSolver</code> and <code>IDASpilsSetLinearSolver</code> are now wrappers for this routine, and may still be used for backward-compatibility. However, these will be deprecated in future releases, so we recommend that users transition to the new routine name soon.</p> |

4.5.4 Nonlinear solver interface function

By default IDA uses the SUNNONLINSOL implementation of Newton's method defined by the SUNNONLINSOL_NEWTON module (see §9.2). To specify a different nonlinear solver in IDA, the user's program must create a SUNNONLINSOL object by calling the appropriate constructor routine. The user must then attach the SUNNONLINSOL object to IDA by calling `IDASetNonlinearSolver`, as documented below.

When changing the nonlinear solver in IDA, `IDASetNonlinearSolver` must be called after `IDAInit`. If any calls to `IDASolve` have been made, then IDA will need to be reinitialized by calling `IDAReInit` to ensure that the nonlinear solver is initialized correctly before any subsequent calls to `IDASolve`.

The first argument passed to the routine `IDASetNonlinearSolver` is the IDA memory pointer returned by `IDACreate` and the second argument is the SUNNONLINSOL object to use for solving the nonlinear system 2.3. A call to this function attaches the nonlinear solver to the main IDA integrator. We note that at present, the SUNNONLINSOL object *must be of type* `SUNNONLINEARSOLVER_ROOTFIND`.

`IDASetNonlinearSolver`

Call `flag = IDASetNonlinearSolver(ida_mem, NLS);`

Description The function `IDASetNonLinearSolver` attaches a SUNNONLINSOL object (NLS) to IDA.

Arguments `ida_mem` (void *) pointer to the IDA memory block.
NLS (`SUNNonlinearSolver`) SUNNONLINSOL object to use for solving nonlinear systems.

Return value The return value `flag` (of type `int`) is one of

- `IDA_SUCCESS` The nonlinear solver was successfully attached.
- `IDA_MEM_NULL` The `ida_mem` pointer is NULL.
- `IDA_ILL_INPUT` The SUNNONLINSOL object is NULL, does not implement the required nonlinear solver operations, is not of the correct type, or the residual function, convergence test function, or maximum number of nonlinear iterations could not be set.

4.5.5 Initial condition calculation function

`IDACalcIC` calculates corrected initial conditions for the DAE system for certain index-one problems including a class of systems of semi-implicit form. (See §2.1 and Ref. [8].) It uses Newton iteration combined with a linesearch algorithm. Calling `IDACalcIC` is optional. It is only necessary when the initial conditions do not satisfy the given system. Thus if `y0` and `yp0` are known to satisfy $F(t_0, y_0, \dot{y}_0) = 0$, then a call to `IDACalcIC` is generally *not* necessary.

A call to the function `IDACalcIC` must be preceded by successful calls to `IDACreate` and `IDAInit` (or `IDARInit`), and by a successful call to the linear system solver specification function. The call to `IDACalcIC` should precede the call(s) to `IDASolve` for the given problem.

`IDACalcIC`

Call `flag = IDACalcIC(ida_mem, icopt, tout1);`

Description The function `IDACalcIC` corrects the initial values `y0` and `yp0` at time `t0`.

Arguments `ida_mem` (void *) pointer to the IDA memory block.
icopt (`int`) is one of the following two options for the initial condition calculation.
`icopt=IDA_YA_YDP_INIT` directs `IDACalcIC` to compute the algebraic components of y and differential components of \dot{y} , given the differential components of y . This option requires that the `N_Vector id` was set through `IDASetId`, specifying the differential and algebraic components.
`icopt=IDA_Y_INIT` directs `IDACalcIC` to compute all components of y , given \dot{y} . In this case, `id` is not required.

| | |
|----------------------------------|--|
| tout1 | (realtype) is the first value of t at which a solution will be requested (from <code>IDASolve</code>). This value is needed here only to determine the direction of integration and rough scale in the independent variable t . |
| Return value | The return value <code>flag</code> (of type <code>int</code>) will be one of the following: |
| <code>IDA_SUCCESS</code> | <code>IDASolve</code> succeeded. |
| <code>IDA_MEM_NULL</code> | The argument <code>ida_mem</code> was <code>NULL</code> . |
| <code>IDA_NO_MALLOC</code> | The allocation function <code>IDAInit</code> has not been called. |
| <code>IDA_ILL_INPUT</code> | One of the input arguments was illegal. |
| <code>IDA_LSETUP_FAIL</code> | The linear solver's setup function failed in an unrecoverable manner. |
| <code>IDA_LINIT_FAIL</code> | The linear solver's initialization function failed. |
| <code>IDA_LSOLVE_FAIL</code> | The linear solver's solve function failed in an unrecoverable manner. |
| <code>IDA_BAD_EWT</code> | Some component of the error weight vector is zero (illegal), either for the input value of <code>y0</code> or a corrected value. |
| <code>IDA_FIRST_RES_FAIL</code> | The user's residual function returned a recoverable error flag on the first call, but <code>IDACalcIC</code> was unable to recover. |
| <code>IDA_RES_FAIL</code> | The user's residual function returned a nonrecoverable error flag. |
| <code>IDA_NO_RECOVERY</code> | The user's residual function, or the linear solver's setup or solve function had a recoverable error, but <code>IDACalcIC</code> was unable to recover. |
| <code>IDA_CONSTR_FAIL</code> | <code>IDACalcIC</code> was unable to find a solution satisfying the inequality constraints. |
| <code>IDA_LINESEARCH_FAIL</code> | The linesearch algorithm failed to find a solution with a step larger than <code>steptol</code> in weighted RMS norm, and within the allowed number of backtracks. |
| <code>IDA_CONV_FAIL</code> | <code>IDACalcIC</code> failed to get convergence of the Newton iterations. |
| Notes | <p>All failure return values are negative and therefore a test <code>flag < 0</code> will trap all <code>IDACalcIC</code> failures.</p> <p>Note that <code>IDACalcIC</code> will correct the values of $y(t_0)$ and $\dot{y}(t_0)$ which were specified in the previous call to <code>IDAInit</code> or <code>IDAReInit</code>. To obtain the corrected values, call <code>IDAGetconsistentIC</code> (see §4.5.10.3).</p> |

4.5.6 Rootfinding initialization function

While integrating the IVP, IDA has the capability of finding the roots of a set of user-defined functions. To activate the rootfinding algorithm, call the following function. This is normally called only once, prior to the first call to `IDASolve`, but if the rootfinding problem is to be changed during the solution, `IDARootInit` can also be called prior to a continuation call to `IDASolve`.

`IDARootInit`

| | |
|--------------|--|
| Call | <code>flag = IDARootInit(ida_mem, nrtfn, g);</code> |
| Description | The function <code>IDARootInit</code> specifies that the roots of a set of functions $g_i(t, y, \dot{y})$ are to be found while the IVP is being solved. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block returned by <code>IDACreate</code>.</p> <p><code>nrtfn</code> (<code>int</code>) is the number of root functions g_i.</p> <p><code>g</code> (<code>IDARootFn</code>) is the C function which defines the <code>nrtfn</code> functions $g_i(t, y, \dot{y})$ whose roots are sought. See §4.6.4 for details.</p> |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of |

| | | |
|-------|----------------------|--|
| | IDA_SUCCESS | The call to <code>IDARootInit</code> was successful. |
| | IDA_MEM_NULL | The <code>ida_mem</code> argument was <code>NULL</code> . |
| | IDA_MEM_FAIL | A memory allocation failed. |
| | IDA_ILL_INPUT | The function <code>g</code> is <code>NULL</code> , but <code>nrtfn</code> > 0. |
| Notes | | If a new IVP is to be solved with a call to <code>IDAReInit</code> , where the new IVP has no rootfinding problem but the prior one did, then call <code>IDARootInit</code> with <code>nrtfn</code> = 0. |

4.5.7 IDA solver function

This is the central step in the solution process, the call to perform the integration of the DAE. One of the input arguments (`itask`) specifies one of two modes as to where IDA is to return a solution. But these modes are modified if the user has set a stop time (with `IDASetStopTime`) or requested rootfinding.

IDASolve

| | | |
|--------------|--|--|
| Call | <code>flag = IDASolve(ida_mem, tout, &tret, yret, ypret, itask);</code> | |
| Description | The function <code>IDASolve</code> integrates the DAE over an interval in t . | |
| Arguments | <code>ida_mem</code> | (void *) pointer to the IDA memory block. |
| | <code>tout</code> | (realtype) the next time at which a computed solution is desired. |
| | <code>tret</code> | (realtype) the time reached by the solver (output). |
| | <code>yret</code> | (N_Vector) the computed solution vector y . |
| | <code>ypret</code> | (N_Vector) the computed solution vector \dot{y} . |
| | <code>itask</code> | (int) a flag indicating the job of the solver for the next user step. The <code>IDA_NORMAL</code> task is to have the solver take internal steps until it has reached or just passed the user specified <code>tout</code> parameter. The solver then interpolates in order to return approximate values of $y(\text{tout})$ and $\dot{y}(\text{tout})$. The <code>IDA_ONE_STEP</code> option tells the solver to just take one internal step and return the solution at the point reached by that step. |
| Return value | <code>IDASolve</code> returns vectors <code>yret</code> and <code>ypret</code> and a corresponding independent variable value $t = \text{tret}$, such that (<code>yret</code> , <code>ypret</code>) are the computed values of ($y(t)$, $\dot{y}(t)$). | |
| | In <code>IDA_NORMAL</code> mode with no errors, <code>tret</code> will be equal to <code>tout</code> and <code>yret</code> = $y(\text{tout})$, <code>ypret</code> = $\dot{y}(\text{tout})$. | |
| | The return value <code>flag</code> (of type <code>int</code>) will be one of the following: | |
| | IDA_SUCCESS | <code>IDASolve</code> succeeded. |
| | IDA_TSTOP_RETURN | <code>IDASolve</code> succeeded by reaching the stop point specified through the optional input function <code>IDASetStopTime</code> . |
| | IDA_ROOT_RETURN | <code>IDASolve</code> succeeded and found one or more roots. In this case, <code>tret</code> is the location of the root. If <code>nrtfn</code> > 1, call <code>IDAGetRootInfo</code> to see which g_i were found to have a root. See §4.5.10.4 for more information. |
| | IDA_MEM_NULL | The <code>ida_mem</code> argument was <code>NULL</code> . |
| | IDA_ILL_INPUT | One of the inputs to <code>IDASolve</code> was illegal, or some other input to the solver was either illegal or missing. The latter category includes the following situations: (a) The tolerances have not been set. (b) A component of the error weight vector became zero during internal time-stepping. (c) The linear solver initialization function (called by the user after calling <code>IDACreate</code>) failed to set the linear solver-specific <code>lsolve</code> field in <code>ida_mem</code> . (d) A root of one of the root functions was found both at a point t and also very near t . In any case, the user should see the printed error message for details. |

| | |
|-------------------|---|
| IDA_TOO_MUCH_WORK | The solver took <code>mxstep</code> internal steps but could not reach <code>tout</code> . The default value for <code>mxstep</code> is <code>MXSTEP_DEFAULT = 500</code> . |
| IDA_TOO_MUCH_ACC | The solver could not satisfy the accuracy demanded by the user for some internal step. |
| IDA_ERR_FAIL | Error test failures occurred too many times (<code>MXNEF = 10</code>) during one internal time step or occurred with $ h = h_{min}$. |
| IDA_CONV_FAIL | Convergence test failures occurred too many times (<code>MXNCF = 10</code>) during one internal time step or occurred with $ h = h_{min}$. |
| IDA_LINIT_FAIL | The linear solver's initialization function failed. |
| IDA_LSETUP_FAIL | The linear solver's setup function failed in an unrecoverable manner. |
| IDA_LSOLVE_FAIL | The linear solver's solve function failed in an unrecoverable manner. |
| IDA_CONSTR_FAIL | The inequality constraints were violated and the solver was unable to recover. |
| IDA_REP_RES_ERR | The user's residual function repeatedly returned a recoverable error flag, but the solver was unable to recover. |
| IDA_RES_FAIL | The user's residual function returned a nonrecoverable error flag. |
| IDA_RTFUNC_FAIL | The rootfinding function failed. |

Notes The vector `yret` can occupy the same space as the vector `y0` of initial conditions that was passed to `IDAInit`, and the vector `ypret` can occupy the same space as `yp0`.

In the `IDA.ONE_STEP` mode, `tout` is used on the first call only, and only to get the direction and rough scale of the independent variable.

All failure return values are negative and therefore a test `flag < 0` will trap all `IDASolve` failures.

On any error return in which one or more internal steps were taken by `IDASolve`, the returned values of `tret`, `yret`, and `ypret` correspond to the farthest point reached in the integration. On all other error returns, these values are left unchanged from the previous `IDASolve` return.

4.5.8 Optional input functions

There are numerous optional input parameters that control the behavior of the IDA solver. IDA provides functions that can be used to change these optional input parameters from their default values. Table 4.2 lists all optional input functions in IDA which are then described in detail in the remainder of this section. For the most casual use of IDA, the reader can skip to §4.6.

We note that, on an error return, all these functions also send an error message to the error handler function. We also note that all error return values are negative, so a test `flag < 0` will catch any error.

4.5.8.1 Main solver optional input functions

The calls listed here can be executed in any order. However, if the user's program calls either `IDASetErrFile` or `IDASetErrHandlerFn`, then that call should appear first, in order to take effect for any later error message.

`IDASetErrFile`

Call `flag = IDASetErrFile(ida_mem, errfp);`

Description The function `IDASetErrFile` specifies the pointer to the file where all IDA messages should be directed when the default IDA error handler function is used.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.

Table 4.2: Optional inputs for IDA and IDALS

| Optional input | Function name | Default |
|---|--------------------------|-----------------------|
| IDA main solver | | |
| Pointer to an error file | IDASetErrFile | stderr |
| Error handler function | IDASetErrHandlerFn | internal fn. |
| User data | IDASetUserData | NULL |
| Maximum order for BDF method | IDASetMaxOrd | 5 |
| Maximum no. of internal steps before t_{out} | IDASetMaxNumSteps | 500 |
| Initial step size | IDASetInitStep | estimated |
| Maximum absolute step size | IDASetMaxStep | ∞ |
| Value of t_{stop} | IDASetStopTime | ∞ |
| Maximum no. of error test failures | IDASetMaxErrTestFails | 10 |
| Maximum no. of nonlinear iterations | IDASetMaxNonlinIters | 4 |
| Maximum no. of convergence failures | IDASetMaxConvFails | 10 |
| Maximum no. of error test failures | IDASetMaxErrTestFails | 7 |
| Coeff. in the nonlinear convergence test | IDASetNonlinConvCoef | 0.33 |
| Suppress alg. vars. from error test | IDASetSuppressAlg | SUNFALSE |
| Variable types (differential/algebraic) | IDASetId | NULL |
| Inequality constraints on solution | IDASetConstraints | NULL |
| Direction of zero-crossing | IDASetRootDirection | both |
| Disable rootfinding warnings | IDASetNoInactiveRootWarn | none |
| IDA initial conditions calculation | | |
| Coeff. in the nonlinear convergence test | IDASetNonlinConvCoefIC | 0.0033 |
| Maximum no. of steps | IDASetMaxNumStepsIC | 5 |
| Maximum no. of Jacobian/precond. evals. | IDASetMaxNumJacsIC | 4 |
| Maximum no. of Newton iterations | IDASetMaxNumItersIC | 10 |
| Max. linesearch backtracks per Newton iter. | IDASetMaxBacksIC | 100 |
| Turn off linesearch | IDASetLineSearchOffIC | SUNFALSE |
| Lower bound on Newton step | IDASetStepToleranceIC | around ^{2/3} |
| IDALS linear solver interface | | |
| Jacobian function | IDASetJacFn | DQ |
| Jacobian-times-vector function | IDASetJacTimes | NULL, DQ |
| Preconditioner functions | IDASetPreconditioner | NULL, NULL |
| Ratio between linear and nonlinear tolerances | IDASetEpsLin | 0.05 |
| Increment factor used in DQ Jv approx. | IDASetIncrementFactor | 1.0 |

errfp (FILE *) pointer to output file.

Return value The return value **flag** (of type **int**) is one of

IDA_SUCCESS The optional value has been successfully set.

IDA_MEM_NULL The **ida_mem** pointer is NULL.

Notes The default value for **errfp** is **stderr**.

Passing a value NULL disables all future error message output (except for the case in which the IDA memory pointer is NULL). This use of **IDASetErrFile** is strongly discouraged.

If **IDASetErrFile** is to be called, it should be called before any other optional input functions, in order to take effect for any later error message.



IDASetErrHandlerFn

Call **flag** = **IDASetErrHandlerFn**(**ida_mem**, **ehfun**, **eh_data**);

Description The function **IDASetErrHandlerFn** specifies the optional user-defined function to be used in handling error messages.

Arguments **ida_mem** (void *) pointer to the IDA memory block.

ehfun (**IDAErrorHandlerFn**) is the user's C error handler function (see §4.6.2).

eh_data (void *) pointer to user data passed to **ehfun** every time it is called.

Return value The return value **flag** (of type **int**) is one of

IDA_SUCCESS The function **ehfun** and data pointer **eh_data** have been successfully set.

IDA_MEM_NULL The **ida_mem** pointer is NULL.

Notes Error messages indicating that the IDA solver memory is NULL will always be directed to **stderr**.

IDASetUserData

Call **flag** = **IDASetUserData**(**ida_mem**, **user_data**);

Description The function **IDASetUserData** specifies the user data block **user_data** and attaches it to the main IDA memory block.

Arguments **ida_mem** (void *) pointer to the IDA memory block.

user_data (void *) pointer to the user data.

Return value The return value **flag** (of type **int**) is one of

IDA_SUCCESS The optional value has been successfully set.

IDA_MEM_NULL The **ida_mem** pointer is NULL.

Notes If specified, the pointer to **user_data** is passed to all user-supplied functions that have it as an argument. Otherwise, a NULL pointer is passed.

If **user_data** is needed in user linear solver or preconditioner functions, the call to **IDASetUserData** must be made *before* the call to specify the linear solver.



IDASetMaxOrd

Call **flag** = **IDASetMaxOrd**(**ida_mem**, **maxord**);

Description The function **IDASetMaxOrd** specifies the maximum order of the linear multistep method.

Arguments **ida_mem** (void *) pointer to the IDA memory block.

maxord (**int**) value of the maximum method order. This must be positive.

Return value The return value **flag** (of type **int**) is one of

| | | |
|-------|---------------|---|
| | IDA_SUCCESS | The optional value has been successfully set. |
| | IDA_MEM_NULL | The <code>ida_mem</code> pointer is NULL. |
| | IDA_ILL_INPUT | The input value <code>maxord</code> is ≤ 0 , or larger than its previous value. |
| Notes | | The default value is 5. If the input value exceeds 5, the value 5 will be used. Since <code>maxord</code> affects the memory requirements for the internal IDA memory block, its value cannot be increased past its previous value. |

IDASetMaxNumSteps

| | | |
|--------------|---|--|
| Call | <code>flag = IDASetMaxNumSteps(ida_mem, mxsteps);</code> | |
| Description | The function <code>IDASetMaxNumSteps</code> specifies the maximum number of steps to be taken by the solver in its attempt to reach the next output time. | |
| Arguments | <code>ida_mem</code> (void *) pointer to the IDA memory block. <code>mxsteps</code> (long int) maximum allowed number of steps. | |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of IDA_SUCCESS The optional value has been successfully set. IDA_MEM_NULL The <code>ida_mem</code> pointer is NULL. | |
| Notes | Passing <code>mxsteps = 0</code> results in IDA using the default value (500). Passing <code>mxsteps < 0</code> disables the test (<i>not recommended</i>). | |

IDASetInitStep

| | | |
|--------------|---|--|
| Call | <code>flag = IDASetInitStep(ida_mem, hin);</code> | |
| Description | The function <code>IDASetInitStep</code> specifies the initial step size. | |
| Arguments | <code>ida_mem</code> (void *) pointer to the IDA memory block. <code>hin</code> (realtype) value of the initial step size to be attempted. Pass 0.0 to have IDA use the default value. | |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of IDA_SUCCESS The optional value has been successfully set. IDA_MEM_NULL The <code>ida_mem</code> pointer is NULL. | |
| Notes | By default, IDA estimates the initial step as the solution of $\ h\dot{y}\ _{\text{WRMS}} = 1/2$, with an added restriction that $ h \leq .001 \text{tout} - \text{t0} $. | |

IDASetMaxStep

| | | |
|--------------|---|--|
| Call | <code>flag = IDASetMaxStep(ida_mem, hmax);</code> | |
| Description | The function <code>IDASetMaxStep</code> specifies the maximum absolute value of the step size. | |
| Arguments | <code>ida_mem</code> (void *) pointer to the IDA memory block. <code>hmax</code> (realtype) maximum absolute value of the step size. | |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of IDA_SUCCESS The optional value has been successfully set. IDA_MEM_NULL The <code>ida_mem</code> pointer is NULL. IDA_ILL_INPUT Either <code>hmax</code> is not positive or it is smaller than the minimum allowable step. | |
| Notes | Pass <code>hmax = 0</code> to obtain the default value ∞ . | |

IDASetStopTime

| | |
|--------------|---|
| Call | <code>flag = IDASetStopTime(ida_mem, tstop);</code> |
| Description | The function <code>IDASetStopTime</code> specifies the value of the independent variable t past which the solution is not to proceed. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>tstop</code> (<code>realtype</code>) value of the independent variable past which the solution should not proceed.</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is NULL.</p> <p><code>IDA_ILL_INPUT</code> The value of <code>tstop</code> is not beyond the current t value, t_n.</p> |
| Notes | The default, if this routine is not called, is that no stop time is imposed. |

IDASetMaxErrTestFails

| | |
|--------------|---|
| Call | <code>flag = IDASetMaxErrTestFails(ida_mem, maxnef);</code> |
| Description | The function <code>IDASetMaxErrTestFails</code> specifies the maximum number of error test failures in attempting one step. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>maxnef</code> (<code>int</code>) maximum number of error test failures allowed on one step (> 0).</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is NULL.</p> |
| Notes | The default value is 7. |

IDASetMaxNonlinIters

| | |
|--------------|--|
| Call | <code>flag = IDASetMaxNonlinIters(ida_mem, maxcor);</code> |
| Description | The function <code>IDASetMaxNonlinIters</code> specifies the maximum number of nonlinear solver iterations at one step. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>maxcor</code> (<code>int</code>) maximum number of nonlinear solver iterations allowed on one step (> 0).</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is NULL.</p> <p><code>IDA_MEM_FAIL</code> The <code>SUNNONLINSOL</code> module is NULL.</p> |
| Notes | The default value is 3. |

IDASetMaxConvFails

| | |
|-------------|---|
| Call | <code>flag = IDASetMaxConvFails(ida_mem, maxncf);</code> |
| Description | The function <code>IDASetMaxConvFails</code> specifies the maximum number of nonlinear solver convergence failures at one step. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>maxncf</code> (<code>int</code>) maximum number of allowable nonlinear solver convergence failures on one step (> 0).</p> |

Return value The return value `flag` (of type `int`) is one of
 `IDA_SUCCESS` The optional value has been successfully set.
 `IDA_MEM_NULL` The `ida_mem` pointer is NULL.
 Notes The default value is 10.

IDASetNonlinConvCoef

Call `flag = IDASetNonlinConvCoef(ida_mem, nlscoef);`
 Description The function `IDASetNonlinConvCoef` specifies the safety factor in the nonlinear convergence test; see Chapter 2, Eq. (2.7).
 Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
 `nlscoef` (`realtype`) coefficient in nonlinear convergence test (> 0.0).
 Return value The return value `flag` (of type `int`) is one of
 `IDA_SUCCESS` The optional value has been successfully set.
 `IDA_MEM_NULL` The `ida_mem` pointer is NULL.
 `IDA_ILL_INPUT` The value of `nlscoef` is ≤ 0.0 .
 Notes The default value is 0.33.

IDASetSuppressAlg

Call `flag = IDASetSuppressAlg(ida_mem, suppressalg);`
 Description The function `IDASetSuppressAlg` indicates whether or not to suppress algebraic variables in the local error test.
 Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
 `suppressalg` (`boolean_t`) indicates whether to suppress (`SUNTRUE`) or not (`SUNFALSE`) the algebraic variables in the local error test.
 Return value The return value `flag` (of type `int`) is one of
 `IDA_SUCCESS` The optional value has been successfully set.
 `IDA_MEM_NULL` The `ida_mem` pointer is NULL.
 Notes The default value is `SUNFALSE`.
 If `suppressalg=SUNTRUE` is selected, then the `id` vector must be set (through `IDASetId`) to specify the algebraic components.
 In general, the use of this option (with `suppressalg = SUNTRUE`) is *discouraged* when solving DAE systems of index 1, whereas it is generally *encouraged* for systems of index 2 or more. See pp. 146-147 of Ref. [4] for more on this issue.

IDASetId

Call `flag = IDASetId(ida_mem, id);`
 Description The function `IDASetId` specifies algebraic/differential components in the y vector.
 Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
 `id` (`N_Vector`) state vector. A value of 1.0 indicates a differential variable, while 0.0 indicates an algebraic variable.
 Return value The return value `flag` (of type `int`) is one of
 `IDA_SUCCESS` The optional value has been successfully set.
 `IDA_MEM_NULL` The `ida_mem` pointer is NULL.
 Notes The vector `id` is required if the algebraic variables are to be suppressed from the local error test (see `IDASetSuppressAlg`) or if `IDACalcIC` is to be called with `icopt = IDA_YA_YDP_INIT` (see §4.5.5).

IDASetConstraints

| | |
|--------------|---|
| Call | <code>flag = IDASetConstraints(ida_mem, constraints);</code> |
| Description | The function <code>IDASetConstraints</code> specifies a vector defining inequality constraints for each component of the solution vector y . |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>constraints</code> (<code>N_Vector</code>) vector of constraint flags. If <code>constraints[i]</code> is</p> <ul style="list-style-type: none"> 0.0 then no constraint is imposed on y_i. 1.0 then y_i will be constrained to be $y_i \geq 0.0$. -1.0 then y_i will be constrained to be $y_i \leq 0.0$. 2.0 then y_i will be constrained to be $y_i > 0.0$. -2.0 then y_i will be constrained to be $y_i < 0.0$. |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code>.</p> <p><code>IDA_ILL_INPUT</code> The constraints vector contains illegal values.</p> |
| Notes | The presence of a non- <code>NULL</code> constraints vector that is not 0.0 in all components will cause constraint checking to be performed. However, a call with 0.0 in all components of <code>constraints</code> will result in an illegal input return. |

4.5.8.2 Linear solver interface optional input functions

The mathematical explanation of the linear solver methods available to IDA is provided in §2.1. We group the user-callable routines into four categories: general routines concerning the overall IDALS linear solver interface, optional inputs for matrix-based linear solvers, optional inputs for matrix-free linear solvers, and optional inputs for iterative linear solvers. We note that the matrix-based and matrix-free groups are mutually exclusive, whereas the “iterative” tag can apply to either case.

When using matrix-based linear solver modules, the IDALS solver interface needs a function to compute an approximation to the Jacobian matrix $J(t, y, \dot{y})$. This function must be of type `IDALsJacFn`. The user can supply a Jacobian function, or if using a dense or banded matrix J can use the default internal difference quotient approximation that comes with the IDALS interface. To specify a user-supplied Jacobian function `jac`, IDALS provides the function `IDASetJacFn`. The IDALS interface passes the pointer `user_data` to the Jacobian function. This allows the user to create an arbitrary structure with relevant problem data and access it during the execution of the user-supplied Jacobian function, without using global data in the program. The pointer `user_data` may be specified through `IDASetUserData`.

IDASetJacFn

| | |
|--------------|--|
| Call | <code>flag = IDASetJacFn(ida_mem, jac);</code> |
| Description | The function <code>IDASetJacFn</code> specifies the Jacobian approximation function to be used for a matrix-based solver within the IDALS interface. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>jac</code> (<code>IDALsJacFn</code>) user-defined Jacobian approximation function.</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDALS_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code>.</p> <p><code>IDALS_LMEM_NULL</code> The IDALS linear solver interface has not been initialized.</p> |

Notes This function must be called *after* the IDALS linear solver interface has been initialized through a call to `IDASetLinearSolver`.

By default, IDALS uses an internal difference quotient function for dense and band matrices. If `NULL` is passed to `jac`, this default function is used. An error will occur if no `jac` is supplied when using other matrix types.

The function type `IDALsJacFn` is described in §4.6.5.

The previous routine `IDADlsSetJacFn` is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

When using matrix-free linear solver modules, the IDALS solver interface requires a function to compute an approximation to the product between the Jacobian matrix $J(t, y)$ and a vector v . The user can supply a Jacobian-times-vector approximation function, or use the default internal difference quotient function that comes with the IDALS solver interface. A user-defined Jacobian-vector function must be of type `IDALsJacTimesVecFn` and can be specified through a call to `IDASetJacTimes` (see §4.6.6 for specification details). The evaluation and processing of any Jacobian-related data needed by the user's Jacobian-times-vector function may be done in the optional user-supplied function `jtsetup` (see §4.6.7 for specification details). The pointer `user_data` received through `IDASetUserData` (or a pointer to `NULL` if `user_data` was not specified) is passed to the Jacobian-times-vector setup and product functions, `jtsetup` and `jtimes`, each time they are called. This allows the user to create an arbitrary structure with relevant problem data and access it during the execution of the user-supplied functions without using global data in the program.

`IDASetJacTimes`

Call `flag = IDASetJacTimes(ida_mem, jsetup, jtimes);`

Description The function `IDASetJacTimes` specifies the Jacobian-vector setup and product functions.

Arguments

- `ida_mem` (`void *`) pointer to the IDA memory block.
- `jtsetup` (`IDALsJacTimesSetupFn`) user-defined function to set up the Jacobian-vector product. Pass `NULL` if no setup is necessary.
- `jtimes` (`IDALsJacTimesVecFn`) user-defined Jacobian-vector product function.

Return value The return value `flag` (of type `int`) is one of

- `IDALS_SUCCESS` The optional value has been successfully set.
- `IDALS_MEM_NULL` The `ida_mem` pointer is `NULL`.
- `IDALS_LMEM_NULL` The IDALS linear solver has not been initialized.
- `IDALS_SUNLS_FAIL` An error occurred when setting up the system matrix-times-vector routines in the `SUNLINSOL` object used by the IDALS interface.

Notes

The default is to use an internal finite difference quotient for `jtimes` and to omit `jtsetup`. If `NULL` is passed to `jtimes`, these defaults are used. A user may specify non-`NULL` `jtimes` and `NULL` `jtsetup` inputs.

This function must be called *after* the IDALS linear solver interface has been initialized through a call to `IDASetLinearSolver`.

The function type `IDALsJacTimesSetupFn` is described in §4.6.7.

The function type `IDALsJacTimesVecFn` is described in §4.6.6.

The previous routine `IDASpilsSetJacTimes` is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

Alternately, when using the default difference-quotient approximation to the Jacobian-vector product, the user may specify the factor to use in setting increments for the finite-difference approximation, via a call to `IDASetIncrementFactor`:

IDASetIncrementFactor

Call `flag = IDASetIncrementFactor(ida_mem, dqincfac);`

Description The function `IDASetIncrementFactor` specifies the increment factor to be used in the difference-quotient approximation to the product Jv . Specifically, Jv is approximated via the formula

$$Jv = \frac{1}{\sigma} [F(t, \tilde{y}, \tilde{y}') - F(t, y, y')],$$

where $\tilde{y} = y + \sigma v$, $\tilde{y}' = y' + c_j \sigma v$, c_j is a BDF parameter proportional to the step size, $\sigma = \sqrt{N} \text{dqincfac}$, and N is the number of equations in the DAE system.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`dqincfac` (`realtype`) user-specified increment factor (positive).

Return value The return value `flag` (of type `int`) is one of

`IDALS_SUCCESS` The optional value has been successfully set.
`IDALS_MEM_NULL` The `ida_mem` pointer is `NULL`.
`IDALS_LMEM_NULL` The IDALS linear solver has not been initialized.
`IDALS_ILL_INPUT` The specified value of `dqincfac` is ≤ 0 .

Notes The default value is 1.0.

This function must be called *after* the IDALS linear solver interface has been initialized through a call to `IDASetLinearSolver`.

The previous routine `IDASpilsSetIncrementFactor` is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

When using an iterative linear solver, the user may supply a preconditioning operator to aid in solution of the system. This operator consists of two user-supplied functions, `psetup` and `psolve`, that are supplied to IDA using the function `IDASetPreconditioner`. The `psetup` function supplied to this routine should handle evaluation and preprocessing of any Jacobian data needed by the user's preconditioner solve function, `psolve`. Both of these functions are fully specified in §4.6. The user data pointer received through `IDASetUserData` (or a pointer to `NULL` if user data was not specified) is passed to the `psetup` and `psolve` functions. This allows the user to create an arbitrary structure with relevant problem data and access it during the execution of the user-supplied preconditioner functions without using global data in the program.

Also, as described in §2.1, the IDALS interface requires that iterative linear solvers stop when the norm of the preconditioned residual satisfies

$$\|r\| \leq \frac{\epsilon_L \epsilon}{10}$$

where ϵ is the nonlinear solver tolerance, and the default $\epsilon_L = 0.05$; this value may be modified by the user through the `IDASetEpsLin` function.

IDASetPreconditioner

Call `flag = IDASetPreconditioner(ida_mem, psetup, psolve);`

Description The function `IDASetPreconditioner` specifies the preconditioner setup and solve functions.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`psetup` (`IDALsPrecSetupFn`) user-defined function to set up the preconditioner. Pass `NULL` if no setup is necessary.
`psolve` (`IDALsPrecSolveFn`) user-defined preconditioner solve function.

Return value The return value `flag` (of type `int`) is one of

`IDALS_SUCCESS` The optional values have been successfully set.

| | |
|-------|---|
| | <p>IDALS_MEM_NULL The <code>ida_mem</code> pointer is NULL.</p> <p>IDALS_LMEM_NULL The IDALS linear solver has not been initialized.</p> <p>IDALS_SUNLS_FAIL An error occurred when setting up preconditioning in the SUNLINSOL object used by the IDALS interface.</p> |
| Notes | <p>The default is NULL for both arguments (i.e., no preconditioning).</p> <p>This function must be called <i>after</i> the IDALS linear solver interface has been initialized through a call to <code>IDASetLinearSolver</code>.</p> <p>The function type <code>IDALSPrecSolveFn</code> is described in §4.6.8.</p> <p>The function type <code>IDALSPrecSetupFn</code> is described in §4.6.9.</p> <p>The previous routine <code>IDASpilsSetPreconditioner</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.</p> |

IDASetEpsLin

| | |
|--------------|---|
| Call | <code>flag = IDASetEpsLin(ida_mem, eplifac);</code> |
| Description | The function <code>IDASetEpsLin</code> specifies the factor by which the Krylov linear solver's convergence test constant is reduced from the nonlinear iteration test constant. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>eplifac</code> (<code>realtype</code>) linear convergence safety factor (≥ 0.0).</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p>IDALS_SUCCESS The optional value has been successfully set.</p> <p>IDALS_MEM_NULL The <code>ida_mem</code> pointer is NULL.</p> <p>IDALS_LMEM_NULL The IDALS linear solver has not been initialized.</p> <p>IDALS_ILL_INPUT The factor <code>eplifac</code> is negative.</p> |
| Notes | <p>The default value is 0.05.</p> <p>This function must be called <i>after</i> the IDALS linear solver interface has been initialized through a call to <code>IDASetLinearSolver</code>.</p> <p>If <code>eplifac= 0.0</code> is passed, the default value is used.</p> <p>The previous routine <code>IDASpilsSetEpsLin</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.</p> |

4.5.8.3 Initial condition calculation optional input functions

The following functions can be called just prior to calling `IDACalcIC` to set optional inputs controlling the initial condition calculation.

IDASetNonlinConvCoefIC

| | |
|--------------|---|
| Call | <code>flag = IDASetNonlinConvCoefIC(ida_mem, epiccon);</code> |
| Description | The function <code>IDASetNonlinConvCoefIC</code> specifies the positive constant in the Newton iteration convergence test within the initial condition calculation. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>epiccon</code> (<code>realtype</code>) coefficient in the Newton convergence test (> 0).</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p>IDA_SUCCESS The optional value has been successfully set.</p> <p>IDA_MEM_NULL The <code>ida_mem</code> pointer is NULL.</p> |

IDA_ILL_INPUT The `epiccon` factor is ≤ 0.0 .

Notes The default value is $0.01 \cdot 0.33$.

This test uses a weighted RMS norm (with weights defined by the tolerances). For new initial value vectors y and \dot{y} to be accepted, the norm of $J^{-1}F(t_0, y, \dot{y})$ must be $\leq \text{epiccon}$, where J is the system Jacobian.

IDASetMaxNumStepsIC

Call `flag = IDASetMaxNumStepsIC(ida_mem, maxnh);`

Description The function `IDASetMaxNumStepsIC` specifies the maximum number of steps allowed when `icopt=IDA_YA_YDP_INIT` in `IDACalcIC`, where h appears in the system Jacobian, $J = \partial F / \partial y + (1/h) \partial F / \partial \dot{y}$.

Arguments `ida_mem` (void *) pointer to the IDA memory block.
`maxnh` (int) maximum allowed number of values for h .

Return value The return value `flag` (of type `int`) is one of
 IDA_SUCCESS The optional value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.
 IDA_ILL_INPUT `maxnh` is non-positive.

Notes The default value is 5.

IDASetMaxNumJacsIC

Call `flag = IDASetMaxNumJacsIC(ida_mem, maxnj);`

Description The function `IDASetMaxNumJacsIC` specifies the maximum number of the approximate Jacobian or preconditioner evaluations allowed when the Newton iteration appears to be slowly converging.

Arguments `ida_mem` (void *) pointer to the IDA memory block.
`maxnj` (int) maximum allowed number of Jacobian or preconditioner evaluations.

Return value The return value `flag` (of type `int`) is one of
 IDA_SUCCESS The optional value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.
 IDA_ILL_INPUT `maxnj` is non-positive.

Notes The default value is 4.

IDASetMaxNumItersIC

Call `flag = IDASetMaxNumItersIC(ida_mem, maxnit);`

Description The function `IDASetMaxNumItersIC` specifies the maximum number of Newton iterations allowed in any one attempt to solve the initial conditions calculation problem.

Arguments `ida_mem` (void *) pointer to the IDA memory block.
`maxnit` (int) maximum number of Newton iterations.

Return value The return value `flag` (of type `int`) is one of
 IDA_SUCCESS The optional value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.
 IDA_ILL_INPUT `maxnit` is non-positive.

Notes The default value is 10.

IDASetMaxBacksIC

| | |
|--------------|--|
| Call | <code>flag = IDASetMaxBacksIC(ida_mem, maxbacks);</code> |
| Description | The function <code>IDASetMaxBacksIC</code> specifies the maximum number of linesearch backtracks allowed in any Newton iteration, when solving the initial conditions calculation problem. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>maxbacks</code> (<code>int</code>) maximum number of linesearch backtracks per Newton step. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDA_ILL_INPUT</code> <code>maxbacks</code> is non-positive. |
| Notes | The default value is 100. |

IDASetLineSearchOffIC

| | |
|--------------|---|
| Call | <code>flag = IDASetLineSearchOffIC(ida_mem, lsoff);</code> |
| Description | The function <code>IDASetLineSearchOffIC</code> specifies whether to turn on or off the linesearch algorithm. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>lsoff</code> (<code>boolean_t</code>) a flag to turn off (<code>SUNTRUE</code>) or keep (<code>SUNFALSE</code>) the linesearch algorithm. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |
| Notes | The default value is <code>SUNFALSE</code> . |

IDASetStepToleranceIC

| | |
|--------------|--|
| Call | <code>flag = IDASetStepToleranceIC(ida_mem, steptol);</code> |
| Description | The function <code>IDASetStepToleranceIC</code> specifies a positive lower bound on the Newton step. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>steptol</code> (<code>int</code>) Minimum allowed WRMS-norm of the Newton step (> 0.0). |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDA_ILL_INPUT</code> The <code>steptol</code> tolerance is ≤ 0.0 . |
| Notes | The default value is $(\text{unit roundoff})^{2/3}$. |

4.5.8.4 Rootfinding optional input functions

The following functions can be called to set optional inputs to control the rootfinding algorithm.

IDASetRootDirection

| | |
|--------------|---|
| Call | <code>flag = IDASetRootDirection(ida_mem, rootdir);</code> |
| Description | The function <code>IDASetRootDirection</code> specifies the direction of zero-crossings to be located and returned to the user. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>rootdir</code> (<code>int *</code>) state array of length <code>nrtfn</code>, the number of root functions g_i, as specified in the call to the function <code>IDARootInit</code>. A value of 0 for <code>rootdir[i]</code> indicates that crossing in either direction should be reported for g_i. A value of +1 or -1 indicates that the solver should report only zero-crossings where g_i is increasing or decreasing, respectively.</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is NULL.</p> <p><code>IDA_ILL_INPUT</code> rootfinding has not been activated through a call to <code>IDARootInit</code>.</p> |
| Notes | The default behavior is to locate both zero-crossing directions. |

IDASetNoInactiveRootWarn

| | |
|--------------|--|
| Call | <code>flag = IDASetNoInactiveRootWarn(ida_mem);</code> |
| Description | The function <code>IDASetNoInactiveRootWarn</code> disables issuing a warning if some root function appears to be identically zero at the beginning of the integration. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is NULL.</p> |
| Notes | IDA will not report the initial conditions as a possible zero-crossing (assuming that one or more components g_i are zero at the initial time). However, if it appears that some g_i is identically zero at the initial time (i.e., g_i is zero at the initial time and after the first step), IDA will issue a warning which can be disabled with this optional input function. |

4.5.9 Interpolated output function

An optional function `IDAGetDky` is available to obtain additional output values. This function must be called after a successful return from `IDASolve` and provides interpolated values of y or its derivatives of order up to the last internal order used for any value of t in the last internal step taken by IDA.

The call to the `IDAGetDky` function has the following form:

IDAGetDky

| | |
|-------------|--|
| Call | <code>flag = IDAGetDky(ida_mem, t, k, dky);</code> |
| Description | The function <code>IDAGetDky</code> computes the interpolated values of the k^{th} derivative of y for any value of t in the last internal step taken by IDA. The value of k must be non-negative and smaller than the last internal order used. A value of 0 for k means that the y is interpolated. The value of t must satisfy $t_n - h_u \leq t \leq t_n$, where t_n denotes the current internal time reached, and h_u is the last internal step size used successfully. |
| Arguments | <p><code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block.</p> <p><code>t</code> (<code>realtype</code>) time at which to interpolate.</p> <p><code>k</code> (<code>int</code>) integer specifying the order of the derivative of y wanted.</p> <p><code>dky</code> (<code>N_Vector</code>) vector containing the interpolated k^{th} derivative of $y(t)$.</p> |

| | |
|--------------|---|
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <ul style="list-style-type: none"> <code>IDA_SUCCESS</code> <code>IDAGetDky</code> succeeded. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> argument was <code>NULL</code>. <code>IDA_BAD_T</code> <code>t</code> is not in the interval $[t_n - h_u, t_n]$. <code>IDA_BAD_K</code> <code>k</code> is not one of $\{0, 1, \dots, klast\}$. <code>IDA_BAD_DKY</code> <code>dky</code> is <code>NULL</code>. |
| Notes | It is only legal to call the function <code>IDAGetDky</code> after a successful return from <code>IDASolve</code> . Functions <code>IDAGetCurrentTime</code> , <code>IDAGetLastStep</code> and <code>IDAGetLastOrder</code> (see §4.5.10.2) can be used to access t_n , h_u and $klast$. |

4.5.10 Optional output functions

IDA provides an extensive list of functions that can be used to obtain solver performance information. Table 4.3 lists all optional output functions in IDA, which are then described in detail in the remainder of this section.

Some of the optional outputs, especially the various counters, can be very useful in determining how successful the IDA solver is in doing its job. For example, the counters `nsteps` and `nrevals` provide a rough measure of the overall cost of a given run, and can be compared among runs with differing input options to suggest which set of options is most efficient. The ratio `nniters/nsteps` measures the performance of the nonlinear solver in solving the nonlinear systems at each time step; typical values for this range from 1.1 to 1.8. The ratio `njevals/nniters` (in the case of a matrix-based linear solver), and the ratio `npevals/nniters` (in the case of an iterative linear solver) measure the overall degree of nonlinearity in these systems, and also the quality of the approximate Jacobian or preconditioner being used. Thus, for example, `njevals/nniters` can indicate if a user-supplied Jacobian is inaccurate, if this ratio is larger than for the case of the corresponding internal Jacobian. The ratio `nliters/nniters` measures the performance of the Krylov iterative linear solver, and thus (indirectly) the quality of the preconditioner.

4.5.10.1 SUNDIALS version information

The following functions provide a way to get SUNDIALS version information at runtime.

SUNDIALSGetVersion

| | |
|--------------|--|
| Call | <code>flag = SUNDIALSGetVersion(version, len);</code> |
| Description | The function <code>SUNDIALSGetVersion</code> fills a character array with SUNDIALS version information. |
| Arguments | <code>version</code> (<code>char *</code>) character array to hold the SUNDIALS version information. <code>len</code> (<code>int</code>) allocated length of the <code>version</code> character array. |
| Return value | If successful, <code>SUNDIALSGetVersion</code> returns 0 and <code>version</code> contains the SUNDIALS version information. Otherwise, it returns <code>-1</code> and <code>version</code> is not set (the input character array is too short). |
| Notes | A string of 25 characters should be sufficient to hold the version information. Any trailing characters in the <code>version</code> array are removed. |

SUNDIALSGetVersionNumber

| | |
|-------------|--|
| Call | <code>flag = SUNDIALSGetVersionNumber(&major, &minor, &patch, label, len);</code> |
| Description | The function <code>SUNDIALSGetVersionNumber</code> set integers for the SUNDIALS major, minor, and patch release numbers and fills a character array with the release label if applicable. |
| Arguments | <code>major</code> (<code>int</code>) SUNDIALS release major version number. |

Table 4.3: Optional outputs from IDA and IDALS

| Optional output | Function name |
|---|------------------------------|
| IDA main solver | |
| Size of IDA real and integer workspace | IDAGetWorkSpace |
| Cumulative number of internal steps | IDAGetNumSteps |
| No. of calls to residual function | IDAGetNumResEvals |
| No. of calls to linear solver setup function | IDAGetNumLinSolvSetups |
| No. of local error test failures that have occurred | IDAGetNumErrTestFails |
| Order used during the last step | IDAGetLastOrder |
| Order to be attempted on the next step | IDAGetCurrentOrder |
| Order reductions due to stability limit detection | IDAGetNumStabLimOrderReds |
| Actual initial step size used | IDAGetActualInitStep |
| Step size used for the last step | IDAGetLastStep |
| Step size to be attempted on the next step | IDAGetCurrentStep |
| Current internal time reached by the solver | IDAGetCurrentTime |
| Suggested factor for tolerance scaling | IDAGetTolScaleFactor |
| Error weight vector for state variables | IDAGetErrWeights |
| Estimated local errors | IDAGetEstLocalErrors |
| No. of nonlinear solver iterations | IDAGetNumNonlinSolvIters |
| No. of nonlinear convergence failures | IDAGetNumNonlinSolvConvFails |
| Array showing roots found | IDAGetRootInfo |
| No. of calls to user root function | IDAGetNumGEvals |
| Name of constant associated with a return flag | IDAGetReturnFlagName |
| IDA initial conditions calculation | |
| Number of backtrack operations | IDAGetNumBacktrackops |
| Corrected initial conditions | IDAGetConsistentIC |
| IDALS linear solver interface | |
| Size of real and integer workspace | IDAGetLinWorkSpace |
| No. of Jacobian evaluations | IDAGetNumJacEvals |
| No. of residual calls for finite diff. Jacobian[-vector] evals. | IDAGetNumLinResEvals |
| No. of linear iterations | IDAGetNumLinIters |
| No. of linear convergence failures | IDAGetNumLinConvFails |
| No. of preconditioner evaluations | IDAGetNumPrecEvals |
| No. of preconditioner solves | IDAGetNumPrecSolves |
| No. of Jacobian-vector setup evaluations | IDAGetNumJTSetupEvals |
| No. of Jacobian-vector product evaluations | IDAGetNumJtimesEvals |
| Last return from a linear solver function | IDAGetLastLinFlag |
| Name of constant associated with a return flag | IDAGetLinReturnFlagName |

| | |
|--------------|--|
| | minor (int) SUNDIALS release minor version number. |
| | patch (int) SUNDIALS release patch version number. |
| | label (char *) character array to hold the SUNDIALS release label. |
| | len (int) allocated length of the label character array. |
| Return value | If successful, SUNDIALSGetVersionNumber returns 0 and the major , minor , patch , and label values are set. Otherwise, it returns -1 and the values are not set (the input character array is too short). |
| Notes | A string of 10 characters should be sufficient to hold the label information. If a label is not used in the release version, no information is copied to label . Any trailing characters in the label array are removed. |

4.5.10.2 Main solver optional output functions

IDA provides several user-callable functions that can be used to obtain different quantities that may be of interest to the user, such as solver workspace requirements, solver performance statistics, as well as additional data from the IDA memory block (a suggested tolerance scaling factor, the error weight vector, and the vector of estimated local errors). Also provided are functions to extract statistics related to the performance of the SUNNONLINSOL nonlinear solver being used. As a convenience, additional extraction functions provide the optional outputs in groups. These optional output functions are described next.

IDAGetWorkSpace

| | |
|--------------|---|
| Call | <code>flag = IDAGetWorkSpace(ida_mem, &lenrw, &leniw);</code> |
| Description | The function IDAGetWorkSpace returns the IDA real and integer workspace sizes. |
| Arguments | ida_mem (void *) pointer to the IDA memory block. lenrw (long int) number of real values in the IDA workspace. leniw (long int) number of integer values in the IDA workspace. |
| Return value | The return value flag (of type int) is one of IDA_SUCCESS The optional output value has been successfully set. IDA_MEM_NULL The ida_mem pointer is NULL. |
| Notes | In terms of the problem size N , the maximum method order maxord , and the number nrtfn of root functions (see §4.5.6), the actual size of the real workspace, in realtype words, is given by the following: |

- base value: $\text{lenrw} = 55 + (m + 6) * N_r + 3 * \text{nrtfn}$;
- with **IDASVtolerances**: $\text{lenrw} = \text{lenrw} + N_r$;
- with constraint checking (see **IDASetConstraints**): $\text{lenrw} = \text{lenrw} + N_r$;
- with **id** specified (see **IDASetId**): $\text{lenrw} = \text{lenrw} + N_r$;

where $m = \max(\text{maxord}, 3)$, and N_r is the number of real words in one **N_Vector** ($\approx N$).

The size of the integer workspace (without distinction between **int** and **long int** words) is given by:

- base value: $\text{leniw} = 38 + (m + 6) * N_i + \text{nrtfn}$;
- with **IDASVtolerances**: $\text{leniw} = \text{leniw} + N_i$;
- with constraint checking: $\text{leniw} = \text{leniw} + N_i$;
- with **id** specified: $\text{leniw} = \text{leniw} + N_i$;

where N_i is the number of integer words in one `N_Vector` (= 1 for `NVECTOR_SERIAL` and $2 \times \text{npes}$ for `NVECTOR_PARALLEL` on `npes` processors).

For the default value of `maxord`, with no rootfinding, no `id`, no constraints, and with no call to `IDASVtolerances`, these lengths are given roughly by: `lenrw` = $55 + 11N$, `leniw` = 49.

IDAGetNumSteps

Call `flag = IDAGetNumSteps(ida_mem, &nsteps);`

Description The function `IDAGetNumSteps` returns the cumulative number of internal steps taken by the solver (total so far).

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`nsteps` (`long int`) number of steps taken by IDA.

Return value The return value `flag` (of type `int`) is one of
`IDA_SUCCESS` The optional output value has been successfully set.
`IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetNumResEvals

Call `flag = IDAGetNumResEvals(ida_mem, &nrevals);`

Description The function `IDAGetNumResEvals` returns the number of calls to the user's residual evaluation function.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`nrevals` (`long int`) number of calls to the user's `res` function.

Return value The return value `flag` (of type `int`) is one of
`IDA_SUCCESS` The optional output value has been successfully set.
`IDA_MEM_NULL` The `ida_mem` pointer is NULL.

Notes The `nrevals` value returned by `IDAGetNumResEvals` does not account for calls made to `res` from a linear solver or preconditioner module.

IDAGetNumLinSolvSetups

Call `flag = IDAGetNumLinSolvSetups(ida_mem, &nlinsetups);`

Description The function `IDAGetNumLinSolvSetups` returns the cumulative number of calls made to the linear solver's setup function (total so far).

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`nlinsetups` (`long int`) number of calls made to the linear solver setup function.

Return value The return value `flag` (of type `int`) is one of
`IDA_SUCCESS` The optional output value has been successfully set.
`IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetNumErrTestFails

Call `flag = IDAGetNumErrTestFails(ida_mem, &netfails);`

Description The function `IDAGetNumErrTestFails` returns the cumulative number of local error test failures that have occurred (total so far).

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`netfails` (`long int`) number of error test failures.

Return value The return value `flag` (of type `int`) is one of

- `IDA_SUCCESS` The optional output value has been successfully set.
- `IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetLastOrder

Call `flag = IDAGetLastOrder(ida_mem, &klast);`

Description The function `IDAGetLastOrder` returns the integration method order used during the last internal step.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`klast` (`int`) method order used on the last internal step.

Return value The return value `flag` (of type `int`) is one of

- `IDA_SUCCESS` The optional output value has been successfully set.
- `IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetCurrentOrder

Call `flag = IDAGetCurrentOrder(ida_mem, &kcur);`

Description The function `IDAGetCurrentOrder` returns the integration method order to be used on the next internal step.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`kcur` (`int`) method order to be used on the next internal step.

Return value The return value `flag` (of type `int`) is one of

- `IDA_SUCCESS` The optional output value has been successfully set.
- `IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetLastStep

Call `flag = IDAGetLastStep(ida_mem, &hlast);`

Description The function `IDAGetLastStep` returns the integration step size taken on the last internal step.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`hlast` (`realtype`) step size taken on the last internal step by IDA, or last artificial step size used in `IDACalcIC`, whichever was called last.

Return value The return value `flag` (of type `int`) is one of

- `IDA_SUCCESS` The optional output value has been successfully set.
- `IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetCurrentStep

Call `flag = IDAGetCurrentStep(ida_mem, &hcur);`

Description The function `IDAGetCurrentStep` returns the integration step size to be attempted on the next internal step.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`hcur` (`realtype`) step size to be attempted on the next internal step.

Return value The return value `flag` (of type `int`) is one of

- `IDA_SUCCESS` The optional output value has been successfully set.
- `IDA_MEM_NULL` The `ida_mem` pointer is NULL.

IDAGetActualInitStep

| | |
|--------------|---|
| Call | <code>flag = IDAGetActualInitStep(ida_mem, &hinused);</code> |
| Description | The function <code>IDAGetActualInitStep</code> returns the value of the integration step size used on the first step. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>hinused</code> (<code>realtype</code>) actual value of initial step size. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |
| Notes | Even if the value of the initial integration step size was specified by the user through a call to <code>IDASetInitStep</code> , this value might have been changed by IDA to ensure that the step size is within the prescribed bounds ($h_{\min} \leq h_0 \leq h_{\max}$), or to meet the local error test. |

IDAGetCurrentTime

| | |
|--------------|--|
| Call | <code>flag = IDAGetCurrentTime(ida_mem, &tcure);</code> |
| Description | The function <code>IDAGetCurrentTime</code> returns the current internal time reached by the solver. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>tcure</code> (<code>realtype</code>) current internal time reached. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |

IDAGetTolScaleFactor

| | |
|--------------|--|
| Call | <code>flag = IDAGetTolScaleFactor(ida_mem, &tolsfac);</code> |
| Description | The function <code>IDAGetTolScaleFactor</code> returns a suggested factor by which the user's tolerances should be scaled when too much accuracy has been requested for some internal step. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>tolsfac</code> (<code>realtype</code>) suggested scaling factor for user tolerances. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |

IDAGetErrWeights

| | |
|--------------|--|
| Call | <code>flag = IDAGetErrWeights(ida_mem, eweight);</code> |
| Description | The function <code>IDAGetErrWeights</code> returns the solution error weights at the current time. These are the W_i given by Eq. (2.6) (or by the user's <code>IDAErrFn</code>). |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>eweight</code> (<code>N_Vector</code>) solution error weights at the current time. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |
| Notes | The user must allocate space for <code>eweight</code> . |



IDAGetEstLocalErrors

| | |
|--------------|--|
| Call | <code>flag = IDAGetEstLocalErrors(ida_mem, ele);</code> |
| Description | The function <code>IDAGetEstLocalErrors</code> returns the estimated local errors. |
| Arguments | <p><code>ida_mem</code> (void *) pointer to the IDA memory block.</p> <p><code>ele</code> (N.Vector) estimated local errors at the current time.</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> The optional output value has been successfully set.</p> <p><code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is NULL.</p> |
| Notes | <p>The user must allocate space for <code>ele</code>.</p> <p>The values returned in <code>ele</code> are only valid if <code>IDASolve</code> returned a non-negative value.</p> <p>The <code>ele</code> vector, together with the <code>eweight</code> vector from <code>IDAGetErrWeights</code>, can be used to determine how the various components of the system contributed to the estimated local error test. Specifically, that error test uses the RMS norm of a vector whose components are the products of the components of these two vectors. Thus, for example, if there were recent error test failures, the components causing the failures are those with largest values for the products, denoted loosely as <code>eweight[i]*ele[i]</code>.</p> |

**IDAGetIntegratorStats**

| | |
|--------------|---|
| Call | <code>flag = IDAGetIntegratorStats(ida_mem, &nsteps, &nrevals, &nlinsetups, &netfails, &klast, &kcur, &hinused, &hlast, &hcur, &tcur);</code> |
| Description | The function <code>IDAGetIntegratorStats</code> returns the IDA integrator statistics as a group. |
| Arguments | <p><code>ida_mem</code> (void *) pointer to the IDA memory block.</p> <p><code>nsteps</code> (long int) cumulative number of steps taken by IDA.</p> <p><code>nrevals</code> (long int) cumulative number of calls to the user's <code>res</code> function.</p> <p><code>nlinsetups</code> (long int) cumulative number of calls made to the linear solver setup function.</p> <p><code>netfails</code> (long int) cumulative number of error test failures.</p> <p><code>klast</code> (int) method order used on the last internal step.</p> <p><code>kcur</code> (int) method order to be used on the next internal step.</p> <p><code>hinused</code> (realtype) actual value of initial step size.</p> <p><code>hlast</code> (realtype) step size taken on the last internal step.</p> <p><code>hcur</code> (realtype) step size to be attempted on the next internal step.</p> <p><code>tcur</code> (realtype) current internal time reached.</p> |
| Return value | <p>The return value <code>flag</code> (of type <code>int</code>) is one of</p> <p><code>IDA_SUCCESS</code> the optional output values have been successfully set.</p> <p><code>IDA_MEM_NULL</code> the <code>ida_mem</code> pointer is NULL.</p> |

IDAGetNumNonlinSolvIters

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumNonlinSolvIters(ida_mem, &nniters);</code> |
| Description | The function <code>IDAGetNumNonlinSolvIters</code> returns the cumulative number of nonlinear iterations performed. |
| Arguments | <p><code>ida_mem</code> (void *) pointer to the IDA memory block.</p> <p><code>nniters</code> (long int) number of nonlinear iterations performed.</p> |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of |

IDA_SUCCESS The optional output value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.
 IDA_MEM_FAIL The SUNNONLINSOL module is NULL.

IDAGetNumNonlinSolvConvFails

Call `flag = IDAGetNumNonlinSolvConvFails(ida_mem, &nncfails);`
Description The function `IDAGetNumNonlinSolvConvFails` returns the cumulative number of non-linear convergence failures that have occurred.
Arguments `ida_mem` (void *) pointer to the IDA memory block.
`nncfails` (long int) number of nonlinear convergence failures.
Return value The return value `flag` (of type `int`) is one of
 IDA_SUCCESS The optional output value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.

IDAGetNonlinSolvStats

Call `flag = IDAGetNonlinSolvStats(ida_mem, &nniters, &nncfails);`
Description The function `IDAGetNonlinSolvStats` returns the IDA nonlinear solver statistics as a group.
Arguments `ida_mem` (void *) pointer to the IDA memory block.
`nniters` (long int) cumulative number of nonlinear iterations performed.
`nncfails` (long int) cumulative number of nonlinear convergence failures.
Return value The return value `flag` (of type `int`) is one of
 IDA_SUCCESS The optional output value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.
 IDA_MEM_FAIL The SUNNONLINSOL module is NULL.

IDAGetReturnFlagName


Call `name = IDAGetReturnFlagName(flag);`
Description The function `IDAGetReturnFlagName` returns the name of the IDA constant corresponding to `flag`.
Arguments The only argument, of type `int`, is a return flag from an IDA function.
Return value The return value is a string containing the name of the corresponding constant.

4.5.10.3 Initial condition calculation optional output functions

IDAGetNumBcktrackOps

Call `flag = IDAGetNumBacktrackOps(ida_mem, &nbacktr);`
Description The function `IDAGetNumBacktrackOps` returns the number of backtrack operations done in the linesearch algorithm in `IDACalcIC`.
Arguments `ida_mem` (void *) pointer to the IDA memory block.
`nbacktr` (long int) the cumulative number of backtrack operations.
Return value The return value `flag` (of type `int`) is one of
 IDA_SUCCESS The optional output value has been successfully set.
 IDA_MEM_NULL The `ida_mem` pointer is NULL.


IDAGetConsistentIC

| | |
|--------------|---|
| Call | <code>flag = IDAGetConsistentIC(ida_mem, yy0_mod, yp0_mod);</code> |
| Description | The function <code>IDAGetConsistentIC</code> returns the corrected initial conditions calculated by <code>IDACalcIC</code> . |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>yy0_mod</code> (<code>N_Vector</code>) consistent solution vector. <code>yp0_mod</code> (<code>N_Vector</code>) consistent derivative vector. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output value has been successfully set. <code>IDA_ILL_INPUT</code> The function was not called before the first call to <code>IDASolve</code> . <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |
| Notes | If the consistent solution vector or consistent derivative vector is not desired, pass <code>NULL</code> for the corresponding argument.  The user must allocate space for <code>yy0_mod</code> and <code>yp0_mod</code> (if not <code>NULL</code>). |

4.5.10.4 Rootfinding optional output functions

There are two optional output functions associated with rootfinding.

IDAGetRootInfo

| | |
|--------------|---|
| Call | <code>flag = IDAGetRootInfo(ida_mem, rootsfound);</code> |
| Description | The function <code>IDAGetRootInfo</code> returns an array showing which functions were found to have a root. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>rootsfound</code> (<code>int *</code>) array of length <code>nrtfn</code> with the indices of the user functions g_i found to have a root. For $i = 0, \dots, \text{nrtfn} - 1$, <code>rootsfound[i]</code> $\neq 0$ if g_i has a root, and $= 0$ if not. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output values have been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |
| Notes | Note that, for the components g_i for which a root was found, the sign of <code>rootsfound[i]</code> indicates the direction of zero-crossing. A value of $+1$ indicates that g_i is increasing, while a value of -1 indicates a decreasing g_i .  The user must allocate memory for the vector <code>rootsfound</code> . |

IDAGetNumGEvals

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumGEvals(ida_mem, &ngevals);</code> |
| Description | The function <code>IDAGetNumGEvals</code> returns the cumulative number of calls to the user root function g . |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>ngevals</code> (<code>long int</code>) number of calls to the user's function g so far. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDA_SUCCESS</code> The optional output value has been successfully set. <code>IDA_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . |

4.5.10.5 IDALS linear solver interface optional output functions

The following optional outputs are available from the IDALS modules: workspace requirements, number of calls to the Jacobian routine, number of calls to the residual routine for finite-difference Jacobian or Jacobian-vector product approximation, number of linear iterations, number of linear convergence failures, number of calls to the preconditioner setup and solve routines, number of calls to the Jacobian-vector setup and product routines, and last return value from an IDALS function. Note that, where the name of an output would otherwise conflict with the name of an optional output from the main solver, a suffix LS (for Linear Solver) has been added (e.g. `lenrwLS`).

| |
|--------------------|
| IDAGetLinWorkSpace |
|--------------------|

| | |
|--------------|---|
| Call | <code>flag = IDAGetLinWorkSpace(ida_mem, &lenrwLS, &leniwLS);</code> |
| Description | The function <code>IDAGetLinWorkSpace</code> returns the sizes of the real and integer workspaces used by the IDALS linear solver interface. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>lenrwLS</code> (<code>long int</code>) the number of real values in the IDALS workspace. <code>leniwLS</code> (<code>long int</code>) the number of integer values in the IDALS workspace. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDALS_SUCCESS</code> The optional output value has been successfully set. <code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDALS_LMEM_NULL</code> The IDALS linear solver has not been initialized. |
| Notes | <p>The workspace requirements reported by this routine correspond only to memory allocated within this interface and to memory allocated by the <code>SUNLINSOL</code> object attached to it. The template Jacobian matrix allocated by the user outside of IDALS is not included in this report.</p> <p>The previous routines <code>IDADlsGetWorkspace</code> and <code>IDASpilsGetWorkspace</code> are now wrappers for this routine, and may still be used for backward-compatibility. However, these will be deprecated in future releases, so we recommend that users transition to the new routine name soon.</p> |

| |
|-------------------|
| IDAGetNumJacEvals |
|-------------------|

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumJacEvals(ida_mem, &njevals);</code> |
| Description | The function <code>IDAGetNumJacEvals</code> returns the cumulative number of calls to the IDALS Jacobian approximation function. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>njevals</code> (<code>long int</code>) the cumulative number of calls to the Jacobian function (total so far). |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDALS_SUCCESS</code> The optional output value has been successfully set. <code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDALS_LMEM_NULL</code> The IDALS linear solver has not been initialized. |
| Notes | The previous routine <code>IDADlsGetNumJacEvals</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumLinResEvals

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumLinResEvals(ida_mem, &nrevalsLS);</code> |
| Description | The function <code>IDAGetNumLinResEvals</code> returns the cumulative number of calls to the user residual function due to the finite difference Jacobian approximation or finite difference Jacobian-vector product approximation. |
| Arguments | <code>ida_mem</code> (void *) pointer to the IDA memory block. <code>nrevalsLS</code> (long int) the cumulative number of calls to the user residual function. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of IDALS_SUCCESS The optional output value has been successfully set. IDALS_MEM_NULL The <code>ida_mem</code> pointer is NULL. IDALS_LMEM_NULL The IDALS linear solver has not been initialized. |
| Notes | The value <code>nrevalsLS</code> is incremented only if one of the default internal difference quotient functions is used. The previous routines <code>IDADlsGetNumRhsEvals</code> and <code>IDASpilsGetNumRhsEvals</code> are now wrappers for this routine, and may still be used for backward-compatibility. However, these will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumLinIters

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumLinIters(ida_mem, &nliters);</code> |
| Description | The function <code>IDAGetNumLinIters</code> returns the cumulative number of linear iterations. |
| Arguments | <code>ida_mem</code> (void *) pointer to the IDA memory block. <code>nliters</code> (long int) the current number of linear iterations. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of IDALS_SUCCESS The optional output value has been successfully set. IDALS_MEM_NULL The <code>ida_mem</code> pointer is NULL. IDALS_LMEM_NULL The IDALS linear solver has not been initialized. |
| Notes | The previous routine <code>IDASpilsGetNumLinIters</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumLinConvFails

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumLinConvFails(ida_mem, &nlcfails);</code> |
| Description | The function <code>IDAGetNumLinConvFails</code> returns the cumulative number of linear convergence failures. |
| Arguments | <code>ida_mem</code> (void *) pointer to the IDA memory block. <code>nlcfails</code> (long int) the current number of linear convergence failures. |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of IDALS_SUCCESS The optional output value has been successfully set. IDALS_MEM_NULL The <code>ida_mem</code> pointer is NULL. IDALS_LMEM_NULL The IDALS linear solver has not been initialized. |
| Notes | The previous routine <code>IDASpilsGetNumConvFails</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumPrecEvals

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumPrecEvals(ida_mem, &npevals);</code> |
| Description | The function <code>IDAGetNumPrecEvals</code> returns the cumulative number of preconditioner evaluations, i.e., the number of calls made to <code>psetup</code> . |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>npevals</code> (<code>long int</code>) the cumulative number of calls to <code>psetup</code> . |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDALS_SUCCESS</code> The optional output value has been successfully set. <code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDALS_LMEM_NULL</code> The IDALS linear solver has not been initialized. |
| Notes | The previous routine <code>IDASpilsGetNumPrecEvals</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumPrecSolves

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumPrecSolves(ida_mem, &npsolves);</code> |
| Description | The function <code>IDAGetNumPrecSolves</code> returns the cumulative number of calls made to the preconditioner solve function, <code>psolve</code> . |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>npsolves</code> (<code>long int</code>) the cumulative number of calls to <code>psolve</code> . |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDALS_SUCCESS</code> The optional output value has been successfully set. <code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDALS_LMEM_NULL</code> The IDALS linear solver has not been initialized. |
| Notes | The previous routine <code>IDASpilsGetNumPrecSolves</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumJTSetupEvals

| | |
|--------------|--|
| Call | <code>flag = IDAGetNumJTSetupEvals(ida_mem, &njtsetup);</code> |
| Description | The function <code>IDAGetNumJTSetupEvals</code> returns the cumulative number of calls made to the Jacobian-vector setup function <code>jtsetup</code> . |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>njtsetup</code> (<code>long int</code>) the current number of calls to <code>jtsetup</code> . |
| Return value | The return value <code>flag</code> (of type <code>int</code>) is one of <code>IDALS_SUCCESS</code> The optional output value has been successfully set. <code>IDALS_MEM_NULL</code> The <code>ida_mem</code> pointer is <code>NULL</code> . <code>IDALS_LMEM_NULL</code> The IDALS linear solver has not been initialized. |
| Notes | The previous routine <code>IDASpilsGetNumJTSetupEvals</code> is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

IDAGetNumJtimesEvals

Call `flag = IDAGetNumJtimesEvals(ida_mem, &njvevals);`

Description The function `IDAGetNumJtimesEvals` returns the cumulative number of calls made to the Jacobian-vector function, `jtimes`.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`njvevals` (`long int`) the cumulative number of calls to `jtimes`.

Return value The return value `flag` (of type `int`) is one of

- `IDALS_SUCCESS` The optional output value has been successfully set.
- `IDALS_MEM_NULL` The `ida_mem` pointer is `NULL`.
- `IDALS_LMEM_NULL` The IDALS linear solver has not been initialized.

Notes The previous routine `IDASpilsGetNumJtimesEvals` is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

IDAGetLastLinFlag

Call `flag = IDAGetLastLinFlag(ida_mem, &lsflag);`

Description The function `IDAGetLastLinFlag` returns the last return value from an IDALS routine.

Arguments `ida_mem` (`void *`) pointer to the IDA memory block.
`lsflag` (`long int`) the value of the last return flag from an IDALS function.

Return value The return value `flag` (of type `int`) is one of

- `IDALS_SUCCESS` The optional output value has been successfully set.
- `IDALS_MEM_NULL` The `ida_mem` pointer is `NULL`.
- `IDALS_LMEM_NULL` The IDALS linear solver has not been initialized.

Notes If the IDALS setup function failed (i.e., `IDASolve` returned `IDA_LSETUP_FAIL`) when using the `SUNLINSOL_DENSE` or `SUNLINSOL_BAND` modules, then the value of `lsflag` is equal to the column index (numbered from one) at which a zero diagonal element was encountered during the LU factorization of the (dense or banded) Jacobian matrix.

If the IDALS setup function failed when using another `SUNLINSOL` module, then `lsflag` will be `SUNLS_PSET_FAIL_UNREC`, `SUNLS_ASET_FAIL_UNREC`, or `SUNLS_PACKAGE_FAIL_UNREC`.

If the IDALS solve function failed (`IDASolve` returned `IDA_LSOLVE_FAIL`), `lsflag` contains the error return flag from the `SUNLINSOL` object, which will be one of: `SUNLS_MEM_NULL`, indicating that the `SUNLINSOL` memory is `NULL`; `SUNLS_ATIMES_FAIL_UNREC`, indicating an unrecoverable failure in the $J*v$ function; `SUNLS_PSOLVE_FAIL_UNREC`, indicating that the preconditioner solve function `psolve` failed unrecoverably; `SUNLS_GS_FAIL`, indicating a failure in the Gram-Schmidt procedure (generated only in `SPGMR` or `SPFGMR`); `SUNLS_QRSOL_FAIL`, indicating that the matrix R was found to be singular during the QR solve phase (`SPGMR` and `SPFGMR` only); or `SUNLS_PACKAGE_FAIL_UNREC`, indicating an unrecoverable failure in an external iterative linear solver package.

The previous routines `IDADlsGetLastFlag` and `IDASpilsGetLastFlag` are now wrappers for this routine, and may still be used for backward-compatibility. However, these will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

IDAGetLinReturnFlagName

Call `name = IDAGetLinReturnFlagName(lsflag);`

Description The function `IDAGetLinReturnFlagName` returns the name of the IDALS constant corresponding to `lsflag`.

| | |
|--------------|--|
| Arguments | The only argument, of type <code>long int</code> , is a return flag from an IDALS function. |
| Return value | The return value is a string containing the name of the corresponding constant. If $1 \leq \text{lsflag} \leq N$ (LU factorization failed), this function returns “NONE”. |
| Notes | The previous routines <code>IDADlsGetReturnFlagName</code> and <code>IDASpilsGetReturnFlagName</code> are now wrappers for this routine, and may still be used for backward-compatibility. However, these will be deprecated in future releases, so we recommend that users transition to the new routine name soon. |

4.5.11 IDA reinitialization function

The function `IDAreInit` reinitializes the main IDA solver for the solution of a new problem, where a prior call to `IDAInit` has been made. The new problem must have the same size as the previous one. `IDAreInit` performs the same input checking and initializations that `IDAInit` does, but does no memory allocation, as it assumes that the existing internal memory is sufficient for the new problem. A call to `IDAreInit` deletes the solution history that was stored internally during the previous integration. Following a successful call to `IDAreInit`, call `IDASolve` again for the solution of the new problem.

The use of `IDAreInit` requires that the maximum method order, `maxord`, is no larger for the new problem than for the problem specified in the last call to `IDAInit`. In addition, the same `NVECTOR` module set for the previous problem will be reused for the new problem.

If there are changes to the linear solver specifications, make the appropriate calls to either the linear solver objects themselves, or to the IDALS interface routines, as described in §4.5.3.

If there are changes to any optional inputs, make the appropriate `IDASet***` calls, as described in §4.5.8. Otherwise, all solver inputs set previously remain in effect.

One important use of the `IDAreInit` function is in the treating of jump discontinuities in the residual function. Except in cases of fairly small jumps, it is usually more efficient to stop at each point of discontinuity and restart the integrator with a readjusted DAE model, using a call to `IDAreInit`. To stop when the location of the discontinuity is known, simply make that location a value of `tout`. To stop when the location of the discontinuity is determined by the solution, use the rootfinding feature. In either case, it is critical that the residual function *not* incorporate the discontinuity, but rather have a smooth extension over the discontinuity, so that the step across it (and subsequent rootfinding, if used) can be done efficiently. Then use a switch within the residual function (communicated through `user.data`) that can be flipped between the stopping of the integration and the restart, so that the restarted problem uses the new values (which have jumped). Similar comments apply if there is to be a jump in the dependent variable vector.

`IDAreInit`

| | |
|--------------|--|
| Call | <code>flag = IDAreInit(ida_mem, t0, y0, yp0);</code> |
| Description | The function <code>IDAreInit</code> provides required problem specifications and reinitializes IDA. |
| Arguments | <code>ida_mem</code> (<code>void *</code>) pointer to the IDA memory block. <code>t0</code> (<code>realtype</code>) is the initial value of t . <code>y0</code> (<code>N.Vector</code>) is the initial value of y . <code>yp0</code> (<code>N.Vector</code>) is the initial value of \dot{y} . |
| Return value | The return value <code>flag</code> (of type <code>int</code>) will be one of the following: <ul style="list-style-type: none"> <code>IDA_SUCCESS</code> The call to <code>IDAreInit</code> was successful. <code>IDA_MEM_NULL</code> The IDA memory block was not initialized through a previous call to <code>IDACreate</code>. <code>IDA_NO_MALLOC</code> Memory space for the IDA memory block was not allocated through a previous call to <code>IDAInit</code>. <code>IDA_ILL_INPUT</code> An input argument to <code>IDAreInit</code> has an illegal value. |

IDAErrHandlerFn

[illegible]

| | |
|---------|--|
| Purpose | This function processes error and warning messages from IDA and its sub-modules. |
|---------|--|

Arguments **error_code** is the error code.

module is the name of the IDA module reporting the error.

function is the name of the function in which the error occurred.

`msg` is the error message.

eh_data is a pointer to user data, the same as the **eh_data** parameter passed to **IDASetErrHandlerFn**.

Return value A IDAErrorHandlerFn function has no return value.

Notes **error_code** is negative for errors and positive (**IDA_WARNING**) for warnings. If a function that returns a pointer to memory encounters an error, it sets **error_code** to 0.

4.6.3 Error weight function

As an alternative to providing the relative and absolute tolerances, the user may provide a function of type `IDAewtFn` to compute a vector `ewt` containing the multiplicative weights W_i used in the WRMS norm $\|v\|_{\text{WRMS}} = \sqrt{(1/N) \sum_1^N (W_i \cdot v_i)^2}$. These weights will be used in place of those defined by Eq. (2.6). The function type `IDAewtFn` is defined as follows:

IDAEwtFn

```
Definition      typedef int (*IDAewtFn)(N_Vector y, N_Vector ewt, void *user_data);
```

| | |
|---------|--|
| Purpose | This function computes the WRMS error weights for the vector y . |
|---------|--|

Arguments y is the value of the dependent variable vector at which the weight vector is to be computed.

ewt is the output vector containing the error weights.

`user_data` is a pointer to user data, the same as the `user_data` parameter passed to `IDASetUserData`.

Return value An `IDAError` function type must return 0 if it successfully set the error weights and `-1` otherwise.

| | |
|-------|--|
| Notes | Allocation of memory for <code>ewt</code> is handled within IDA. |
|-------|--|

The error weight vector must have all components positive. It is the user's responsibility to perform this test and return -1 if it is not satisfied.



4.6.4 Rootfinding function

If a rootfinding problem is to be solved during the integration of the DAE system, the user must supply a C function of type `IDARootFn`, defined as follows:

IDARootFn

[illegible]

| | |
|---------|--|
| Purpose | This function computes a vector-valued function $g(t, y, \dot{y})$ such that the roots of the <code>nrtfn</code> components $g_i(t, y, \dot{y})$ are to be found during the integration. |
|---------|--|

Arguments t is the current value of the independent variable.

y is the current value of the dependent variable vector, $y(t)$.

| | |
|------------------------|---|
| <code>yp</code> | is the current value of $\dot{y}(t)$, the t -derivative of y . |
| <code>gout</code> | is the output array, of length <code>nrtfn</code> , with components $g_i(t, y, \dot{y})$. |
| <code>user_data</code> | is a pointer to user data, the same as the <code>user_data</code> parameter passed to <code>IDASetUserData</code> . |
| Return value | An <code>IDARootFn</code> should return 0 if successful or a non-zero value if an error occurred (in which case the integration is halted and <code>IDASolve</code> returns <code>IDA_RTFUNC_FAIL</code>). |
| Notes | Allocation of memory for <code>gout</code> is handled within IDA. |

4.6.5 Jacobian construction (matrix-based linear solvers)

If a matrix-based linear solver module is used (i.e. a non-NULL `SUNMATRIX` object was supplied to `IDASetLinearSolver`), the user may provide a function of type `IDALsJacFn` defined as follows:

`IDALsJacFn`

| | | |
|--------------|--|--|
| Definition | <pre>typedef int (*IDALsJacFn)(realtype tt, realtype cj, N_Vector yy, N_Vector yp, N_Vector rr, SUNMatrix Jac, void *user_data, N_Vector tmp1, N_Vector tmp2, N_Vector tmp3);</pre> | |
| Purpose | This function computes the Jacobian matrix J of the DAE system (or an approximation to it), defined by Eq. (2.5). | |
| Arguments | <code>tt</code> | is the current value of the independent variable t . |
| | <code>cj</code> | is the scalar in the system Jacobian, proportional to the inverse of the step size (α in Eq. (2.5)). |
| | <code>yy</code> | is the current value of the dependent variable vector, $y(t)$. |
| | <code>yp</code> | is the current value of $\dot{y}(t)$. |
| | <code>rr</code> | is the current value of the residual vector $F(t, y, \dot{y})$. |
| | <code>Jac</code> | is the output (approximate) Jacobian matrix (of type <code>SUNMatrix</code>), $J = \partial F / \partial y + cj \partial F / \partial \dot{y}$. |
| | <code>user_data</code> | is a pointer to user data, the same as the <code>user_data</code> parameter passed to <code>IDASetUserData</code> . |
| | <code>tmp1</code> | |
| | <code>tmp2</code> | |
| | <code>tmp3</code> | are pointers to memory allocated for variables of type <code>N_Vector</code> which can be used by <code>IDALsJacFn</code> function as temporary storage or work space. |
| Return value | An <code>IDALsJacFn</code> should return 0 if successful, a positive value if a recoverable error occurred, or a negative value if a nonrecoverable error occurred. | |
| | In the case of a recoverable error return, the integrator will attempt to recover by reducing the stepsize, and hence changing α in (2.5). | |
| Notes | <p>Information regarding the structure of the specific <code>SUNMATRIX</code> structure (e.g. number of rows, upper/lower bandwidth, sparsity type) may be obtained through using the implementation-specific <code>SUNMATRIX</code> interface functions (see Chapter 7 for details).</p> <p>Prior to calling the user-supplied Jacobian function, the Jacobian matrix $J(t, y)$ is zeroed out, so only nonzero elements need to be loaded into <code>Jac</code>.</p> <p>If the user's <code>IDALsJacFn</code> function uses difference quotient approximations, it may need to access quantities not in the call list. These quantities may include the current stepsize, the error weights, etc. To obtain these, the user will need to add a pointer to <code>ida_mem</code> to <code>user_data</code> and then use the <code>IDAGet*</code> functions described in §4.5.10.2. The unit roundoff can be accessed as <code>UNIT_ROUNDOFF</code> defined in <code>sundials.types.h</code>.</p> | |

dense:

A user-supplied dense Jacobian function must load the $\text{Neq} \times \text{Neq}$ dense matrix `Jac` with an approximation to the Jacobian matrix $J(t, y, \dot{y})$ at the point `(tt, yy, yp)`. The accessor macros `SM_ELEMENT_D` and `SM_COLUMN_D` allow the user to read and write dense matrix elements without making explicit references to the underlying representation of the `SUNMATRIX_DENSE` type. `SM_ELEMENT_D(J, i, j)` references the (i, j) -th element of the dense matrix `Jac` (with $i, j = 0 \dots N - 1$). This macro is meant for small problems for which efficiency of access is not a major concern. Thus, in terms of the indices m and n ranging from 1 to N , the Jacobian element $J_{m,n}$ can be set using the statement `SM_ELEMENT_D(J, m-1, n-1) = Jm,n`. Alternatively, `SM_COLUMN_D(J, j)` returns a pointer to the first element of the j -th column of `Jac` (with $j = 0 \dots N - 1$), and the elements of the j -th column can then be accessed using ordinary array indexing. Consequently, $J_{m,n}$ can be loaded using the statements `col_n = SM_COLUMN_D(J, n-1); col_n[m-1] = Jm,n`. For large problems, it is more efficient to use `SM_COLUMN_D` than to use `SM_ELEMENT_D`. Note that both of these macros number rows and columns starting from 0. The `SUNMATRIX_DENSE` type and accessor macros are documented in §7.2.

banded:

A user-supplied banded Jacobian function must load the $\text{Neq} \times \text{Neq}$ banded matrix `Jac` with an approximation to the Jacobian matrix $J(t, y, \dot{y})$ at the point `(tt, yy, yp)`. The accessor macros `SM_ELEMENT_B`, `SM_COLUMN_B`, and `SM_COLUMN_ELEMENT_B` allow the user to read and write banded matrix elements without making specific references to the underlying representation of the `SUNMATRIX_BAND` type. `SM_ELEMENT_B(J, i, j)` references the (i, j) -th element of the banded matrix `Jac`, counting from 0. This macro is meant for use in small problems for which efficiency of access is not a major concern. Thus, in terms of the indices m and n ranging from 1 to N with (m, n) within the band defined by `mupper` and `mlower`, the Jacobian element $J_{m,n}$ can be loaded using the statement `SM_ELEMENT_B(J, m-1, n-1) = Jm,n`. The elements within the band are those with $-\text{mupper} \leq m-n \leq \text{mlower}$. Alternatively, `SM_COLUMN_B(J, j)` returns a pointer to the diagonal element of the j -th column of `Jac`, and if we assign this address to `realtype *col_j`, then the i -th element of the j -th column is given by `SM_COLUMN_ELEMENT_B(col_j, i, j)`, counting from 0. Thus, for (m, n) within the band, $J_{m,n}$ can be loaded by setting `col_n = SM_COLUMN_B(J, n-1)`; and `SM_COLUMN_ELEMENT_B(col_n, m-1, n-1) = Jm,n`. The elements of the j -th column can also be accessed via ordinary array indexing, but this approach requires knowledge of the underlying storage for a band matrix of type `SUNMATRIX_BAND`. The array `col_n` can be indexed from $-\text{mupper}$ to `mlower`. For large problems, it is more efficient to use `SM_COLUMN_B` and `SM_COLUMN_ELEMENT_B` than to use the `SM_ELEMENT_B` macro. As in the dense case, these macros all number rows and columns starting from 0. The `SUNMATRIX_BAND` type and accessor macros are documented in §7.3.

sparse:

A user-supplied sparse Jacobian function must load the $\text{Neq} \times \text{Neq}$ compressed-sparse-column or compressed-sparse-row matrix `Jac` with an approximation to the Jacobian matrix $J(t, y, \dot{y})$ at the point `(tt, yy, yp)`. Storage for `Jac` already exists on entry to this function, although the user should ensure that sufficient space is allocated in `Jac` to hold the nonzero values to be set; if the existing space is insufficient the user may reallocate the data and index arrays as needed. The amount of allocated space in a `SUNMATRIX_SPARSE` object may be accessed using the macro `SM_NNZ_S` or the routine `SUNSparseMatrix.NNZ`. The `SUNMATRIX_SPARSE` type and accessor macros are documented in §7.4.

The previous function type `IDADlsJacFn` is identical to `IDALsJacFn`, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new function type name soon.

4.6.6 Jacobian-vector product (matrix-free linear solvers)

If a matrix-free linear solver is to be used (i.e., a NULL-valued `SUNMATRIX` was supplied to `IDASetLinearSolver`), the user may provide a function of type `IDALsJacTimesVecFn` in the following form, to compute matrix-vector products Jv . If such a function is not supplied, the default is a difference quotient approximation to these products.

`IDALsJacTimesVecFn`

| | | |
|--------------|--|---|
| Definition | <pre>typedef int (*IDALsJacTimesVecFn)(realtype tt, N_Vector yy, N_Vector yp, N_Vector rr, N_Vector v, N_Vector Jv, realtype cj, void *user_data, N_Vector tmp1, N_Vector tmp2);</pre> | |
| Purpose | This function computes the product Jv of the DAE system Jacobian J (or an approximation to it) and a given vector v , where J is defined by Eq. (2.5). | |
| Arguments | <code>tt</code> | is the current value of the independent variable. |
| | <code>yy</code> | is the current value of the dependent variable vector, $y(t)$. |
| | <code>yp</code> | is the current value of $\dot{y}(t)$. |
| | <code>rr</code> | is the current value of the residual vector $F(t, y, \dot{y})$. |
| | <code>v</code> | is the vector by which the Jacobian must be multiplied to the right. |
| | <code>Jv</code> | is the computed output vector. |
| | <code>cj</code> | is the scalar in the system Jacobian, proportional to the inverse of the step size (α in Eq. (2.5)). |
| | <code>user_data</code> | is a pointer to user data, the same as the <code>user_data</code> parameter passed to <code>IDASetUserData</code> . |
| | <code>tmp1</code> | |
| | <code>tmp2</code> | are pointers to memory allocated for variables of type <code>N_Vector</code> which can be used by <code>IDALsJacTimesVecFn</code> as temporary storage or work space. |
| Return value | The value returned by the Jacobian-times-vector function should be 0 if successful. A nonzero value indicates that a nonrecoverable error occurred. | |
| Notes | This function must return a value of $J * v$ that uses the <i>current</i> value of J , i.e. as evaluated at the current (t, y, \dot{y}) . | |
| | If the user's <code>IDALsJacTimesVecFn</code> function uses difference quotient approximations, it may need to access quantities not in the call list. These include the current stepsize, the error weights, etc. To obtain these, the user will need to add a pointer to <code>ida_mem</code> to <code>user_data</code> and then use the <code>IDAGet*</code> functions described in §4.5.10.2. The unit roundoff can be accessed as <code>UNIT_ROUNDOFF</code> defined in <code>sundials.types.h</code> . | |
| | The previous function type <code>IDASpilsJacTimesVecFn</code> is identical to <code>IDALsJacTimesVecFn</code> , and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new function type name soon. | |

4.6.7 Jacobian-vector product setup (matrix-free linear solvers)

If the user's Jacobian-times-vector requires that any Jacobian-related data be preprocessed or evaluated, then this needs to be done in a user-supplied function of type `IDALsJacTimesSetupFn`, defined as follows:

IDALsJacTimesSetupFn

| | | | |
|--------------|--|---|--|
| Definition | <pre>typedef int (*IDALsJacTimesSetupFn)(realtype tt, N_Vector yy, N_Vector yp, N_Vector rr, realtype cj, void *user_data);</pre> | | |
| Purpose | This function preprocesses and/or evaluates Jacobian data needed by the Jacobian-times-vector routine. | | |
| Arguments | tt | is the current value of the independent variable. | |
| | yy | is the current value of the dependent variable vector, $y(t)$. | |
| | yp | is the current value of $\dot{y}(t)$. | |
| | rr | is the current value of the residual vector $F(t, y, \dot{y})$. | |
| | cj | is the scalar in the system Jacobian, proportional to the inverse of the step size (α in Eq. (2.5)). | |
| | user_data | is a pointer to user data, the same as the user_data parameter passed to IDASetUserData . | |
| Return value | The value returned by the Jacobian-vector setup function should be 0 if successful, positive for a recoverable error (in which case the step will be retried), or negative for an unrecoverable error (in which case the integration is halted). | | |
| Notes | <p>Each call to the Jacobian-vector setup function is preceded by a call to the IDAResFn user function with the same (t, y, yp) arguments. Thus, the setup function can use any auxiliary data that is computed and saved during the evaluation of the DAE residual.</p> <p>If the user's IDALsJacTimesVecFn function uses difference quotient approximations, it may need to access quantities not in the call list. These include the current stepsize, the error weights, etc. To obtain these, the user will need to add a pointer to ida_mem to user_data and then use the IDAGet* functions described in §4.5.10.2. The unit roundoff can be accessed as UNIT_ROUNDOFF defined in sundials.types.h.</p> <p>The previous function type IDASpilsJacTimesSetupFn is identical to IDALsJacTimesSetupFn, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new function type name soon.</p> | | |

4.6.8 Preconditioner solve (iterative linear solvers)

If a user-supplied preconditioner is to be used with a SUNLINSOL solver module, then the user must provide a function to solve the linear system $Pz = r$ where P is a left preconditioner matrix which approximates (at least crudely) the Jacobian matrix $J = \partial F / \partial y + cj \partial F / \partial \dot{y}$. This function must be of type **IDALsPrecSolveFn**, defined as follows:

IDALsPrecSolveFn

| | | | |
|------------|---|--|--|
| Definition | <pre>typedef int (*IDALsPrecSolveFn)(realtype tt, N_Vector yy, N_Vector yp, N_Vector rr, N_Vector rvec, N_Vector zvec, realtype cj, realtype delta, void *user_data);</pre> | | |
| Purpose | This function solves the preconditioning system $Pz = r$. | | |
| Arguments | tt | is the current value of the independent variable. | |
| | yy | is the current value of the dependent variable vector, $y(t)$. | |
| | yp | is the current value of $\dot{y}(t)$. | |
| | rr | is the current value of the residual vector $F(t, y, \dot{y})$. | |
| | rvec | is the right-hand side vector r of the linear system to be solved. | |

| | |
|------------------|---|
| zvec | is the computed output vector. |
| cj | is the scalar in the system Jacobian, proportional to the inverse of the step size (α in Eq. (2.5)). |
| delta | is an input tolerance to be used if an iterative method is employed in the solution. In that case, the residual vector $Res = r - Pz$ of the system should be made less than delta in weighted l_2 norm, i.e., $\sqrt{\sum_i (Res_i \cdot ewt_i)^2} < \mathbf{delta}$. To obtain the <code>N_Vector</code> ewt , call <code>IDAGetErrWeights</code> (see §4.5.10.2). |
| user_data | is a pointer to user data, the same as the user_data parameter passed to the function <code>IDASetUserData</code> . |
| Return value | The value to be returned by the preconditioner solve function is a flag indicating whether it was successful. This value should be 0 if successful, positive for a recoverable error (in which case the step will be retried), negative for an unrecoverable error (in which case the integration is halted). |
| Notes | The previous function type <code>IDASpilsPrecSolveFn</code> is identical to <code>IDALsPrecSolveFn</code> , and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new function type name soon. |

4.6.9 Preconditioner setup (iterative linear solvers)

If the user's preconditioner requires that any Jacobian-related data be evaluated or preprocessed, then this needs to be done in a user-supplied function of type `IDALsPrecSetupFn`, defined as follows:

IDALsPrecSetupFn

| | | |
|--------------|--|--|
| Definition | <pre>typedef int (*IDALsPrecSetupFn)(realtype tt, N_Vector yy, N_Vector yp, N_Vector rr, realtype cj, void *user_data);</pre> | |
| Purpose | This function evaluates and/or preprocesses Jacobian-related data needed by the preconditioner. | |
| Arguments | tt | is the current value of the independent variable. |
| | yy | is the current value of the dependent variable vector, $y(t)$. |
| | yp | is the current value of $\dot{y}(t)$. |
| | rr | is the current value of the residual vector $F(t, y, \dot{y})$. |
| | cj | is the scalar in the system Jacobian, proportional to the inverse of the step size (α in Eq. (2.5)). |
| | user_data | is a pointer to user data, the same as the user_data parameter passed to the function <code>IDASetUserData</code> . |
| Return value | The value returned by the preconditioner setup function is a flag indicating whether it was successful. This value should be 0 if successful, positive for a recoverable error (in which case the step will be retried), negative for an unrecoverable error (in which case the integration is halted). | |
| Notes | <p>The operations performed by this function might include forming a crude approximate Jacobian, and performing an LU factorization on the resulting approximation.</p> <p>Each call to the preconditioner setup function is preceded by a call to the <code>IDAResFn</code> user function with the same (tt, yy, yp) arguments. Thus the preconditioner setup function can use any auxiliary data that is computed and saved during the evaluation of the DAE residual.</p> <p>This function is not called in advance of every call to the preconditioner solve function, but rather is called only as often as needed to achieve convergence in the nonlinear solver.</p> | |

If the user's `IDALsPrecSetupFn` function uses difference quotient approximations, it may need to access quantities not in the call list. These include the current stepsize, the error weights, etc. To obtain these, the user will need to add a pointer to `ida_mem` to `user_data` and then use the `IDAGet*` functions described in §4.5.10.2. The unit roundoff can be accessed as `UNIT_ROUNDOFF` defined in `sundials_types.h`.

The previous function type `IDASpilsPrecSetupFn` is identical to `IDALsPrecSetupFn`, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new function type name soon.

4.7 A parallel band-block-diagonal preconditioner module

A principal reason for using a parallel DAE solver such as IDA lies in the solution of partial differential equations (PDEs). Moreover, the use of a Krylov iterative method for the solution of many such problems is motivated by the nature of the underlying linear system of equations (2.4) that must be solved at each time step. The linear algebraic system is large, sparse, and structured. However, if a Krylov iterative method is to be effective in this setting, then a nontrivial preconditioner needs to be used. Otherwise, the rate of convergence of the Krylov iterative method is usually unacceptably slow. Unfortunately, an effective preconditioner tends to be problem-specific.

However, we have developed one type of preconditioner that treats a rather broad class of PDE-based problems. It has been successfully used for several realistic, large-scale problems [27] and is included in a software module within the IDA package. This module works with the parallel vector module `NVECTOR_PARALLEL` and generates a preconditioner that is a block-diagonal matrix with each block being a band matrix. The blocks need not have the same number of super- and sub-diagonals, and these numbers may vary from block to block. This Band-Block-Diagonal Preconditioner module is called `IDABBDPRE`.

One way to envision these preconditioners is to think of the domain of the computational PDE problem as being subdivided into M non-overlapping sub-domains. Each of these sub-domains is then assigned to one of the M processors to be used to solve the DAE system. The basic idea is to isolate the preconditioning so that it is local to each processor, and also to use a (possibly cheaper) approximate residual function. This requires the definition of a new function $G(t, y, \dot{y})$ which approximates the function $F(t, y, \dot{y})$ in the definition of the DAE system (2.1). However, the user may set $G = F$. Corresponding to the domain decomposition, there is a decomposition of the solution vectors y and \dot{y} into M disjoint blocks y_m and \dot{y}_m , and a decomposition of G into blocks G_m . The block G_m depends on y_m and \dot{y}_m , and also on components of $y_{m'}$ and $\dot{y}_{m'}$ associated with neighboring sub-domains (so-called ghost-cell data). Let \bar{y}_m and $\bar{\dot{y}}_m$ denote y_m and \dot{y}_m (respectively) augmented with those other components on which G_m depends. Then we have

$$G(t, y, \dot{y}) = [G_1(t, \bar{y}_1, \bar{\dot{y}}_1), G_2(t, \bar{y}_2, \bar{\dot{y}}_2), \dots, G_M(t, \bar{y}_M, \bar{\dot{y}}_M)]^T, \quad (4.1)$$

and each of the blocks $G_m(t, \bar{y}_m, \bar{\dot{y}}_m)$ is uncoupled from the others.

The preconditioner associated with this decomposition has the form

$$P = \text{diag}[P_1, P_2, \dots, P_M] \quad (4.2)$$

where

$$P_m \approx \partial G_m / \partial y_m + \alpha \partial G_m / \partial \dot{y}_m \quad (4.3)$$

This matrix is taken to be banded, with upper and lower half-bandwidths `mudq` and `mlldq` defined as the number of non-zero diagonals above and below the main diagonal, respectively. The difference quotient approximation is computed using `mudq` + `mlldq` + 2 evaluations of G_m , but only a matrix of bandwidth `mukeep` + `mlkeep` + 1 is retained.

Neither pair of parameters need be the true half-bandwidths of the Jacobians of the local block of G , if smaller values provide a more efficient preconditioner. Such an efficiency gain may occur if the couplings in the DAE system outside a certain bandwidth are considerably weaker than those within

the band. Reducing `mukeep` and `mlkeep` while keeping `mudq` and `mldq` at their true values, discards the elements outside the narrower band. Reducing both pairs has the additional effect of lumping the outer Jacobian elements into the computed elements within the band, and requires more caution and experimentation.

The solution of the complete linear system

$$Px = b \quad (4.4)$$

reduces to solving each of the equations

$$P_m x_m = b_m \quad (4.5)$$

and this is done by banded LU factorization of P_m followed by a banded backsolve.

Similar block-diagonal preconditioners could be considered with different treatment of the blocks P_m . For example, incomplete LU factorization or an iterative method could be used instead of banded LU factorization.

The `IDABBDPRE` module calls two user-provided functions to construct P : a required function `Gres` (of type `IDABBDLocalFn`) which approximates the residual function $G(t, y, \dot{y}) \approx F(t, y, \dot{y})$ and which is computed locally, and an optional function `Gcomm` (of type `IDABBDCommFn`) which performs all inter-process communication necessary to evaluate the approximate residual G . These are in addition to the user-supplied residual function `res`. Both functions take as input the same pointer `user_data` as passed by the user to `IDASetUserData` and passed to the user's function `res`. The user is responsible for providing space (presumably within `user_data`) for components of `yy` and `yp` that are communicated by `Gcomm` from the other processors, and that are then used by `Gres`, which should not do any communication.

`IDABBDLocalFn`

| | |
|--------------|--|
| Definition | <pre>typedef int (*IDABBDLocalFn)(sunindextype Nlocal, realtype tt, N_Vector yy, N_Vector yp, N_Vector gval, void *user_data);</pre> |
| Purpose | This <code>Gres</code> function computes $G(t, y, \dot{y})$. It loads the vector <code>gval</code> as a function of <code>tt</code> , <code>yy</code> , and <code>yp</code> . |
| Arguments | <code>Nlocal</code> is the local vector length. |
| | <code>tt</code> is the value of the independent variable. |
| | <code>yy</code> is the dependent variable. |
| | <code>yp</code> is the derivative of the dependent variable. |
| | <code>gval</code> is the output vector. |
| | <code>user_data</code> is a pointer to user data, the same as the <code>user_data</code> parameter passed to <code>IDASetUserData</code> . |
| Return value | An <code>IDABBDLocalFn</code> function type should return 0 to indicate success, 1 for a recoverable error, or -1 for a non-recoverable error. |
| Notes | <p>This function must assume that all inter-processor communication of data needed to calculate <code>gval</code> has already been done, and this data is accessible within <code>user_data</code>.</p> <p>The case where G is mathematically identical to F is allowed.</p> |

`IDABBDCommFn`

| | | | |
|------------|---|---|--|
| Definition | <pre>typedef int (*IDABBDCommFn)(sunindextype Nlocal, realtype tt, N_Vector yy, N_Vector yp, void *user_data);</pre> | | |
| Purpose | This <code>Gcomm</code> function performs all inter-processor communications necessary for the execution of the <code>Gres</code> function above, using the input vectors <code>yy</code> and <code>yp</code> . | | |
| Arguments | <code>Nlocal</code> | is the local vector length. | |
| | <code>tt</code> | is the value of the independent variable. | |

| | | |
|--------------|--|---|
| | <code>yy</code> | is the dependent variable. |
| | <code>yp</code> | is the derivative of the dependent variable. |
| | <code>user_data</code> | is a pointer to user data, the same as the <code>user_data</code> parameter passed to <code>IDASetUserData</code> . |
| Return value | An <code>IDABBDCommFn</code> function type should return 0 to indicate success, 1 for a recoverable error, or -1 for a non-recoverable error. | |
| Notes | <p>The <code>Gcomm</code> function is expected to save communicated data in space defined within the structure <code>user_data</code>.</p> <p>Each call to the <code>Gcomm</code> function is preceded by a call to the residual function <code>res</code> with the same (<code>tt</code>, <code>yy</code>, <code>yp</code>) arguments. Thus <code>Gcomm</code> can omit any communications done by <code>res</code> if relevant to the evaluation of <code>Gres</code>. If all necessary communication was done in <code>res</code>, then <code>Gcomm = NULL</code> can be passed in the call to <code>IDABBDPrecInit</code> (see below).</p> | |

Besides the header files required for the integration of the DAE problem (see §4.3), to use the `IDABBDPRE` module, the main program must include the header file `ida_bbdpre.h` which declares the needed function prototypes.

The following is a summary of the usage of this module and describes the sequence of calls in the user main program. Steps that are unchanged from the user main program presented in §4.4 are grayed-out.

1. **Initialize MPI**
2. **Set problem dimensions etc.**
3. **Set vectors of initial values**
4. **Create IDA object**
5. **Initialize IDA solver**
6. **Specify integration tolerances**
7. **Create linear solver object**

When creating the iterative linear solver object, specify the use of left preconditioning (`PREC_LEFT`) as IDA only supports left preconditioning.
8. **Set linear solver optional inputs**
9. **Attach linear solver module**
10. **Set optional inputs**

Note that the user should not overwrite the preconditioner setup function or solve function through calls to `idIDASetPreconditioner` optional input function.
11. **Initialize the IDABBDPRE preconditioner module**

Specify the upper and lower bandwidths `mudq`, `mldq` and `mukeep`, `mlkeep` and call

```
flag = IDABBDPrecInit(ida_mem, Nlocal, mudq, mldq,
                    mukeep, mlkeep, dq_rel_yy, Gres, Gcomm);
```

to allocate memory and initialize the internal preconditioner data. The last two arguments of `IDABBDPrecInit` are the two user-supplied functions described above.
12. **Create nonlinear solver object**
13. **Attach nonlinear solver module**

IDALS_ILL_INPUT The supplied vector implementation was not compatible with the block band preconditioner.

Notes If one of the half-bandwidths **mudq** or **mldq** to be used in the difference-quotient calculation of the approximate Jacobian is negative or exceeds the value **Nlocal**−1, it is replaced by 0 or **Nlocal**−1 accordingly.

The half-bandwidths **mudq** and **mldq** need not be the true half-bandwidths of the Jacobian of the local block of G , when smaller values may provide a greater efficiency.

Also, the half-bandwidths **mukeep** and **mlkeep** of the retained banded approximate Jacobian block may be even smaller, to reduce storage and computation costs further.

For all four half-bandwidths, the values need not be the same on every processor.

The **IDABBDPRE** module also provides a reinitialization function to allow for a sequence of problems of the same size, with the same linear solver choice, provided there is no change in **local_N**, **mukeep**, or **mlkeep**. After solving one problem, and after calling **IDAReInit** to re-initialize IDA for a subsequent problem, a call to **IDABBDPrecReInit** can be made to change any of the following: the half-bandwidths **mudq** and **mldq** used in the difference-quotient Jacobian approximations, the relative increment **dq_rel_yy**, or one of the user-supplied functions **Gres** and **Gcomm**. If there is a change in any of the linear solver inputs, an additional call to the “Set” routines provided by the **SUNLINSOL** module, and/or one or more of the corresponding **IDASet***** functions, must also be made (in the proper order).

IDABBDPrecReInit

Call `flag = IDABBDPrecReInit(ida_mem, mudq, mldq, dq_rel_yy);`

Description The function **IDABBDPrecReInit** reinitializes the **IDABBDPRE** preconditioner.

Arguments

- ida_mem** (void *) pointer to the IDA memory block.
- mudq** (sunindextype) upper half-bandwidth to be used in the difference-quotient Jacobian approximation.
- mldq** (sunindextype) lower half-bandwidth to be used in the difference-quotient Jacobian approximation.
- dq_rel_yy** (realtype) the relative increment in components of **y** used in the difference quotient approximations. The default is $\text{dq_rel_yy} = \sqrt{\text{unit roundoff}}$, which can be specified by passing **dq_rel_yy** = 0.0.

Return value The return value **flag** (of type **int**) is one of

IDALS_SUCCESS The call to **IDABBDPrecReInit** was successful.

IDALS_MEM_NULL The **ida_mem** pointer was **NULL**.

IDALS_LMEM_NULL An **IDALS** linear solver memory was not attached.

IDALS_PMEM_NULL The function **IDABBDPrecInit** was not previously called.

Notes If one of the half-bandwidths **mudq** or **mldq** is negative or exceeds the value **Nlocal**−1, it is replaced by 0 or **Nlocal**−1, accordingly.

The following two optional output functions are available for use with the **IDABBDPRE** module:

IDABBDPrecGetWorkSpace

Call `flag = IDABBDPrecGetWorkSpace(ida_mem, &lenrwBBDP, &leniwBBDP);`

Description The function **IDABBDPrecGetWorkSpace** returns the local sizes of the **IDABBDPRE** real and integer workspaces.

Arguments

- ida_mem** (void *) pointer to the IDA memory block.
- lenrwBBDP** (long int) local number of real values in the **IDABBDPRE** workspace.
- leniwBBDP** (long int) local number of integer values in the **IDABBDPRE** workspace.

Return value The return value `flag` (of type `int`) is one of

- `IDALS_SUCCESS` The optional output value has been successfully set.
- `IDALS_MEM_NULL` The `ida_mem` pointer was `NULL`.
- `IDALS_PMEM_NULL` The IDABBDPRE preconditioner has not been initialized.

Notes The workspace requirements reported by this routine correspond only to memory allocated within the IDABBDPRE module (the banded matrix approximation, banded SUNLINSOL object, temporary vectors). These values are local to each process.

The workspaces referred to here exist in addition to those given by the corresponding function `IDAGetLinWorkSpace`.

| |
|---------------------------------|
| IDABBDPrecGetNumGfnEvals |
|---------------------------------|

Call `flag = IDABBDPrecGetNumGfnEvals(ida_mem, &ngevalsBBDP);`

Description The function `IDABBDPrecGetNumGfnEvals` returns the cumulative number of calls to the user `Gres` function due to the finite difference approximation of the Jacobian blocks used within IDABBDPRE's preconditioner setup function.

Arguments `ida_mem` (void *) pointer to the IDA memory block.
`ngevalsBBDP` (long int) the cumulative number of calls to the user `Gres` function.

Return value The return value `flag` (of type `int`) is one of

- `IDALS_SUCCESS` The optional output value has been successfully set.
- `IDALS_MEM_NULL` The `ida_mem` pointer was `NULL`.
- `IDALS_PMEM_NULL` The IDABBDPRE preconditioner has not been initialized.

In addition to the `ngevalsBBDP` `Gres` evaluations, the costs associated with IDABBDPRE also include `nlinsetups` LU factorizations, `nlinsetups` calls to `Gcomm`, `npsolves` banded backsolve calls, and `nrevalsLS` residual function evaluations, where `nlinsetups` is an optional IDA output (see §4.5.10.2), and `npsolves` and `nrevalsLS` are linear solver optional outputs (see §4.5.10.5).

Chapter 5

FIDA, an Interface Module for FORTRAN Applications

The FIDA interface module is a package of C functions which support the use of the IDA solver, for the solution of DAE systems, in a mixed FORTRAN/C setting. While IDA is written in C, it is assumed here that the user's calling program and user-supplied problem-defining routines are written in FORTRAN. This package provides the necessary interface to IDA for all supplied serial and parallel NVECTOR implementations.

5.1 Important note on portability

In this package, the names of the interface functions, and the names of the FORTRAN user routines called by them, appear as dummy names which are mapped to actual values by a series of definitions in the header files. By default, those mapping definitions depend in turn on the C macro `F77_FUNC` defined in the header file `sundials_config.h`. The mapping defined by `F77_FUNC` in turn transforms the C interface names to match the name-mangling approach used by the supplied Fortran compiler.

By “name-mangling”, we mean that due to the case-independent nature of the FORTRAN language, FORTRAN compilers convert all subroutine and object names to use either all lower-case or all upper-case characters, and append either zero, one or two underscores as a prefix or suffix to the name. For example, the FORTRAN subroutine `MyFunction()` will be changed to one of `myfunction`, `MYFUNCTION`, `myfunction_`, `MYFUNCTION_`, and so on, depending on the FORTRAN compiler used.

SUNDIALS determines this name-mangling scheme at configuration time (see [Appendix A](#)).

5.2 Fortran Data Types

Throughout this documentation, we will refer to data types according to their usage in C. The equivalent types to these may vary, depending on your computer architecture and on how SUNDIALS was compiled (see [Appendix A](#)). A FORTRAN user should first determine the equivalent types for their architecture and compiler, and then take care that all arguments passed through this FORTRAN/C interface are declared of the appropriate type.

Integers: While SUNDIALS uses the configurable `sunindextype` type as the integer type for vector and matrix indices for its C code, the FORTRAN interfaces are more restricted. The `sunindextype` is only used for index values and pointers when filling sparse matrices. As for C, the `sunindextype` can be configured to be a 32- or 64-bit signed integer by setting the variable `SUNDIALS_INDEX_TYPE` at compile time (See [Appendix A](#)). The default value is `int64_t`. A FORTRAN user should set this variable based on the integer type used for vector and matrix indices in their FORTRAN code. The corresponding FORTRAN types are:

- `int32_t` – equivalent to an `INTEGER` or `INTEGER*4` in FORTRAN

- `int64_t` – equivalent to an `INTEGER*8` in FORTRAN

In general, for the FORTRAN interfaces in SUNDIALS, flags of type `int`, vector and matrix lengths, counters, and arguments to `*SETIN()` functions all have `long int` type, and `sunindextype` is only used for index values and pointers when filling sparse matrices. Note that if an F90 (or higher) user wants to find out the value of `sunindextype`, they can include `sundials_fconfig.h`.

Real numbers: As discussed in Appendix A, at compilation SUNDIALS allows the configuration option `SUNDIALS_PRECISION`, that accepts values of `single`, `double` or `extended` (the default is `double`). This choice dictates the size of a `realttype` variable. The corresponding FORTRAN types for these `realttype` sizes are:

- `single` – equivalent to a `REAL` or `REAL*4` in FORTRAN
- `double` – equivalent to a `DOUBLE PRECISION` or `REAL*8` in FORTRAN
- `extended` – equivalent to a `REAL*16` in FORTRAN

5.3 FIDA routines

The user-callable functions, with the corresponding IDA functions, are as follows:

- Interface to the NVECTOR modules
 - `FNVINITS` (defined by `NVECTOR_SERIAL`) interfaces to `N_VNewEmpty_Serial`.
 - `FNVINITP` (defined by `NVECTOR_PARALLEL`) interfaces to `N_VNewEmpty_Parallel`.
 - `FNVINITOMP` (defined by `NVECTOR_OPENMP`) interfaces to `N_VNewEmpty_OpenMP`.
 - `FNVINITPTS` (defined by `NVECTOR_PTHREADS`) interfaces to `N_VNewEmpty_Pthreads`.
- Interface to the SUNMATRIX modules
 - `FSUNBANDMATINIT` (defined by `SUNMATRIX_BAND`) interfaces to `SUNBandMatrix`.
 - `FSUNDENSEMATINIT` (defined by `SUNMATRIX_DENSE`) interfaces to `SUNDenseMatrix`.
 - `FSUNSPARSEMATINIT` (defined by `SUNMATRIX_SPARSE`) interfaces to `SUNSparseMatrix`.
- Interface to the SUNLINSOL modules
 - `FSUNBANDLINSOLINIT` (defined by `SUNLINSOL_BAND`) interfaces to `SUNLinSol_Band`.
 - `FSUNDENSELINSOLINIT` (defined by `SUNLINSOL_DENSE`) interfaces to `SUNLinSol_Dense`.
 - `FSUNKLUINIT` (defined by `SUNLINSOL_KLU`) interfaces to `SUNLinSol_KLU`.
 - `FSUNKLUREINIT` (defined by `SUNLINSOL_KLU`) interfaces to `SUNLinSol_KLUReinit`.
 - `FSUNLAPACKBANDINIT` (defined by `SUNLINSOL_LAPACKBAND`) interfaces to `SUNLinSol_LapackBand`.
 - `FSUNLAPACKDENSEINIT` (defined by `SUNLINSOL_LAPACKDENSE`) interfaces to `SUNLinSol_LapackDense`.
 - `FSUNPCGINIT` (defined by `SUNLINSOL_PCG`) interfaces to `SUNLinSol_PCG`.
 - `FSUNSPBCGSINIT` (defined by `SUNLINSOL_SPBCGS`) interfaces to `SUNLinSol_SPBCGS`.
 - `FSUNSPFGMRINIT` (defined by `SUNLINSOL_SPFGMR`) interfaces to `SUNLinSol_SPFGMR`.
 - `FSUNSPGMRINIT` (defined by `SUNLINSOL_SPGMR`) interfaces to `SUNLinSol_SPGMR`.
 - `FSUNSPTFQMRINIT` (defined by `SUNLINSOL_SPTFQMR`) interfaces to `SUNLinSol_SPTFQMR`.
 - `FSUNSUPERLUMTINIT` (defined by `SUNLINSOL_SUPERLUMT`) interfaces to `SUNLinSol_SuperLUMT`.

-
- Interface to the main IDA module
 - FIDAMALLOC interfaces to IDACreate, IDASetUserData, IDAInit, IDASStolerances, and IDASVtolerances.
 - FIDAREINIT interfaces to IDAReInit and IDASStolerances/IDASVtolerances.
 - FIDASETIIN, FIDASETVIN, and FIDASETRIN interface to IDASet* functions.
 - FIDATOLREINIT interfaces to IDASStolerances/IDASVtolerances.
 - FIDACALCIC interfaces to IDACalcIC.
 - FIDAEWTSET interfaces to IDAWFtolerances.
 - FIDASOLVE interfaces to IDASolve, IDAGet* functions, and to the optional output functions for the selected linear solver module.
 - FIDAGETDKY interfaces to IDAGetDky.
 - FIDAGETERRWEIGHTS interfaces to IDAGetErrWeights.
 - FIDAGETESTLOCALERR interfaces to IDAGetEstLocalErrors.
 - FIDAFREE interfaces to IDAFree.
- Interface to the IDALS module
 - FIDALSINIT interfaces to IDASetLinearSolver.
 - FIDALSSETEPSLIN interfaces to IDASetEpsLin
 - FIDALSSETJAC interfaces to IDASetJacTimes.
 - FIDALSSETPREC interfaces to IDASetPreconditioner.
 - FIDADENSESETJAC interfaces to IDASetJacFn.
 - FIDABANDSETJAC interfaces to IDASetJacFn.
 - FIDASPARSESETJAC interfaces to IDASetJacFn.

The user-supplied functions, each listed with the corresponding internal interface function which calls it (and its type within IDA), are as follows:

| FIDA routine (FORTRAN, user-supplied) | IDA function (C, interface) | IDA type of interface function |
|--|--------------------------------|-----------------------------------|
| FIDARESFUN | FIDaresfn | IDAResFn |
| FIDAEWT | FIDAEwtSet | IDAEwtFn |
| FIDADJAC | FIDADenseJac | IDALsJacFn |
| FIDABJAC | FIDABandJac | IDALsJacFn |
| FIDASPJAC | FIDASparseJac | IDALsJacFn |
| FIDAPSOL | FIDAPSol | IDALsPrecSolveFn |
| FIDAPSET | FIDAPSet | IDALsPrecSetupFn |
| FIDAJTIMES | FIDAJtimes | IDALsJacTimesVecFn |
| FIDAJTSETUP | FIDAJTSetup | IDALsJacTimesSetupFn |

In contrast to the case of direct use of IDA, and of most FORTRAN DAE solvers, the names of all user-supplied routines here are fixed, in order to maximize portability for the resulting mixed-language program.

5.4 Usage of the FIDA interface module

The usage of FIDA requires calls to a variety of interface functions, depending on the method options selected, and one or more user-supplied routines which define the problem to be solved. These function calls and user routines are summarized separately below. Some details are omitted, and the user is referred to the description of the corresponding IDA functions for information on the arguments of any given user-callable interface routine, or of a given user-supplied function called by an interface function. The usage of FIDA for rootfinding, and usage of FIDA with preconditioner modules, are each described in later sections.

1. Residual function specification

The user must, in all cases, supply the following FORTRAN routine

```
SUBROUTINE FIDARESFUN (T, Y, YP, R, IPAR, RPAR, IER)
  DIMENSION Y(*), YP(*), R(*), IPAR(*), RPAR(*)
```

It must set the R array to $F(t, y, \dot{y})$, the residual function of the DAE system, as a function of $T = t$ and the arrays $Y = y$ and $YP = \dot{y}$. The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to FIDAMALLOC. It should return $IER = 0$ if it was successful, $IER = 1$ if it had a recoverable failure, or $IER = -1$ if it had a non-recoverable failure.

2. NVECTOR module initialization

If using one of the NVECTOR modules supplied with SUNDIALS, the user must make a call of the form

```
CALL FNVINIT***(...)
```

in which the name and call sequence are as described in the appropriate section of Chapter 6.

3. SUNMATRIX module initialization

In the case of a stiff system, the implicit BDF method involves the solution of linear systems related to the Jacobian of the DAE system. If using a Newton iteration with the direct SUNLINSOL linear solver module and one of the SUNMATRIX modules supplied with SUNDIALS, the user must make a call of the form

```
CALL FSUN***MATINIT(...)
```

in which the name and call sequence are as described in the appropriate section of Chapter 7. Note that the dense, band, or sparse matrix options are usable only in a serial or multi-threaded environment.

4. SUNLINSOL module initialization

If using a Newton iteration with one of the SUNLINSOL linear solver modules supplied with SUNDIALS, the user must make a call of the form

```
CALL FSUNBANDLINSOLINIT(...)
CALL FSUNDENSELINSOLINIT(...)
CALL FSUNKLUINIT(...)
CALL FSUNLAPACKBANDINIT(...)
CALL FSUNLAPACKDENSEINIT(...)
CALL FSUNPCGINIT(...)
CALL FSUNSPBCGSINIT(...)
CALL FSUNSPFGMRINIT(...)
```

```
CALL FSUNSPGMRINIT(...)
CALL FSUNSPTFQMRINIT(...)
CALL FSUNSUPERLUMTINIT(...)
```

in which the call sequence is as described in the appropriate section of Chapter 8. Note that the dense, band, or sparse solvers are usable only in a serial or multi-threaded environment.

Once one of these solvers has been initialized, its solver parameters may be modified using a call to the functions

```
CALL FSUNKLUSETORDERING(...)
CALL FSUNSUPERLUMTSETORDERING(...)
CALL FSUNPCGSETPRECTYPE(...)
CALL FSUNPCGSETMAXL(...)
CALL FSUNSPBCGSSETPRECTYPE(...)
CALL FSUNSPBCGSSETMAXL(...)
CALL FSUNSPFGMRSETGSTYPE(...)
CALL FSUNSPFGMRSETPRECTYPE(...)
CALL FSUNSPGMRSETGSTYPE(...)
CALL FSUNSPGMRSETPRECTYPE(...)
CALL FSUNSPTFQMRSETPRECTYPE(...)
CALL FSUNSPTFQMRSETMAXL(...)
```

where again the call sequences are described in the appropriate sections of Chapter 8.

5. Problem specification

To set various problem and solution parameters and allocate internal memory, make the following call:

FIDAMALLOC

| | |
|--------------|--|
| Call | CALL FIDAMALLOC(TO, YO, YPO, IATOL, RTOL, ATOL, & IOUT, ROUT, IPAR, RPAR, IER) |
| Description | This function provides required problem and solution specifications, specifies optional inputs, allocates internal memory, and initializes IDA. |
| Arguments | <p>TO is the initial value of t.</p> <p>YO is an array of initial conditions for y.</p> <p>YPO is an array of initial conditions for \dot{y}.</p> <p>IATOL specifies the type for absolute tolerance ATOL: 1 for scalar or 2 for array. If IATOL = 3, the arguments RTOL and ATOL are ignored and the user is expected to subsequently call FIDAEWTSET and provide the function FIDAEWT.</p> <p>RTOL is the relative tolerance (scalar).</p> <p>ATOL is the absolute tolerance (scalar or array).</p> <p>IOUT is an integer array of length at least 21 for integer optional outputs.</p> <p>ROUT is a real array of length at least 6 for real optional outputs.</p> <p>IPAR is an integer array of user data which will be passed unmodified to all user-provided routines.</p> <p>RPAR is a real array of user data which will be passed unmodified to all user-provided routines.</p> |
| Return value | IER is a return completion flag. Values are 0 for successful return and -1 otherwise. See printed message for details in case of failure. |
| Notes | The user integer data arrays IOUT and IPAR must be declared as INTEGER*4 or INTEGER*8 according to the C type long int. |

Modifications to the user data arrays `IPAR` and `RPAR` inside a user-provided routine will be propagated to all subsequent calls to such routines.

The optional outputs associated with the main IDA integrator are listed in Table 5.2.

As an alternative to providing tolerances in the call to `FIDAMALLOC`, the user may provide a routine to compute the error weights used in the WRMS norm evaluations. If supplied, it must have the following form:

```
SUBROUTINE FIDAEWT (Y, EWT, IPAR, RPAR, IER)
  DIMENSION Y(*), EWT(*), IPAR(*), RPAR(*)
```

It must set the positive components of the error weight vector `EWT` for the calculation of the WRMS norm of `Y`. On return, set `IER` = 0 if `FIDAEWT` was successful, and nonzero otherwise. The arrays `IPAR` (of integers) and `RPAR` (of reals) contain user data and are the same as those passed to `FIDAMALLOC`.

If the `FIDAEWT` routine is provided, then, following the call to `FIDAMALLOC`, the user must make the call:

```
CALL FIDAEWTSET (FLAG, IER)
```

with `FLAG` \neq 0 to specify use of the user-supplied error weight routine. The argument `IER` is an error return flag, which is 0 for success or non-zero if an error occurred.

6. Set optional inputs

Call `FIDASETIIN`, `FIDASETRIN`, and/or `FIDASETVIN` to set desired optional inputs, if any. See §5.5 for details.

7. Linear solver interface specification

The variable-order, variable-coefficient BDF method used by IDA involves the solution of linear systems related to the system Jacobian $J = \partial F / \partial y + \alpha \partial F / \partial \dot{y}$. See Eq. (2.4). To attach the linear solver (and optionally the matrix) objects initialized in steps 3 and 4 above, the user of FIDA must initialize the IDALS linear solver interface. To attach any `SUNLINSOL` object (and optional `SUNMATRIX` object) to IDA, then following calls to initialize the `SUNLINSOL` (and `SUNMATRIX`) object(s) in steps 3 and 4 above, the user must make the call:

```
CALL FIDALSINIT(IER)
```

`IER` is an error return flag set on 0 on success or -1 if a memory failure occurred.

The previous routines `FIDADLSINIT` and `FIDASPILSINIT` are now wrappers for this routine, and may still be used for backward-compatibility. However, these will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

IDALS with dense Jacobian matrix

As an option when using the IDALS interface with the `SUNLINSOL_DENSE` or `SUNLINSOL_LAPACKDENSE` linear solvers, the user may supply a routine that computes a dense approximation of the system Jacobian J . If supplied, it must have the following form:

```
SUBROUTINE FIDADJAC (NEQ, T, Y, YP, R, DJAC, CJ, EWT, H,
&                    IPAR, RPAR, WK1, WK2, WK3, IER)
  DIMENSION Y(*), YP(*), R(*), EWT(*), DJAC(NEQ,*),
&                    IPAR(*), RPAR(*), WK1(*), WK2(*), WK3(*)
```

This routine must compute the Jacobian and store it columnwise in `DJAC`. The vectors `WK1`, `WK2`, and `WK3` of length `NEQ` are provided as work space for use in `FIDADJAC`. The input arguments `T`, `Y`,

YP, R, and CJ are the current values of t , y , \dot{y} , $F(t, y, \dot{y})$, and α , respectively. The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to FIDAMALLOC. NOTE: The argument NEQ has a type consistent with C type `long int` even in the case when the LAPACK dense solver is to be used.

If the user's FIDADJAC uses difference quotient approximations, it may need to use the error weight array EWT and current stepsize H in the calculation of suitable increments. It may also need the unit roundoff, which can be obtained as the optional output ROUT(6), passed from the calling program to this routine using COMMON.

If the FIDADJAC routine is provided, then, following the call to FIDALSINIT the user must make the call:

```
CALL FIDADENSESETJAC (FLAG, IER)
```

with FLAG $\neq 0$ to specify use of the user-supplied Jacobian approximation. The argument IER is an error return flag, which is 0 for success or non-zero if an error occurred.

IDLALS with band Jacobian matrix

As an option when using the IDALS interface with the SUNLINSOL_BAND or SUNLINSOL_LAPACKBAND linear solvers, the user may supply a routine that computes a band approximation of the system Jacobian J . If supplied, it must have the following form:

```
SUBROUTINE FIDABJAC(NEQ, MU, ML, MDIM, T, Y, YP, R, CJ, BJAC,
&                  EWT, H, IPAR, RPAR, WK1, WK2, WK3, IER)
  DIMENSION Y(*), YP(*), R(*), EWT(*), BJAC(MDIM,*),
&          IPAR(*), RPAR(*), WK1(*), WK2(*), WK3(*)
```

This routine must load the MDIM by NEQ array BJAC with the Jacobian matrix at the current (t, y, \dot{y}) in band form. Store in $BJAC(k, j)$ the Jacobian element $J_{i,j}$ with $k = i - j + MU + 1$ ($k = 1 \cdots ML + MU + 1$) and $j = 1 \cdots N$. The vectors WK1, WK2, and WK3 of length NEQ are provided as work space for use in FIDABJAC. The input arguments T, Y, YP, R, and CJ are the current values of t , y , \dot{y} , $F(t, y, \dot{y})$, and α , respectively. The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to FIDAMALLOC. NOTE: The arguments NEQ, MU, ML, and MDIM have a type consistent with C type `long int` even in the case when the LAPACK band solver is to be used.

If the user's FIDABJAC uses difference quotient approximations, it may need to use the error weight array EWT and current stepsize H in the calculation of suitable increments. It may also need the unit roundoff, which can be obtained as the optional output ROUT(6), passed from the calling program to this routine using COMMON.

If the FIDABJAC routine is provided, then, following the call to FIDALSINIT, the user must make the call:

```
CALL FIDABANDSETJAC (FLAG, IER)
```

with FLAG $\neq 0$ to specify use of the user-supplied Jacobian approximation. The argument IER is an error return flag, which is 0 for success or non-zero if an error occurred.

IDLALS with sparse Jacobian matrix

When using the IDALS interface with the SUNLINSOL_KLU or SUNLINSOL_SUPERLUMT linear solvers, the user must supply the FIDASPJAC routine that computes a compressed-sparse-column (CSC) or compressed-sparse-row (CSR) approximation of the system Jacobian $J = \partial F / \partial y + c_j \partial F / \partial \dot{y}$. If supplied, it must have the following form:

```
SUBROUTINE FIDASPJAC(T, CJ, Y, YP, R, N, NNZ, JDATA, JINDEXVALS,
&                  JINDEXPTRS, H, IPAR, RPAR, WK1, WK2, WK3, IER)
```

It must load the N by N compressed sparse column [or compressed sparse row] matrix with storage for NNZ nonzeros, stored in the arrays `JDATA` (nonzero values), `JINDEXVALS` (row [or column] indices for each nonzero), `JINDEXPTRS` (indices for start of each column [or row]), with the Jacobian matrix at the current (t, y) in CSC [or CSR] form (see `summatrix.sparse.h` for more information). The arguments are `T`, the current time; `CJ`, scalar in the system proportional to the inverse step size; `Y`, an array containing state variables; `YP`, an array containing state derivatives; `R`, an array containing the system nonlinear residual; `N`, the number of matrix rows/columns in the Jacobian; `NNZ`, allocated length of nonzero storage; `JDATA`, nonzero values in the Jacobian (of length `NNZ`); `JINDEXVALS`, row [or column] indices for each nonzero in Jacobian (of length `NNZ`); `JINDEXPTRS`, pointers to each Jacobian column [or row] in the two preceding arrays (of length $N+1$); `H`, the current step size; `IPAR`, an array containing integer user data that was passed to `FIDAMALLOC`; `RPAR`, an array containing real user data that was passed to `FIDAMALLOC`; `WK*`, work arrays containing temporary workspace of same size as `Y`; and `IER`, error return code (0 if successful, > 0 if a recoverable error occurred, or < 0 if an unrecoverable error occurred.)

To indicate that the `FIDASPJAC` routine has been provided, then following the call to `FIDALSINIT`, the following call must be made

```
CALL FIDAPARSESETJAC (IER)
```

The int return flag `IER` is an error return flag which is 0 for success or nonzero for an error.

IDALS with Jacobian-vector product

As an option when using the IDALS linear solver interface, the user may supply a routine that computes the product of the system Jacobian $J = \partial F / \partial y + \alpha \partial F / \partial \dot{y}$ and a given vector v . If supplied, it must have the following form:

```
SUBROUTINE FIDAJTIMES(T, Y, YP, R, V, FJV, CJ, EWT, H,
&                      IPAR, RPAR, WK1, WK2, IER)
  DIMENSION Y(*), YP(*), R(*), V(*), FJV(*), EWT(*),
&          IPAR(*), RPAR(*), WK1(*), WK2(*)
```

This routine must compute the product vector Jv , where the vector v is stored in `V`, and store the product in `FJV`. On return, set `IER` = 0 if `FIDAJTIMES` was successful, and nonzero otherwise. The vectors `WK1` and `WK2`, of length `NEQ`, are provided as work space for use in `FIDAJTIMES`. The input arguments `T`, `Y`, `YP`, `R`, and `CJ` are the current values of t , y , \dot{y} , $F(t, y, \dot{y})$, and α , respectively. The arrays `IPAR` (of integers) and `RPAR` (of reals) contain user data and are the same as those passed to `FIDAMALLOC`.

If the user's `FIDAJTIMES` uses difference quotient approximations, it may need to use the error weight array `EWT` and current stepsize `H` in the calculation of suitable increments. It may also need the unit roundoff, which can be obtained as the optional output `ROUT(6)`, passed from the calling program to this routine using `COMMON`.

If the user's Jacobian-times-vector product routine requires that any Jacobian related data be evaluated or preprocessed, then the following routine can be used for the evaluation and preprocessing of this data:

```
SUBROUTINE FIDAJTSETUP (T, Y, YP, R, CJ, EWT, H, IPAR, RPAR, IER)
  DIMENSION Y(*), YP(*), R(*), EWT(*), IPAR(*), RPAR(*)
```

Typically this routine will use only `T`, `Y`, and `IDAYP`. It should compute any necessary data for subsequent calls to `FIDAJTIMES`. On return, set `IER` = 0 if `FIDAJTSETUP` was successful, and nonzero otherwise. The arrays `IPAR` (of integers) and `RPAR` (of reals) contain user data and are the same as those passed to `FIDAMALLOC`.

To indicate that the `FIDAJTIMES` and `FIDAJTSETUP` routines have been provided, then following the call to `FIDALSINIT`, the following call must be made

```
CALL FIDALSSETJAC (FLAG, IER)
```

with $\text{FLAG} \neq 0$. The return flag IER is 0 if successful, or negative if a memory error occurred.

The previous routine `FIDASPILSETJAC` is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.

If the user calls `FIDALSSETJAC`, the routine `FIDAJTSETUP` must be provided, even if it is not needed, and it must return $\text{IER}=0$.



IDALS with preconditioning

If user-supplied preconditioning is to be performed, the following routine must be supplied for solution of the preconditioner linear system:

```
SUBROUTINE FIDAPSOL(T, Y, YP, R, RV, ZV, CJ, DELTA, EWT,
&                  IPAR, RPAR, IER)
  DIMENSION Y(*), YP(*), R(*), RV(*), ZV(*), EWT(*),
&          IPAR(*), RPAR(*)
```

It must solve the preconditioner linear system $Pz = r$, where $r = \text{RV}$ is input, and store the solution z in ZV . Here P is the left preconditioner. The input arguments T , Y , YP , R , and CJ are the current values of t , y , \dot{y} , $F(t, y, \dot{y})$, and α , respectively. On return, set $\text{IER} = 0$ if `FIDAPSOL` was successful, set IER positive if a recoverable error occurred, and set IER negative if a non-recoverable error occurred.

The arguments EWT and DELTA are input and provide the error weight array and a scalar tolerance, respectively, for use by `FIDAPSOL` if it uses an iterative method in its solution. In that case, the residual vector $\rho = r - Pz$ of the system should be made less than DELTA in weighted ℓ_2 norm, i.e. $\sqrt{\sum (\rho_i * \text{EWT}[i])^2} < \text{DELTA}$. The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to `FIDAMALLOC`.

If the user's preconditioner requires that any Jacobian-related data be evaluated or preprocessed, then the following routine is to be used for the evaluation and preprocessing of the preconditioner:

```
SUBROUTINE FIDAPSET(T, Y, YP, R, CJ, EWT, H,
&                  IPAR, RPAR, IER)
  DIMENSION Y(*), YP(*), R(*), EWT(*),
&          IPAR(*), RPAR(*)
```

It must perform any evaluation of Jacobian-related data and preprocessing needed for the solution of the preconditioner linear systems by `FIDAPSOL`. The input arguments T , Y , YP , R , and CJ are the current values of t , y , \dot{y} , $F(t, y, \dot{y})$, and α , respectively. On return, set $\text{IER} = 0$ if `FIDAPSET` was successful, set IER positive if a recoverable error occurred, and set IER negative if a non-recoverable error occurred. The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to `FIDAMALLOC`.

If the user's `FIDAPSET` uses difference quotient approximations, it may need to use the error weight array EWT and current stepsize H in the calculation of suitable increments. It may also need the unit roundoff, which can be obtained as the optional output $\text{ROUT}(6)$, passed from the calling program to this routine using `COMMON`.

To indicate that the `FIDAPSET` and `FIDAPSOL` routines are supplied, then following the call to `FIDALSINIT`, the user must call

```
CALL FIDALSSETPREC (FLAG, IER)
```

with `FLAG` $\neq 0$. The return flag `IER` is 0 if successful, or negative if a memory error occurred. In addition, the user must supply preconditioner routines `FIDAPSET` and `FIDAPSOL`.

The previous routine `FIDASPILSETPREC` is now a wrapper for this routine, and may still be used for backward-compatibility. However, this will be deprecated in future releases, so we recommend that users transition to the new routine name soon.



If the user calls `FIDALSSETPREC`, the subroutine `FIDAPSET` must be provided, even if it is not needed, and it must return `IER = 0`.

8. Correct initial values

Optionally, to correct the initial values y and/or \dot{y} , make the call

```
CALL FIDACALCIC (ICOPT, TOUT1, IER)
```

(See §2.1 for details.) The arguments are as follows: `ICOPT` is 1 for initializing the algebraic components of y and differential components of \dot{y} , or 2 for initializing all of y . `IER` is an error return flag, which is 0 for success, or negative for a failure (see `IDACalcIC` return values).

9. Problem solution

Carrying out the integration is accomplished by making calls as follows:

```
CALL FIDASOLVE (TOUT, T, Y, YP, ITASK, IER)
```

The arguments are as follows. `TOUT` specifies the next value of t at which a solution is desired (input). `T` is the value of t reached by the solver on output. `Y` is an array containing the computed solution vector y on output. `YP` is an array containing the computed solution vector \dot{y} on output. `ITASK` is a task indicator and should be set to 1 for normal mode (overshoot `TOUT` and interpolate), or to 2 for one-step mode (return after each internal step taken). `IER` is a completion flag and will be set to a positive value upon successful return or to a negative value if an error occurred. These values correspond to the `IDASolve` returns (see §4.5.7 and §B.2). The current values of the optional outputs are available in `IOUT` and `ROUT` (see Table 5.2).

10. Additional solution output

After a successful return from `FIDASOLVE`, the routine `FIDAGETDKY` may be called to get interpolated values of y or any derivative $d^k y/dt^k$ for k not exceeding the current method order, and for any value of t in the last internal step taken by IDA. The call is as follows:

```
CALL FIDAGETDKY (T, K, DKY, IER)
```

where `T` is the input value of t at which solution derivative is desired, `K` is the derivative order, and `DKY` is an array containing the computed vector $y^{(K)}(t)$ on return. The value of `T` must lie between `TCUR - HLAST` and `TCUR`. The value of `K` must satisfy $0 \leq K \leq \text{QLAST}$. (See the optional outputs for `TCUR`, `HLAST`, and `QLAST`.) The return flag `IER` is set to 0 upon successful return, or to a negative value to indicate an illegal input.

11. Problem reinitialization

To re-initialize the IDA solver for the solution of a new problem of the same size as one already solved, make the following call:

```
CALL FIDAREINIT (T0, Y0, YP0, IATOL, RTOL, ATOL, IER)
```

The arguments have the same names and meanings as those of `FIDAMALLOC`. `FIDAREINIT` performs the same initializations as `FIDAMALLOC`, but does no memory allocation, using instead the existing internal memory created by the previous `FIDAMALLOC` call.

Following this call, if the choice of linear solver is being changed then a user must make a call to create the alternate SUNLINSOL module and then attach it to the IDALS interface, as shown above. If only linear solver parameters are being modified, then these calls may be made without re-attaching to the IDALS interface.

12. Memory deallocation

To free the internal memory created by the call to FIDAMALLOC, FIDALSINIT, FNVINIT* and FSUN***MATINIT, make the call

```
CALL FIDAFREE
```

5.5 FIDA optional input and output

In order to keep the number of user-callable FIDA interface routines to a minimum, optional inputs to the IDA solver are passed through only three routines: FIDASETIIN for integer optional inputs, FIDASETRIN for real optional inputs, and FIDASETVIN for real vector (array) optional inputs. These functions should be called as follows:

```
CALL FIDASETIIN(KEY, IVAL, IER)
CALL FIDASETRIN(KEY, RVAL, IER)
CALL FIDASETVIN(KEY, VVAL, IER)
```

where KEY is a quoted string indicating which optional input is set (see Table 5.1), IVAL is the input integer value, RVAL is the input real value (scalar), VVAL is the input real array, and IER is an integer return flag which is set to 0 on success and a negative value if a failure occurred. IVAL should be declared so as to match C type `long int`.

When using FIDASETVIN to specify the variable types (KEY = 'ID_VEC') the components in the array VVAL must be 1.0 to indicate a differential variable, or 0.0 to indicate an algebraic variable. Note that this array is required only if FIDACALCIC is to be called with ICOPT = 1, or if algebraic variables are suppressed from the error test (indicated using FIDASETIIN with KEY = 'SUPPRESS_ALG'). When using FIDASETVIN to specify optional constraints on the solution vector (KEY = 'CONSTR_VEC') the components in the array VVAL should be one of -2.0, -1.0, 0.0, 1.0, or 2.0. See the description of IDASetConstraints (§4.5.8.1) for details.

The optional outputs from the IDA solver are accessed not through individual functions, but rather through a pair of arrays, IOUT (integer type) of dimension at least 21, and ROUT (real type) of dimension at least 6. These arrays are owned (and allocated) by the user and are passed as arguments to FIDAMALLOC. Table 5.2 lists the entries in these two arrays and specifies the optional variable as well as the IDA function which is actually called to extract the optional output.

For more details on the optional inputs and outputs, see §4.5.8 and §4.5.10.

In addition to the optional inputs communicated through FIDASET* calls and the optional outputs extracted from IOUT and ROUT, the following user-callable routines are available:

To reset the tolerances at any time, make the following call:

```
CALL FIDATOLREINIT (IATOL, RTOL, ATOL, IER)
```

The tolerance arguments have the same names and meanings as those of FIDAMALLOC. The error return flag IER is 0 if successful, and negative if there was a memory failure or illegal input.

To obtain the error weight array EWT, containing the multiplicative error weights used the WRMS norms, make the following call:

```
CALL FIDAGETERRWEIGHTS (EWT, IER)
```

This computes the EWT array, normally defined by Eq. (2.6). The array EWT, of length NEQ or NLOCAL, must already have been declared by the user. The error return flag IER is zero if successful, and negative if there was a memory error.

Table 5.1: Keys for setting FIDA optional inputs

| Integer optional inputs (FIDASETIIN) | | |
|--------------------------------------|---|----------------|
| Key | Optional input | Default value |
| MAX_ORD | Maximum LMM method order | 5 |
| MAX_NSTEPS | Maximum no. of internal steps before t_{out} | 500 |
| MAX_ERRFAIL | Maximum no. of error test failures | 10 |
| MAX_NITERS | Maximum no. of nonlinear iterations | 4 |
| MAX_CONVFAIL | Maximum no. of convergence failures | 10 |
| SUPPRESS_ALG | Suppress alg. vars. from error test (1 = SUNTRUE) | 0 (= SUNFALSE) |
| MAX_NSTEPS_IC | Maximum no. of steps for IC calc. | 5 |
| MAX_NITERS_IC | Maximum no. of Newton iterations for IC calc. | 10 |
| MAX_NJE_IC | Maximum no. of Jac. evals fo IC calc. | 4 |
| LS_OFF_IC | Turn off line search (1 = SUNTRUE) | 0 (= SUNFALSE) |

| Real optional inputs (FIDASETRIN) | | |
|-----------------------------------|---|-----------------------|
| Key | Optional input | Default value |
| INIT_STEP | Initial step size | estimated |
| MAX_STEP | Maximum absolute step size | ∞ |
| STOP_TIME | Value of t_{stop} | undefined |
| NLCONV_COEF | Coeff. in the nonlinear conv. test | 0.33 |
| NLCONV_COEF_IC | Coeff. in the nonlinear conv. test for IC calc. | 0.0033 |
| STEP_TOL_IC | Lower bound on Newton step for IC calc. | around ^{2/3} |

| Real vector optional inputs (FIDASETVIN) | | |
|--|--|---------------|
| Key | Optional input | Default value |
| ID_VEC | Differential/algebraic component types | undefined |
| CONSTR_VEC | Inequality constraints on solution | undefined |

Table 5.2: Description of the FIDA optional output arrays IOUT and ROUT

| Integer output array IOUT | | |
|-------------------------------|-----------------|---------------------------|
| Index | Optional output | IDA function |
| IDA main solver | | |
| 1 | LENRW | IDAGetWorkSpace |
| 2 | LENIW | IDAGetWorkSpace |
| 3 | NST | IDAGetNumSteps |
| 4 | NRE | IDAGetNumResEvals |
| 5 | NETF | IDAGetNumErrTestFails |
| 6 | NNCFAILS | IDAGetNonlinSolvConvFails |
| 7 | NNI | IDAGetNumNonlinSolvIters |
| 8 | NSETUPS | IDAGetNumLinSolvSetups |
| 9 | QLAST | IDAGetLastOrder |
| 10 | QCUR | IDAGetCurrentOrder |
| 11 | NBCKTRKOPS | IDAGetNumBacktrackOps |
| 12 | NGE | IDAGetNumGEvals |
| IDALS linear solver interface | | |
| 13 | LENRWLS | IDAGetLinWorkSpace |
| 14 | LENIWLS | IDAGetLinWorkSpace |
| 15 | LS_FLAG | IDAGetLastLinFlag |
| 16 | NRELS | IDAGetNumLinResEvals |
| 17 | NJE | IDAGetNumJacEvals |
| 18 | NJTS | IDAGetNumJTSetupEvals |
| 19 | NJT | IDAGetNumJtimesEvals |
| 20 | NPE | IDAGetNumPrecEvals |
| 21 | NPS | IDAGetNumPrecSolves |
| 22 | NLI | IDAGetNumLinIters |
| 23 | NCFL | IDAGetNumLinConvFails |
| Real output array ROUT | | |
| Index | Optional output | IDA function |
| 1 | H0_USED | IDAGetActualInitStep |
| 2 | HLAST | IDAGetLastStep |
| 3 | HCUR | IDAGetCurrentStep |
| 4 | TCUR | IDAGetCurrentTime |
| 5 | TOLFACT | IDAGetTolScaleFactor |
| 6 | UROUND | unit roundoff |

To obtain the estimated local errors, following a successful call to `FIDASOLVE`, make the following call:

```
CALL FIDAGETESTLOCALERR (ELE, IER)
```

This computes the `ELE` array of estimated local errors as of the last step taken. The array `ELE` must already have been declared by the user. The error return flag `IER` is zero if successful, and negative if there was a memory error.

5.6 Usage of the FIDAROOT interface to rootfinding

The `FIDAROOT` interface package allows programs written in FORTRAN to use the rootfinding feature of the `IDA` solver module. The user-callable functions in `FIDAROOT`, with the corresponding `IDA` functions, are as follows:

- `FIDAROOTINIT` interfaces to `IDARootInit`.
- `FIDAROOTINFO` interfaces to `IDAGetRootInfo`.
- `FIDAROOTFREE` interfaces to `IDARootFree`.

Note that, at this time `FIDAROOT` does not provide support to specify the direction of zero-crossing that is to be monitored. Instead, all roots are considered. However, the actual direction of zero-crossing is reported (through the sign of the non-zero elements in the array `INFO` returned by `FIDAROOTINFO`).

In order to use the rootfinding feature of `IDA`, the following call must be made, after calling `FIDAMALLOC` but prior to calling `FIDASOLVE`, to allocate and initialize memory for the `FIDAROOT` module:

```
CALL FIDAROOTINIT (NRTFN, IER)
```

The arguments are as follows: `NRTFN` is the number of root functions. `IER` is a return completion flag; its values are 0 for success, -1 if the `IDA` memory was `NULL`, and -14 if a memory allocation failed.

To specify the functions whose roots are to be found, the user must define the following routine:

```
SUBROUTINE FIDAROOTFN (T, Y, YP, G, IPAR, RPAR, IER)
  DIMENSION Y(*), YP(*), G(*), IPAR(*), RPAR(*)
```

It must set the `G` array, of length `NRTFN`, with components $g_i(t, y, \dot{y})$, as a function of $T = t$ and the arrays $Y = y$ and $YP = \dot{y}$. The arrays `IPAR` (of integers) and `RPAR` (of reals) contain user data and are the same as those passed to `FIDAMALLOC`. Set `IER` on 0 if successful, or on a non-zero value if an error occurred.

When making calls to `FIDASOLVE` to solve the DAE system, the occurrence of a root is flagged by the return value `IER = 2`. In that case, if `NRTFN > 1`, the functions g_i which were found to have a root can be identified by making the following call:

```
CALL FIDAROOTINFO (NRTFN, INFO, IER)
```

The arguments are as follows: `NRTFN` is the number of root functions. `INFO` is an integer array of length `NRTFN` with root information. `IER` is a return completion flag; its values are 0 for success, negative if there was a memory failure. The returned values of `INFO(i)` ($i = 1, \dots, NRTFN$) are 0 or ± 1 , such that `INFO(i) = +1` if g_i was found to have a root and g_i is increasing, `INFO(i) = -1` if g_i was found to have a root and g_i is decreasing, and `INFO(i) = 0` otherwise.

The total number of calls made to the root function `FIDAROOTFN`, denoted `NGE`, can be obtained from `IOUT(12)`. If the `FIDA/IDA` memory block is reinitialized to solve a different problem via a call to `FIDAREINIT`, then the counter `NGE` is reset to zero.

To free the memory resources allocated by a prior call to `FIDAROOTINIT`, make the following call:

```
CALL FIDAROOTFREE
```

See §4.5.6 for additional information on the rootfinding feature.

5.7 Usage of the FIDABBD interface to IDABBDPRE

The FIDABBD interface sub-module is a package of C functions which, as part of the FIDA interface module, support the use of the IDA solver with the parallel NVECTOR_PARALLEL module, in a combination of any of the Krylov iterative solver modules with the IDABBDPRE preconditioner module (see §4.7).

The user-callable functions in this package, with the corresponding IDA and IDABBDPRE functions, are as follows:

- FIDABBDINIT interfaces to IDABBDPrecAlloc.
- FIDABBDREINIT interfaces to IDABBDPrecReInit.
- FIDABBDOPT interfaces to IDABBDPRE optional output functions.
- FIDABBDFREE interfaces to IDABBDPrecFree.

In addition to the FORTRAN residual function FIDARESFUN, the user-supplied functions used by this package, are listed below, each with the corresponding interface function which calls it (and its type within IDABBDPRE or IDA):

| FIDABBD routine (FORTRAN) | IDA function (C) | IDA function type |
|---------------------------|------------------|----------------------|
| FIDAGLOCFN | FIDAgloc | IDABBDLocalFn |
| FIDACOMMFN | FIDAcfn | IDABBDCommFn |
| FIDAJTIMES | FIDAJtimes | IDALsJacTimesVecFn |
| FIDAJTSETUP | FIDAJTSetup | IDALsJacTimesSetupFn |

As with the rest of the FIDA routines, the names of all user-supplied routines here are fixed, in order to maximize portability for the resulting mixed-language program. Additionally, based on flags discussed above in §5.3, the names of the user-supplied routines are mapped to actual values through a series of definitions in the header file `fidabbd.h`.

The following is a summary of the usage of this module. Steps that are unchanged from the main program described in §5.4 are grayed-out.

1. Residual function specification

2. NVECTOR module initialization

3. SUNLINSOL module initialization

Initialize one of the iterative SUNLINSOL modules, by calling one of FSUNPCGINIT, FSUNSPBCGSINIT, FSUNSPFGMRINIT, FSUNSPGMRINIT or FSUNSPTFQMRINIT.

4. Problem specification

5. Set optional inputs

6. Linear solver interface specification

Initialize the IDALS iterative linear solver interface by calling FIDALSINIT.

7. BBD preconditioner initialization

To initialize the IDABBDPRE preconditioner, make the following call:

```
CALL FIDABBDINIT (NLOCAL, MUDQ, MLDQ, MU, ML, DQRELY, IER)
```

The arguments are as follows. NLOCAL is the local size of vectors on this processor. MUDQ and MLDQ are the upper and lower half-bandwidths to be used in the computation of the local Jacobian blocks by difference quotients. These may be smaller than the true half-bandwidths of the Jacobian of

the local block of G , when smaller values may provide greater efficiency. MU and ML are the upper and lower half-bandwidths of the band matrix that is retained as an approximation of the local Jacobian block. These may be smaller than MUDQ and MLDQ. DQRELY is the relative increment factor in y for difference quotients (optional). A value of 0.0 indicates the default, $\sqrt{\text{unit roundoff}}$. IER is a return completion flag. A value of 0 indicates success, while a value of -1 indicates that a memory failure occurred or that an input had an illegal value.

8. Correct initial values

9. Problem solution

10. Additional solution output

11. IDABBDPRE Optional outputs

Optional outputs specific to the SPGMR, SPBCGS, or SPTFQMR solver are listed in Table 5.2. To obtain the optional outputs associated with the IDABBDPRE module, make the following call:

```
CALL FIDABBDOPT (LENRWBBD, LENIWBBBD, NGEBBBD)
```

The arguments should be consistent with C type `long int`. Their returned values are as follows: LENRWBBD is the length of real preconditioner work space, in `realtype` words. LENIWBBBD is the length of integer preconditioner work space, in integer words. Both of these sizes are local to the current processor. NGEBBBD is the number of $G(t, y, \dot{y})$ evaluations (calls to FIDALOCFN) so far.

12. Problem reinitialization

If a sequence of problems of the same size is being solved using the same linear solver in combination with the IDABBDPRE preconditioner, then the IDA package can be re-initialized for the second and subsequent problems by calling FIDAREINIT, following which a call to FIDABBDINIT may or may not be needed. If the input arguments are the same, no FIDABBDINIT call is needed. If there is a change in input arguments other than MU or ML, then the user program should make the call

```
CALL FIDABBDREINIT (NLOCAL, MUDQ, MLDQ, DQRELY, IER)
```

This reinitializes the IDABBDPRE preconditioner, but without reallocating its memory. The arguments of the FIDABBDREINIT routine have the same names and meanings as those of FIDABBDINIT. If the value of MU or ML is being changed, then a call to FIDABBDINIT must be made. Finally, if there is a change in any of the linear solver inputs, then a call to one of FSUN****INIT, followed by a call to FIDALSINIT must also be made; in this case the linear solver memory is reallocated.

13. Memory deallocation

(The memory allocated for the FIDABBD module is deallocated automatically by FIDAFREE.)

14. User-supplied routines

The following two routines must be supplied for use with the IDABBDPRE module:

```
SUBROUTINE FIDAGLOCFN (NLOC, T, YLOC, YPLOC, GLOC, IPAR, RPAR, IER)
  DIMENSION YLOC(*), YPLOC(*), GLOC(*), IPAR(*), RPAR(*)
```

This routine is to evaluate the function $G(t, y, \dot{y})$ approximating F (possibly identical to F), in terms of $T = t$, and the arrays YLOC and YPLOC (of length NLOC), which are the sub-vectors of y and \dot{y} local to this processor. The resulting (local) sub-vector is to be stored in the array GLOC. IER is a return flag that should be set to 0 if successful, to 1 (for a recoverable error), or to -1 (for a non-recoverable error). The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to FIDAMALLOC.

```
SUBROUTINE FIDACOMMFN (NLOC, T, YLOC, YPLOC, IPAR, RPAR, IER)
  DIMENSION YLOC(*), YPLOC(*), IPAR(*), RPAR(*)
```

This routine is to perform the inter-processor communication necessary for the FIDAGLOCFN routine. Each call to FIDACOMMFN is preceded by a call to the residual routine FIDARESFUN with the same arguments T, YLOC, and YPLOC. Thus FIDACOMMFN can omit any communications done by FIDARESFUN if relevant to the evaluation of GLOC. The arrays IPAR (of integers) and RPAR (of reals) contain user data and are the same as those passed to FIDAMALLOC. IER is a return flag that should be set to 0 if successful, to 1 (for a recoverable error), or to -1 (for a non-recoverable error).

The subroutine FIDACOMMFN must be supplied even if it is empty, and it must return IER = 0.

Optionally, the user can supply routines FIDAJTIMES and FIDAJTSETUP for the evaluation of Jacobian-vector products, as described above in step 7 in §5.4.



Chapter 6

Description of the NVECTOR module

The SUNDIALS solvers are written in a data-independent manner. They all operate on generic vectors (of type `N_Vector`) through a set of operations defined by the particular NVECTOR implementation. Users can provide their own specific implementation of the NVECTOR module, or use one of the implementations provided with SUNDIALS. The generic operations are described below and the implementations provided with SUNDIALS are described in the following sections.

The generic `N_Vector` type is a pointer to a structure that has an implementation-dependent *content* field containing the description and actual data of the vector, and an *ops* field pointing to a structure with generic vector operations. The type `N_Vector` is defined as

```
typedef struct _generic_N_Vector *N_Vector;
```

```
struct _generic_N_Vector {  
    void *content;  
    struct _generic_N_Vector_Ops *ops;  
};
```

The `_generic_N_Vector_Ops` structure is essentially a list of pointers to the various actual vector operations, and is defined as

```
struct _generic_N_Vector_Ops {  
    N_Vector_ID (*nvgetvectorid)(N_Vector);  
    N_Vector (*nvclone)(N_Vector);  
    N_Vector (*nvcloneempty)(N_Vector);  
    void (*nvdestroy)(N_Vector);  
    void (*nvspace)(N_Vector, sunindextype *, sunindextype *);  
    realtype* (*nvgetarraypointer)(N_Vector);  
    void (*nvsetarraypointer)(realtype *, N_Vector);  
    void (*nvlinearsum)(realtype, N_Vector, realtype, N_Vector, N_Vector);  
    void (*nvconst)(realtype, N_Vector);  
    void (*nvprod)(N_Vector, N_Vector, N_Vector);  
    void (*nvdiv)(N_Vector, N_Vector, N_Vector);  
    void (*nvscale)(realtype, N_Vector, N_Vector);  
    void (*nvabs)(N_Vector, N_Vector);  
    void (*nvinv)(N_Vector, N_Vector);  
    void (*nvaddconst)(N_Vector, realtype, N_Vector);  
    realtype (*nvdotprod)(N_Vector, N_Vector);  
    realtype (*nvmaxnorm)(N_Vector);  
    realtype (*nvwrmsnorm)(N_Vector, N_Vector);
```

```

realtype    (*nvwrmsnormmask)(N_Vector, N_Vector, N_Vector);
realtype    (*nvmin)(N_Vector);
realtype    (*nvwl2norm)(N_Vector, N_Vector);
realtype    (*nv1lnorm)(N_Vector);
void        (*nvcompare)(realtype, N_Vector, N_Vector);
boolean_t   (*nvinvtest)(N_Vector, N_Vector);
boolean_t   (*nvconstrmask)(N_Vector, N_Vector, N_Vector);
realtype    (*nvminquotient)(N_Vector, N_Vector);
int         (*nvlinearcombination)(int, realtype*, N_Vector*, N_Vector);
int         (*nvscaleaddmulti)(int, realtype*, N_Vector, N_Vector*, N_Vector*);
int         (*nvdotprodmulti)(int, N_Vector, N_Vector*, realtype*);
int         (*nvlinearsumvectorarray)(int, realtype, N_Vector*, realtype,
                                     N_Vector*, N_Vector*);
int         (*nvscalevectorarray)(int, realtype*, N_Vector*, N_Vector*);
int         (*nvconstvectorarray)(int, realtype, N_Vector*);
int         (*nvwrmsnomrvectorarray)(int, N_Vector*, N_Vector*, realtype*);
int         (*nvwrmsnomrmaskvectorarray)(int, N_Vector*, N_Vector*, N_Vector,
                                     realtype*);
int         (*nvscaleaddmultivectorarray)(int, int, realtype*, N_Vector*,
                                     N_Vector**, N_Vector**);
int         (*nvlinearcombinationvectorarray)(int, int, realtype*, N_Vector**,
                                     N_Vector*);
};

```

The generic NVECTOR module defines and implements the vector operations acting on an `N_Vector`. These routines are nothing but wrappers for the vector operations defined by a particular NVECTOR implementation, which are accessed through the `ops` field of the `N_Vector` structure. To illustrate this point we show below the implementation of a typical vector operation from the generic NVECTOR module, namely `N_VScale`, which performs the scaling of a vector `x` by a scalar `c`:

```

void N_VScale(realtype c, N_Vector x, N_Vector z)
{
    z->ops->nvscale(c, x, z);
}

```

Table 6.2 contains a complete list of all standard vector operations defined by the generic NVECTOR module. Tables 6.3 and 6.4 list *optional* fused and vector array operations respectively.

Fused and vector array operations are intended to increase data reuse, reduce parallel communication on distributed memory systems, and lower the number of kernel launches on systems with accelerators. If a particular NVECTOR implementation defines a fused or vector array operation as `NULL`, the generic NVECTOR module will automatically call standard vector operations as necessary to complete the desired operation. Currently, all fused and vector array operations are disabled by default however, SUNDIALS provided NVECTOR implementations define additional user-callable functions to enable/disable any or all of the fused and vector array operations. See the following sections for the implementation specific functions to enable/disable operations.

Finally, note that the generic NVECTOR module defines the functions `N_VCloneVectorArray` and `N_VCloneVectorArrayEmpty`. Both functions create (by cloning) an array of `count` variables of type `N_Vector`, each of the same type as an existing `N_Vector`. Their prototypes are

```

N_Vector *N_VCloneVectorArray(int count, N_Vector w);
N_Vector *N_VCloneVectorArrayEmpty(int count, N_Vector w);

```

and their definitions are based on the implementation-specific `N_VClone` and `N_VCloneEmpty` operations, respectively.

An array of variables of type `N_Vector` can be destroyed by calling `N_VDestroyVectorArray`, whose prototype is

Table 6.1: Vector Identifications associated with vector kernels supplied with SUNDIALS.

| Vector ID | Vector type | ID Value |
|-------------------------|--|----------|
| SUNDIALS_NVEC_SERIAL | Serial | 0 |
| SUNDIALS_NVEC_PARALLEL | Distributed memory parallel (MPI) | 1 |
| SUNDIALS_NVEC_OPENMP | OpenMP shared memory parallel | 2 |
| SUNDIALS_NVEC_PTHREADS | PThreads shared memory parallel | 3 |
| SUNDIALS_NVEC_PARHYP | <i>hypr</i> ParHyp parallel vector | 4 |
| SUNDIALS_NVEC_PETSC | PETSc parallel vector | 5 |
| SUNDIALS_NVEC_OPENMPDEV | OpenMP shared memory parallel with device offloading | 6 |
| SUNDIALS_NVEC_CUSTOM | User-provided custom vector | 7 |

```
void N_VDestroyVectorArray(N_Vector *vs, int count);
```

and whose definition is based on the implementation-specific `N_VDestroy` operation.

A particular implementation of the NVECTOR module must:

- Specify the *content* field of `N_Vector`.
- Define and implement the vector operations. Note that the names of these routines should be unique to that implementation in order to permit using more than one NVECTOR module (each with different `N_Vector` internal data representations) in the same code.
- Define and implement user-callable constructor and destructor routines to create and free an `N_Vector` with the new *content* field and with *ops* pointing to the new vector operations.
- Optionally, define and implement additional user-callable routines acting on the newly defined `N_Vector` (e.g., a routine to print the content for debugging purposes).
- Optionally, provide accessor macros as needed for that particular implementation to be used to access different parts in the *content* field of the newly defined `N_Vector`.

Each NVECTOR implementation included in SUNDIALS has a unique identifier specified in enumeration and shown in Table 6.1. It is recommended that a user-supplied NVECTOR implementation use the `SUNDIALS_NVEC_CUSTOM` identifier.

Table 6.2: Description of the NVECTOR operations

| Name | Usage and Description |
|---------------------------------|--|
| <code>N_VGetVectorID</code> | <pre>id = N_VGetVectorID(w);</pre> <p>Returns the vector type identifier for the vector <code>w</code>. It is used to determine the vector implementation type (e.g. serial, parallel, ...) from the abstract <code>N_Vector</code> interface. Returned values are given in Table 6.1.</p> |
| <code>N_VClone</code> | <pre>v = N_VClone(w);</pre> <p>Creates a new <code>N_Vector</code> of the same type as an existing vector <code>w</code> and sets the <code>ops</code> field. It does not copy the vector, but rather allocates storage for the new vector.</p> |
| <code>N_VCloneEmpty</code> | <pre>v = N_VCloneEmpty(w);</pre> <p>Creates a new <code>N_Vector</code> of the same type as an existing vector <code>w</code> and sets the <code>ops</code> field. It does not allocate storage for data.</p> |
| <code>N_VDestroy</code> | <pre>N_VDestroy(v);</pre> <p>Destroys the <code>N_Vector</code> <code>v</code> and frees memory allocated for its internal data.</p> |
| <code>N_VSpace</code> | <pre>N_VSpace(nvSpec, &lrw, &liw);</pre> <p>Returns storage requirements for one <code>N_Vector</code>. <code>lrw</code> contains the number of realtype words and <code>liw</code> contains the number of integer words. This function is advisory only, for use in determining a user's total space requirements; it could be a dummy function in a user-supplied NVECTOR module if that information is not of interest.</p> |
| <code>N_VGetArrayPointer</code> | <pre>vdata = N_VGetArrayPointer(v);</pre> <p>Returns a pointer to a <code>realtype</code> array from the <code>N_Vector</code> <code>v</code>. Note that this assumes that the internal data in <code>N_Vector</code> is a contiguous array of <code>realtype</code>. This routine is only used in the solver-specific interfaces to the dense and banded (serial) linear solvers, the sparse linear solvers (serial and threaded), and in the interfaces to the banded (serial) and band-block-diagonal (parallel) preconditioner modules provided with SUNDIALS.</p> |
| <code>N_VSetArrayPointer</code> | <pre>N_VSetArrayPointer(vdata, v);</pre> <p>Overwrites the data in an <code>N_Vector</code> with a given array of <code>realtype</code>. Note that this assumes that the internal data in <code>N_Vector</code> is a contiguous array of <code>realtype</code>. This routine is only used in the interfaces to the dense (serial) linear solver, hence need not exist in a user-supplied NVECTOR module for a parallel environment.</p> |
| <i>continued on next page</i> | |

| <i>continued from last page</i> | |
|---------------------------------|---|
| Name | Usage and Description |
| N_VLinearSum | <code>N_VLinearSum(a, x, b, y, z);</code> Performs the operation $z = ax + by$, where a and b are realtype scalars and x and y are of type N_Vector : $z_i = ax_i + by_i$, $i = 0, \dots, n-1$. |
| N_VConst | <code>N_VConst(c, z);</code> Sets all components of the N_Vector z to realtype c : $z_i = c$, $i = 0, \dots, n-1$. |
| N_VProd | <code>N_VProd(x, y, z);</code> Sets the N_Vector z to be the component-wise product of the N_Vector inputs x and y : $z_i = x_i y_i$, $i = 0, \dots, n-1$. |
| N_VDiv | <code>N_VDiv(x, y, z);</code> Sets the N_Vector z to be the component-wise ratio of the N_Vector inputs x and y : $z_i = x_i / y_i$, $i = 0, \dots, n-1$. The y_i may not be tested for 0 values. It should only be called with a y that is guaranteed to have all nonzero components. |
| N_VScale | <code>N_VScale(c, x, z);</code> Scales the N_Vector x by the realtype scalar c and returns the result in z : $z_i = cx_i$, $i = 0, \dots, n-1$. |
| N_VAbs | <code>N_VAbs(x, z);</code> Sets the components of the N_Vector z to be the absolute values of the components of the N_Vector x : $y_i = x_i $, $i = 0, \dots, n-1$. |
| N_VInv | <code>N_VInv(x, z);</code> Sets the components of the N_Vector z to be the inverses of the components of the N_Vector x : $z_i = 1.0/x_i$, $i = 0, \dots, n-1$. This routine may not check for division by 0. It should be called only with an x which is guaranteed to have all nonzero components. |
| N_VAddConst | <code>N_VAddConst(x, b, z);</code> Adds the realtype scalar b to all components of x and returns the result in the N_Vector z : $z_i = x_i + b$, $i = 0, \dots, n-1$. |
| N_VDotProd | <code>d = N_VDotProd(x, y);</code> Returns the value of the ordinary dot product of x and y : $d = \sum_{i=0}^{n-1} x_i y_i$. |
| N_VMaxNorm | <code>m = N_VMaxNorm(x);</code> Returns the maximum norm of the N_Vector x : $m = \max_i x_i $. |
| <i>continued on next page</i> | |

| <i>continued from last page</i> | |
|---------------------------------|--|
| Name | Usage and Description |
| N_VWrmsNorm | $\mathbf{m} = \text{N_VWrmsNorm}(\mathbf{x}, \mathbf{w})$ Returns the weighted root-mean-square norm of the N_Vector \mathbf{x} with realtype weight vector \mathbf{w} : $m = \sqrt{\left(\sum_{i=0}^{n-1} (x_i w_i)^2\right) / n}$. |
| N_VWrmsNormMask | $\mathbf{m} = \text{N_VWrmsNormMask}(\mathbf{x}, \mathbf{w}, \text{id});$ Returns the weighted root mean square norm of the N_Vector \mathbf{x} with realtype weight vector \mathbf{w} built using only the elements of \mathbf{x} corresponding to positive elements of the N_Vector id : $m = \sqrt{\left(\sum_{i=0}^{n-1} (x_i w_i H(\text{id}_i))^2\right) / n}, \text{ where } H(\alpha) = \begin{cases} 1 & \alpha > 0 \\ 0 & \alpha \leq 0 \end{cases}$ |
| N_VMin | $\mathbf{m} = \text{N_VMin}(\mathbf{x});$ Returns the smallest element of the N_Vector \mathbf{x} : $m = \min_i x_i$. |
| N_VWL2Norm | $\mathbf{m} = \text{N_VWL2Norm}(\mathbf{x}, \mathbf{w});$ Returns the weighted Euclidean ℓ_2 norm of the N_Vector \mathbf{x} with realtype weight vector \mathbf{w} : $m = \sqrt{\sum_{i=0}^{n-1} (x_i w_i)^2}$. |
| N_VL1Norm | $\mathbf{m} = \text{N_VL1Norm}(\mathbf{x});$ Returns the ℓ_1 norm of the N_Vector \mathbf{x} : $m = \sum_{i=0}^{n-1} x_i $. |
| N_VCompare | $\text{N_VCompare}(\mathbf{c}, \mathbf{x}, \mathbf{z});$ Compares the components of the N_Vector \mathbf{x} to the realtype scalar \mathbf{c} and returns an N_Vector \mathbf{z} such that: $z_i = 1.0$ if $ x_i \geq c$ and $z_i = 0.0$ otherwise. |
| N_VInvTest | $\mathbf{t} = \text{N_VInvTest}(\mathbf{x}, \mathbf{z});$ Sets the components of the N_Vector \mathbf{z} to be the inverses of the components of the N_Vector \mathbf{x} , with prior testing for zero values: $z_i = 1.0/x_i, i = 0, \dots, n-1$. This routine returns a boolean assigned to SUNTRUE if all components of \mathbf{x} are nonzero (successful inversion) and returns SUNFALSE otherwise. |
| N_VConstrMask | $\mathbf{t} = \text{N_VConstrMask}(\mathbf{c}, \mathbf{x}, \mathbf{m});$ Performs the following constraint tests: $x_i > 0$ if $c_i = 2$, $x_i \geq 0$ if $c_i = 1$, $x_i \leq 0$ if $c_i = -1$, $x_i < 0$ if $c_i = -2$. There is no constraint on x_i if $c_i = 0$. This routine returns a boolean assigned to SUNFALSE if any element failed the constraint test and assigned to SUNTRUE if all passed. It also sets a mask vector \mathbf{m} , with elements equal to 1.0 where the constraint test failed, and 0.0 where the test passed. This routine is used only for constraint checking. |
| <i>continued on next page</i> | |

| <i>continued from last page</i> | |
|---------------------------------|--|
| Name | Usage and Description |
| N_VMinQuotient | <pre>minq = N_VMinQuotient(num, denom);</pre> <p>This routine returns the minimum of the quotients obtained by term-wise dividing num_i by denom_i. A zero element in denom will be skipped. If no such quotients are found, then the large value BIG_REAL (defined in the header file sundials_types.h) is returned.</p> |

Table 6.3: Description of the NVECTOR fused operations

| Name | Usage and Description |
|-------------------------------|---|
| N_VLinearCombination | <pre>ier = N_VLinearCombination(nv, c, X, z);</pre> <p>This routine computes the linear combination of n_v vectors with n elements:</p> $z_i = \sum_{j=0}^{n_v-1} c_j x_{j,i}, \quad i = 0, \dots, n-1,$ <p>where c is an array of n_v scalars (type realtype*), X is an array of n_v vectors (type N_Vector*), and z is the output vector (type N_Vector). If the output vector z is one of the vectors in X, then it <i>must</i> be the first vector in the vector array. The operation returns 0 for success and a non-zero value otherwise.</p> |
| N_VScaleAddMulti | <pre>ier = N_VScaleAddMulti(nv, c, x, Y, Z);</pre> <p>This routine scales and adds one vector to n_v vectors with n elements:</p> $z_{j,i} = c_j x_i + y_{j,i}, \quad j = 0, \dots, n_v-1 \quad i = 0, \dots, n-1,$ <p>where c is an array of n_v scalars (type realtype*), x is the vector (type N_Vector) to be scaled and added to each vector in the vector array of n_v vectors Y (type N_Vector*), and Z (type N_Vector*) is a vector array of n_v output vectors. The operation returns 0 for success and a non-zero value otherwise.</p> |
| <i>continued on next page</i> | |

| <i>continued from last page</i> | |
|---------------------------------|--|
| Name | Usage and Description |
| N_VDotProdMulti | <p>ier = N_VDotProdMulti(nv, x, Y, d);</p> <p>This routine computes the dot product of a vector with n_v other vectors:</p> $d_j = \sum_{i=0}^{n-1} x_i y_{j,i}, \quad j = 0, \dots, n_v - 1,$ <p>where d (type realtype*) is an array of n_v scalars containing the dot products of the vector x (type N_Vector) with each of the n_v vectors in the vector array Y (type N_Vector*). The operation returns 0 for success and a non-zero value otherwise.</p> |

Table 6.4: Description of the NVECTOR vector array operations

| Name | Usage and Description |
|-------------------------------|--|
| N_VLinearSumVectorArray | <p>ier = N_VLinearSumVectorArray(nv, a, X, b, Y, Z);</p> <p>This routine computes the linear sum of two vector arrays containing n_v vectors of n elements:</p> $z_{j,i} = ax_{j,i} + by_{j,i}, \quad i = 0, \dots, n-1 \quad j = 0, \dots, n_v - 1,$ <p>where a and b are realtype scalars and X, Y, and Z are arrays of n_v vectors (type N_Vector*). The operation returns 0 for success and a non-zero value otherwise.</p> |
| N_VScaleVectorArray | <p>ier = N_VScaleVectorArray(nv, c, X, Z);</p> <p>This routine scales each vector of n elements in a vector array of n_v vectors by a potentially different constant:</p> $z_{j,i} = c_j x_{j,i}, \quad i = 0, \dots, n-1 \quad j = 0, \dots, n_v - 1,$ <p>where c is an array of n_v scalars (type realtype*) and X and Z are arrays of n_v vectors (type N_Vector*). The operation returns 0 for success and a non-zero value otherwise.</p> |
| <i>continued on next page</i> | |

| continued from last page | |
|----------------------------|--|
| Name | Usage and Description |
| N_VConstVectorArray | <p>ier = N_VConstVectorArray(nv, c, X);</p> <p>This routine sets each element in a vector of n elements in a vector array of n_v vectors to the same value:</p> $z_{j,i} = c, \quad i = 0, \dots, n-1 \quad j = 0, \dots, n_v-1,$ <p>where c is a realtype scalar and X is an array of n_v vectors (type N_Vector*). The operation returns 0 for success and a non-zero value otherwise.</p> |
| N_VWrmsNormVectorArray | <p>ier = N_VWrmsNormVectorArray(nv, X, W, m);</p> <p>This routine computes the weighted root mean square norm of n_v vectors with n elements:</p> $m_j = \left(\frac{1}{n} \sum_{i=0}^{n-1} (x_{j,i} w_{j,i})^2 \right)^{1/2}, \quad j = 0, \dots, n_v-1,$ <p>where m (type realtype*) contains the n_v norms of the vectors in the vector array X (type N_Vector*) with corresponding weight vectors W (type N_Vector*). The operation returns 0 for success and a non-zero value otherwise.</p> |
| N_VWrmsNormMaskVectorArray | <p>ier = N_VWrmsNormMaskVectorArray(nv, X, W, id, m);</p> <p>This routine computes the masked weighted root mean square norm of n_v vectors with n elements:</p> $m_j = \left(\frac{1}{n} \sum_{i=0}^{n-1} (x_{j,i} w_{j,i} H(id_i))^2 \right)^{1/2}, \quad j = 0, \dots, n_v-1,$ <p>$H(id_i) = 1$ for $id_i > 0$ and is zero otherwise, m (type realtype*) contains the n_v norms of the vectors in the vector array X (type N_Vector*) with corresponding weight vectors W (type N_Vector*) and mask vector id (type N_Vector). The operation returns 0 for success and a non-zero value otherwise.</p> |
| continued on next page | |

| <i>continued from last page</i> | |
|---------------------------------|--|
| Name | Usage and Description |
| N_VScaleAddMultiVectorArray | <p><code>ier = N_VScaleAddMultiVectorArray(nv, ns, c, X, YY, ZZ);</code></p> <p>This routine scales and adds a vector in a vector array of n_v vectors to the corresponding vector in n_s vector arrays:</p> $z_{j,i} = \sum_{k=0}^{n_s-1} c_k x_{k,j,i}, \quad i = 0, \dots, n-1 \quad j = 0, \dots, n_v-1,$ <p>where c is an array of n_s scalars (type <code>realtype*</code>), X is a vector array of n_v vectors (type <code>idN_Vector*</code>) to be scaled and added to the corresponding vector in each of the n_s vector arrays in the array of vector arrays YY (type <code>N_Vector**</code>) and stored in the output array of vector arrays ZZ (type <code>N_Vector**</code>). The operation returns 0 for success and a non-zero value otherwise.</p> |
| N_VLinearCombinationVectorArray | <p><code>ier = N_VLinearCombinationVectorArray(nv, ns, c, XX, Z);</code></p> <p>This routine computes the linear combination of n_s vector arrays containing n_v vectors with n elements:</p> $z_{j,i} = \sum_{k=0}^{n_s-1} c_k x_{k,j,i}, \quad i = 0, \dots, n-1 \quad j = 0, \dots, n_v-1,$ <p>where c is an array of n_s scalars (type <code>realtype*</code>), XX (type <code>N_Vector**</code>) is an array of n_s vector arrays each containing n_v vectors to be summed into the output vector array of n_v vectors Z (type <code>N_Vector*</code>). If the output vector array Z is one of the vector arrays in XX, then it <i>must</i> be the first vector array in XX. The operation returns 0 for success and a non-zero value otherwise.</p> |

6.1 NVECTOR functions used by IDA

In Table 6.5 below, we list the vector functions used in the NVECTOR module used by the IDA package. The table also shows, for each function, which of the code modules uses the function. The IDA column shows function usage within the main integrator module, while the remaining columns show function usage within the IDALS linear solvers interface, the IDABBDPRE preconditioner module, and the FIDA module.

At this point, we should emphasize that the IDA user does not need to know anything about the usage of vector functions by the IDA code modules in order to use IDA. The information is presented as an implementation detail for the interested reader.

Special cases (numbers match markings in table):

1. These routines are only required if an internal difference-quotient routine for constructing dense or band Jacobian matrices is used.
2. This routine is optional, and is only used in estimating space requirements for IDA modules for user feedback.
3. The optional function `N_VDotProdMulti` is only used when Classical Gram-Schmidt is enabled with SPGMR or SPFGMR. The remaining operations from Tables 6.3 and 6.4 not listed above are

Table 6.5: List of vector functions usage by IDA code modules

| | IDA | IDALS | IDABDDPRE | FIDA |
|-------------------------|-----|-------|-----------|------|
| N_VGetVectorID | | | | |
| N_VClone | ✓ | ✓ | ✓ | ✓ |
| N_VCloneEmpty | | 1 | | ✓ |
| N_VDestroy | ✓ | ✓ | ✓ | ✓ |
| N_VSpace | ✓ | 2 | | |
| N_VGetArrayPointer | | 1 | ✓ | ✓ |
| N_VSetArrayPointer | | 1 | | ✓ |
| N_VLinearSum | ✓ | ✓ | | |
| N_VConst | ✓ | ✓ | | |
| N_VProd | ✓ | | | |
| N_VDiv | ✓ | | | |
| N_VScale | ✓ | ✓ | ✓ | |
| N_VAbs | ✓ | | | |
| N_VInv | ✓ | | | |
| N_VAddConst | ✓ | | | |
| N_VDotProd | | ✓ | | |
| N_VMaxNorm | ✓ | | | |
| N_VWrmsNorm | ✓ | | | |
| N_VMin | ✓ | | | |
| N_VMinQuotient | ✓ | | | |
| N_VConstrMask | ✓ | | | |
| N_VWrmsNormMask | ✓ | | | |
| N_VCompare | ✓ | | | |
| N_VLinearCombination | ✓ | | | |
| N_VScaleAddMulti | ✓ | | | |
| N_VDotProdMulti | | 3 | | |
| N_VLinearSumVectorArray | ✓ | | | |
| N_VScaleVectorArray | ✓ | | | |

unused and a user-supplied NVECTOR module for IDA could omit these operations.

Of the functions listed in Table 6.2, `N_VWL2Norm`, `N_VL1Norm`, and `N_VInvTest` are *not* used by IDA. Therefore a user-supplied NVECTOR module for IDA could omit these functions.

6.2 The NVECTOR_SERIAL implementation

The serial implementation of the NVECTOR module provided with SUNDIALS, `NVECTOR_SERIAL`, defines the *content* field of `N_Vector` to be a structure containing the length of the vector, a pointer to the beginning of a contiguous data array, and a boolean flag *own_data* which specifies the ownership of *data*.

```

struct _N_VectorContent_Serial {
    sunindextype length;
    booleantype own_data;
    realtype *data;
};

```

The header file to include when using this module is `nvector_serial.h`. The installed module library to link to is `libsundials_nvecserial.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries.

6.2.1 NVECTOR_SERIAL accessor macros

The following macros are provided to access the content of an NVECTOR_SERIAL vector. The suffix `_S` in the names denotes the serial version.

- **NV_CONTENT_S**

This routine gives access to the contents of the serial vector `N_Vector`.

The assignment `v_cont = NV_CONTENT_S(v)` sets `v_cont` to be a pointer to the serial `N_Vector` content structure.

Implementation:

```
#define NV_CONTENT_S(v) ( (N_VectorContent_Serial)(v->content) )
```

- **NV_OWN_DATA_S, NV_DATA_S, NV_LENGTH_S**

These macros give individual access to the parts of the content of a serial `N_Vector`.

The assignment `v_data = NV_DATA_S(v)` sets `v_data` to be a pointer to the first component of the data for the `N_Vector` `v`. The assignment `NV_DATA_S(v) = v_data` sets the component array of `v` to be `v_data` by storing the pointer `v_data`.

The assignment `v_len = NV_LENGTH_S(v)` sets `v_len` to be the length of `v`. On the other hand, the call `NV_LENGTH_S(v) = len_v` sets the length of `v` to be `len_v`.

Implementation:

```
#define NV_OWN_DATA_S(v) ( NV_CONTENT_S(v)->own_data )
```

```
#define NV_DATA_S(v) ( NV_CONTENT_S(v)->data )
```

```
#define NV_LENGTH_S(v) ( NV_CONTENT_S(v)->length )
```

- **NV_Ith_S**

This macro gives access to the individual components of the data array of an `N_Vector`.

The assignment `r = NV_Ith_S(v,i)` sets `r` to be the value of the `i`-th component of `v`. The assignment `NV_Ith_S(v,i) = r` sets the value of the `i`-th component of `v` to be `r`.

Here `i` ranges from 0 to $n - 1$ for a vector of length n .

Implementation:

```
#define NV_Ith_S(v,i) ( NV_DATA_S(v)[i] )
```

6.2.2 NVECTOR_SERIAL functions

The NVECTOR_SERIAL module defines serial implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4. Their names are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_Serial` (e.g. `N_VDestroy_Serial`). All the standard vector operations listed in 6.2 with the suffix `_Serial` appended are callable via the FORTRAN 2003 interface by prepending an ‘F’ (e.g. `FN_VDestroy_Serial`).

The module NVECTOR_SERIAL provides the following additional user-callable routines:

| |
|----------------------|
| N_VNew_Serial |
|----------------------|

Prototype `N_Vector N_VNew_Serial(sunindextype vec_length);`

Description This function creates and allocates memory for a serial `N_Vector`. Its only argument is the vector length.

F2003 Name This function is callable as `FN_VNew_Serial` when using the Fortran 2003 interface module.

N_VNewEmpty_Serial

Prototype `N_Vector N_VNewEmpty_Serial(sunindextype vec_length);`

Description This function creates a new serial `N_Vector` with an empty (`NULL`) data array.

F2003 Name This function is callable as `FN_VNewEmpty_Serial` when using the Fortran 2003 interface module.

N_VMake_Serial

Prototype `N_Vector N_VMake_Serial(sunindextype vec_length, realtype *v_data);`

Description This function creates and allocates memory for a serial vector with user-provided data array.

(This function does *not* allocate memory for `v_data` itself.)

F2003 Name This function is callable as `FN_VMake_Serial` when using the Fortran 2003 interface module.

N_VCloneVectorArray_Serial

Prototype `N_Vector *N_VCloneVectorArray_Serial(int count, N_Vector w);`

Description This function creates (by cloning) an array of `count` serial vectors.

N_VCloneVectorArrayEmpty_Serial

Prototype `N_Vector *N_VCloneVectorArrayEmpty_Serial(int count, N_Vector w);`

Description This function creates (by cloning) an array of `count` serial vectors, each with an empty (`NULL`) data array.

N_VDestroyVectorArray_Serial

Prototype `void N_VDestroyVectorArray_Serial(N_Vector *vs, int count);`

Description This function frees memory allocated for the array of `count` variables of type `N_Vector` created with `N_VCloneVectorArray_Serial` or with `N_VCloneVectorArrayEmpty_Serial`.

N_VGetLength_Serial

Prototype `sunindextype N_VGetLength_Serial(N_Vector v);`

Description This function returns the number of vector elements.

F2003 Name This function is callable as `FN_VGetLength_Serial` when using the Fortran 2003 interface module.

N_VPrint_Serial

Prototype `void N_VPrint_Serial(N_Vector v);`

Description This function prints the content of a serial vector to `stdout`.

F2003 Name This function is callable as `FN_VPrint_Serial` when using the Fortran 2003 interface module.

N_VPrintFile_Serial

Prototype `void N_VPrintFile_Serial(N_Vector v, FILE *outfile);`

Description This function prints the content of a serial vector to `outfile`.

By default all fused and vector array operations are disabled in the NVECTOR_SERIAL module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_Serial`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_Serial` will have the default settings for the NVECTOR_SERIAL module.

N_VEnableFusedOps_Serial

Prototype `int N_VEnableFusedOps_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) all fused and vector array operations in the serial vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearCombination_Serial

Prototype `int N_VEnableLinearCombination_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination fused operation in the serial vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleAddMulti_Serial

Prototype `int N_VEnableScaleAddMulti_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the serial vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableDotProdMulti_Serial

Prototype `int N_VEnableDotProdMulti_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the serial vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearSumVectorArray_Serial

Prototype `int N_VEnableLinearSumVectorArray_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the serial vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleVectorArray_Serial

Prototype `int N_VEnableScaleVectorArray_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the serial vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableConstVectorArray_Serial

Prototype `int N_VEnableConstVectorArray_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the serial vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_Serial

Prototype `int N_VEnableWrmsNormVectorArray_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the serial vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_Serial

Prototype `int N_VEnableWrmsNormMaskVectorArray_Serial(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the serial vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleAddMultiVectorArray_Serial

Prototype `int N_VEnableScaleAddMultiVectorArray_Serial(N_Vector v,
boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector array to multiple vector arrays operation in the serial vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearCombinationVectorArray_Serial

Prototype `int N_VEnableLinearCombinationVectorArray_Serial(N_Vector v,
boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the serial vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

Notes

- When looping over the components of an `N_Vector v`, it is more efficient to first obtain the component array via `v_data = NV_DATA_S(v)` and then access `v_data[i]` within the loop than it is to use `NV_Ith_S(v,i)` within the loop.
- `N_VNewEmpty_Serial`, `N_VMake_Serial`, and `N_VCloneVectorArrayEmpty_Serial` set the field `own_data = SUNFALSE`. `N_VDestroy_Serial` and `N_VDestroyVectorArray_Serial` will not attempt to free the pointer `data` for any `N_Vector` with `own_data` set to `SUNFALSE`. In such a case, it is the user's responsibility to deallocate the `data` pointer.
- To maximize efficiency, vector operations in the NVECTOR_SERIAL implementation that have more than one `N_Vector` argument do not check for consistent internal representation of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.



6.2.3 NVECTOR_SERIAL Fortran interfaces

The NVECTOR_SERIAL module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTTRAN 2003 interface module

The `fnvector_serial_mod` FORTRAN module defines interfaces to all NVECTOR_SERIAL C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading 'F'. For example, the function `N_VNew_Serial` is interfaced as `FN_VNew_Serial`.

The FORTRAN 2003 NVECTOR_SERIAL interface module can be accessed with the `use` statement, i.e. `use fnvector_serial_mod`, and linking to the library `libsundials_fnvectorserial_mod.lib` in addition to the C library. For details on where the library and module file `fnvector_serial_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fnvectorserial_mod` library.

FORTTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the NVECTOR_SERIAL module also includes a FORTRAN-callable function `FNVINITS(code, NEQ, IER)`, to initialize this NVECTOR_SERIAL module. Here `code` is an input solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, 4 for ARKODE); `NEQ` is the problem size (declared so as to match C type `long int`); and `IER` is an error return flag equal 0 for success and -1 for failure.

6.3 The NVECTOR_PARALLEL implementation

The NVECTOR_PARALLEL implementation of the NVECTOR module provided with SUNDIALS is based on MPI. It defines the `content` field of `N_Vector` to be a structure containing the global and local lengths of the vector, a pointer to the beginning of a contiguous local data array, an MPI communicator, and a boolean flag `own_data` indicating ownership of the data array `data`.

```
struct _N_VectorContent_Parallel {
    sunindextype local_length;
    sunindextype global_length;
    booleantype own_data;
    realtype *data;
    MPI_Comm comm;
};
```

The header file to include when using this module is `nvector_parallel.h`. The installed module library to link to is `libsundials_nvecparallel.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries.

6.3.1 NVECTOR_PARALLEL accessor macros

The following macros are provided to access the content of a NVECTOR_PARALLEL vector. The suffix `_P` in the names denotes the distributed memory parallel version.

- `NV_CONTENT_P`

This macro gives access to the contents of the parallel vector `N_Vector`.

The assignment `v_cont = NV_CONTENT_P(v)` sets `v_cont` to be a pointer to the `N_Vector` content structure of type `struct _N_VectorContent_Parallel`.

Implementation:

```
#define NV_CONTENT_P(v) ( (N_VectorContent_Parallel)(v->content) )
```

- NV_OWN_DATA_P, NV_DATA_P, NV_LOCLENGTH_P, NV_GLOBLENGTH_P

These macros give individual access to the parts of the content of a parallel `N_Vector`.

The assignment `v_data = NV_DATA_P(v)` sets `v_data` to be a pointer to the first component of the local data for the `N_Vector` `v`. The assignment `NV_DATA_P(v) = v_data` sets the component array of `v` to be `v_data` by storing the pointer `v_data`.

The assignment `v_llen = NV_LOCLENGTH_P(v)` sets `v_llen` to be the length of the local part of `v`. The call `NV_LENGTH_P(v) = llen_v` sets the local length of `v` to be `llen_v`.

The assignment `v_glen = NV_GLOBLENGTH_P(v)` sets `v_glen` to be the global length of the vector `v`. The call `NV_GLOBLENGTH_P(v) = glen_v` sets the global length of `v` to be `glen_v`.

Implementation:

```
#define NV_OWN_DATA_P(v)    ( NV_CONTENT_P(v)->own_data )
#define NV_DATA_P(v)        ( NV_CONTENT_P(v)->data )
#define NV_LOCLENGTH_P(v)   ( NV_CONTENT_P(v)->local_length )
#define NV_GLOBLENGTH_P(v) ( NV_CONTENT_P(v)->global_length )
```

- NV_COMM_P

This macro provides access to the MPI communicator used by the `NVECTOR_PARALLEL` vectors.

Implementation:

```
#define NV_COMM_P(v) ( NV_CONTENT_P(v)->comm )
```

- NV_Ith_P

This macro gives access to the individual components of the local data array of an `N_Vector`.

The assignment `r = NV_Ith_P(v,i)` sets `r` to be the value of the `i`-th component of the local part of `v`. The assignment `NV_Ith_P(v,i) = r` sets the value of the `i`-th component of the local part of `v` to be `r`.

Here `i` ranges from 0 to $n - 1$, where n is the local length.

Implementation:

```
#define NV_Ith_P(v,i) ( NV_DATA_P(v)[i] )
```

6.3.2 NVECTOR_PARALLEL functions

The `NVECTOR_PARALLEL` module defines parallel implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4. Their names are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_Parallel` (e.g. `N_VDestroy_Parallel`). The module `NVECTOR_PARALLEL` provides the following additional user-callable routines:

`N_VNew_Parallel`

Prototype `N_Vector N_VNew_Parallel(MPI_Comm comm, sunindextype local_length, sunindextype global_length);`

Description This function creates and allocates memory for a parallel vector.

`N_VNewEmpty_Parallel`

Prototype `N_Vector N_VNewEmpty_Parallel(MPI_Comm comm, sunindextype local_length, sunindextype global_length);`

Description This function creates a new parallel `N_Vector` with an empty (NULL) data array.

N_VMake_Parallel

Prototype `N_Vector N_VMake_Parallel(MPI_Comm comm, sunindextype local_length,
sunindextype global_length, realtype *v_data);`

Description This function creates and allocates memory for a parallel vector with user-provided data array. This function does *not* allocate memory for `v_data` itself.

N_VCloneVectorArray_Parallel

Prototype `N_Vector *N_VCloneVectorArray_Parallel(int count, N_Vector w);`

Description This function creates (by cloning) an array of `count` parallel vectors.

N_VCloneVectorArrayEmpty_Parallel

Prototype `N_Vector *N_VCloneVectorArrayEmpty_Parallel(int count, N_Vector w);`

Description This function creates (by cloning) an array of `count` parallel vectors, each with an empty (NULL) data array.

N_VDestroyVectorArray_Parallel

Prototype `void N_VDestroyVectorArray_Parallel(N_Vector *vs, int count);`

Description This function frees memory allocated for the array of `count` variables of type `N_Vector` created with `N_VCloneVectorArray_Parallel` or with `N_VCloneVectorArrayEmpty_Parallel`.

N_VGetLength_Parallel

Prototype `sunindextype N_VGetLength_Parallel(N_Vector v);`

Description This function returns the number of vector elements (global vector length).

N_VGetLocalLength_Parallel

Prototype `sunindextype N_VGetLocalLength_Parallel(N_Vector v);`

Description This function returns the local vector length.

N_VPrint_Parallel

Prototype `void N_VPrint_Parallel(N_Vector v);`

Description This function prints the local content of a parallel vector to `stdout`.

N_VPrintFile_Parallel

Prototype `void N_VPrintFile_Parallel(N_Vector v, FILE *outfile);`

Description This function prints the local content of a parallel vector to `outfile`.

By default all fused and vector array operations are disabled in the `NVECTOR_PARALLEL` module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_Parallel`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone` with that vector. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_Parallel` will have the default settings for the `NVECTOR_PARALLEL` module.

N_VEnableFusedOps_Parallel

Prototype `int N_VEnableFusedOps_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) all fused and vector array operations in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearCombination_Parallel

Prototype `int N_VEnableLinearCombination_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination fused operation in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleAddMulti_Parallel

Prototype `int N_VEnableScaleAddMulti_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableDotProdMulti_Parallel

Prototype `int N_VEnableDotProdMulti_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearSumVectorArray_Parallel

Prototype `int N_VEnableLinearSumVectorArray_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleVectorArray_Parallel

Prototype `int N_VEnableScaleVectorArray_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableConstVectorArray_Parallel

Prototype `int N_VEnableConstVectorArray_Parallel(N_Vector v, boolean_t tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the parallel vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_Parallel

Prototype `int N_VEnableWrmsNormVectorArray_Parallel(N_Vector v, booleantype tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the parallel vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableWrmsNormMaskVectorArray_Parallel

Prototype `int N_VEnableWrmsNormMaskVectorArray_Parallel(N_Vector v, booleantype tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the parallel vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleAddMultiVectorArray_Parallel

Prototype `int N_VEnableScaleAddMultiVectorArray_Parallel(N_Vector v,
booleantype tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector array to multiple vector arrays operation in the parallel vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearCombinationVectorArray_Parallel

Prototype `int N_VEnableLinearCombinationVectorArray_Parallel(N_Vector v,
booleantype tf);`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the parallel vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

Notes

- When looping over the components of an `N_Vector v`, it is more efficient to first obtain the local component array via `v_data = NV_DATA_P(v)` and then access `v_data[i]` within the loop than it is to use `NV_Ith_P(v,i)` within the loop.
- `N_VNewEmpty_Parallel`, `N_VMake_Parallel`, and `N_VCloneVectorArrayEmpty_Parallel` set the field `own_data = SUNFALSE`. `N_VDestroy_Parallel` and `N_VDestroyVectorArray_Parallel` will not attempt to free the pointer `data` for any `N_Vector` with `own_data` set to `SUNFALSE`. In such a case, it is the user's responsibility to deallocate the `data` pointer.
- To maximize efficiency, vector operations in the `NVECTOR_PARALLEL` implementation that have more than one `N_Vector` argument do not check for consistent internal representation of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.

6.3.3 NVECTOR_PARALLEL Fortran interfaces

For solvers that include a FORTRAN 77 interface module, the `NVECTOR_PARALLEL` module also includes a FORTRAN-callable function `FNVINITP(COMM, code, NLOCAL, NGLOBAL, IER)`, to initialize this `NVECTOR_PARALLEL` module. Here `COMM` is the MPI communicator, `code` is an input solver id (1 for `CVODE`, 2 for `IDA`, 3 for `KINSOL`, 4 for `ARKODE`); `NLOCAL` and `NGLOBAL` are the local and global vector sizes, respectively (declared so as to match C type `long int`); and `IER` is an error return flag equal 0 for success and -1 for failure. NOTE: If the header file `sundials_config.h` defines `SUNDIALS_MPI_COMM_F2C` to be 1 (meaning the MPI implementation used to build `SUNDIALS`

includes the `MPI_Comm_f2c` function), then `COMM` can be any valid MPI communicator. Otherwise, `MPI_COMM_WORLD` will be used, so just pass an integer value as a placeholder.

6.4 The NVECTOR_OPENMP implementation

In situations where a user has a multi-core processing unit capable of running multiple parallel threads with shared memory, SUNDIALS provides an implementation of NVECTOR using OpenMP, called `NVECTOR_OPENMP`, and an implementation using Pthreads, called `NVECTOR_PTHREADS`. Testing has shown that vectors should be of length at least 100,000 before the overhead associated with creating and using the threads is made up by the parallelism in the vector calculations.

The OpenMP NVECTOR implementation provided with SUNDIALS, `NVECTOR_OPENMP`, defines the `content` field of `N_Vector` to be a structure containing the length of the vector, a pointer to the beginning of a contiguous data array, a boolean flag `own_data` which specifies the ownership of `data`, and the number of threads. Operations on the vector are threaded using OpenMP.

```
struct _N_VectorContent_OpenMP {
    sunindextype length;
    booleantype own_data;
    realtype *data;
    int num_threads;
};
```

The header file to include when using this module is `nvector_openmp.h`. The installed module library to link to is `libsundials_nvecopenmp.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries. The FORTRAN module file to use when using the FORTRAN 2003 interface to this module is `fnvector_openmp_mod.mod`.

6.4.1 NVECTOR_OPENMP accessor macros

The following macros are provided to access the content of an `NVECTOR_OPENMP` vector. The suffix `_OMP` in the names denotes the OpenMP version.

- `NV_CONTENT_OMP`

This routine gives access to the contents of the OpenMP vector `N_Vector`.

The assignment `v_cont = NV_CONTENT_OMP(v)` sets `v_cont` to be a pointer to the OpenMP `N_Vector` content structure.

Implementation:

```
#define NV_CONTENT_OMP(v) ( (_N_VectorContent_OpenMP)(v->content) )
```

- `NV_OWN_DATA_OMP`, `NV_DATA_OMP`, `NV_LENGTH_OMP`, `NV_NUM_THREADS_OMP`

These macros give individual access to the parts of the content of a OpenMP `N_Vector`.

The assignment `v_data = NV_DATA_OMP(v)` sets `v_data` to be a pointer to the first component of the data for the `N_Vector` `v`. The assignment `NV_DATA_OMP(v) = v_data` sets the component array of `v` to be `v_data` by storing the pointer `v_data`.

The assignment `v_len = NV_LENGTH_OMP(v)` sets `v_len` to be the length of `v`. On the other hand, the call `NV_LENGTH_OMP(v) = len_v` sets the length of `v` to be `len_v`.

The assignment `v_num_threads = NV_NUM_THREADS_OMP(v)` sets `v_num_threads` to be the number of threads from `v`. On the other hand, the call `NV_NUM_THREADS_OMP(v) = num_threads_v` sets the number of threads for `v` to be `num_threads_v`.

Implementation:

```
#define NV_OWN_DATA_OMP(v) ( NV_CONTENT_OMP(v)->own_data )
```

```
#define NV_DATA_OMP(v) ( NV_CONTENT_OMP(v)->data )
```

```
#define NV_LENGTH_OMP(v) ( NV_CONTENT_OMP(v)->length )
#define NV_NUM_THREADS_OMP(v) ( NV_CONTENT_OMP(v)->num_threads )
```

- NV_Ith_OMP

This macro gives access to the individual components of the data array of an `N_Vector`.

The assignment `r = NV_Ith_OMP(v,i)` sets `r` to be the value of the `i`-th component of `v`. The assignment `NV_Ith_OMP(v,i) = r` sets the value of the `i`-th component of `v` to be `r`.

Here i ranges from 0 to $n - 1$ for a vector of length n .

Implementation:

```
#define NV_Ith_OMP(v,i) ( NV_DATA_OMP(v)[i] )
```

6.4.2 NVECTOR_OPENMP functions

The `NVECTOR_OPENMP` module defines OpenMP implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4. Their names are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_OpenMP` (e.g. `N_VDestroy_OpenMP`). All the standard vector operations listed in 6.2 with the suffix `_OpenMP` appended are callable via the Fortran 2003 interface by prepending an ‘F’ (e.g. `FN_VDestroy_OpenMP`).

The module `NVECTOR_OPENMP` provides the following additional user-callable routines:

N_VNew_OpenMP

Prototype `N_Vector N_VNew_OpenMP(sunindextype vec_length, int num_threads)`

Description This function creates and allocates memory for a OpenMP `N_Vector`. Arguments are the vector length and number of threads.

F2003 Name This function is callable as `FN_VNew_OpenMP` when using the Fortran 2003 interface module.

N_VNewEmpty_OpenMP

Prototype `N_Vector N_VNewEmpty_OpenMP(sunindextype vec_length, int num_threads)`

Description This function creates a new OpenMP `N_Vector` with an empty (NULL) data array.

F2003 Name This function is callable as `FN_VNewEmpty_OpenMP` when using the Fortran 2003 interface module.

N_VMake_OpenMP

Prototype `N_Vector N_VMake_OpenMP(sunindextype vec_length, realtype *v_data, int num_threads);`

Description This function creates and allocates memory for a OpenMP vector with user-provided data array. This function does *not* allocate memory for `v_data` itself.

F2003 Name This function is callable as `FN_VMake_OpenMP` when using the Fortran 2003 interface module.

N_VCloneVectorArray_OpenMP

Prototype `N_Vector *N_VCloneVectorArray_OpenMP(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` OpenMP vectors.

N_VCloneVectorArrayEmpty_OpenMP

Prototype `N_Vector *N_VCloneVectorArrayEmpty_OpenMP(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` OpenMP vectors, each with an empty (NULL) data array.

N_VDestroyVectorArray_OpenMP

Prototype `void N_VDestroyVectorArray_OpenMP(N_Vector *vs, int count)`

Description This function frees memory allocated for the array of `count` variables of type `N_Vector` created with `N_VCloneVectorArray_OpenMP` or with `N_VCloneVectorArrayEmpty_OpenMP`.

N_VGetLength_OpenMP

Prototype `sunindextype N_VGetLength_OpenMP(N_Vector v)`

Description This function returns number of vector elements.

F2003 Name This function is callable as `FN_VGetLength_OpenMP` when using the Fortran 2003 interface module.

N_VPrint_OpenMP

Prototype `void N_VPrint_OpenMP(N_Vector v)`

Description This function prints the content of an OpenMP vector to `stdout`.

F2003 Name This function is callable as `FN_VPrint_OpenMP` when using the Fortran 2003 interface module.

N_VPrintFile_OpenMP

Prototype `void N_VPrintFile_OpenMP(N_Vector v, FILE *outfile)`

Description This function prints the content of an OpenMP vector to `outfile`.

By default all fused and vector array operations are disabled in the `NVECTOR_OPENMP` module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_OpenMP`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_OpenMP` will have the default settings for the `NVECTOR_OPENMP` module.

N_VEnableFusedOps_OpenMP

Prototype `int N_VEnableFusedOps_OpenMP(N_Vector v, boolean_type tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) all fused and vector array operations in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearCombination_OpenMP

Prototype `int N_VEnableLinearCombination_OpenMP(N_Vector v, boolean_type tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) the linear combination fused operation in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleAddMulti_OpenMP

Prototype `int N_VEnableScaleAddMulti_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableDotProdMulti_OpenMP

Prototype `int N_VEnableDotProdMulti_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearSumVectorArray_OpenMP

Prototype `int N_VEnableLinearSumVectorArray_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleVectorArray_OpenMP

Prototype `int N_VEnableScaleVectorArray_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableConstVectorArray_OpenMP

Prototype `int N_VEnableConstVectorArray_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_OpenMP

Prototype `int N_VEnableWrmsNormVectorArray_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_OpenMP

Prototype `int N_VEnableWrmsNormMaskVectorArray_OpenMP(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

| | |
|-------------|--|
| Description | This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector array to multiple vector arrays operation in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL . |
|-------------|--|

[illegible]

| | |
|-------------|--|
| Description | This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the OpenMP vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL . |
|-------------|--|

Notes

- When looping over the components of an `N_Vector` `v`, it is more efficient to first obtain the component array via `v_data = NV_DATA_OMP(v)` and then access `v_data[i]` within the loop than it is to use `NV_Ith_OMP(v,i)` within the loop.
- `N_VNewEmpty_OpenMP`, `N_VMake_OpenMP`, and `N_VCloneVectorArrayEmpty_OpenMP` set the field `own_data = SUNFALSE`. `N_VDestroy_OpenMP` and `N_VDestroyVectorArray_OpenMP` will not attempt to free the pointer `data` for any `N_Vector` with `own_data` set to `SUNFALSE`. In such a case, it is the user's responsibility to deallocate the `data` pointer.
- To maximize efficiency, vector operations in the `NVECTOR_OPENMP` implementation that have more than one `N_Vector` argument do not check for consistent internal representation of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.



6.4.3 NVECTOR_OPENMP Fortran interfaces

The NVECTOR_OPENMP module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `nvector_omp_mod` FORTRAN module defines interfaces to most `NVECTOR_OPENMP` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `N_VNew_OpenMP` is interfaced as `FN_VNew_OpenMP`.

The FORTRAN 2003 NVECTOR_OPENMP interface module can be accessed with the `use` statement, i.e. `use fnvector_openmp_mod`, and linking to the library `libsundials_fnvectoropenmp_mod.lib` in addition to the C library. For details on where the library and module file `fnvector_openmp_mod.mod` are installed see Appendix A.

FORTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the NVECTOR_OPENMP module also includes a FORTRAN-callable function `FNVINITOMP(code, NEQ, NUMTHREADS, IER)`, to initialize this module. Here `code` is an input solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, 4 for ARKODE); `NEQ` is the problem size (declared so as to match C type `long int`); `NUMTHREADS` is the number of threads; and `IER` is an error return flag equal 0 for success and -1 for failure.

6.5 The NVECTOR_PTHREADS implementation

In situations where a user has a multi-core processing unit capable of running multiple parallel threads with shared memory, SUNDIALS provides an implementation of NVECTOR using OpenMP, called NVECTOR_OPENMP, and an implementation using Pthreads, called NVECTOR_PTHREADS. Testing has shown that vectors should be of length at least 100,000 before the overhead associated with creating and using the threads is made up by the parallelism in the vector calculations.

The Pthreads NVECTOR implementation provided with SUNDIALS, denoted NVECTOR_PTHREADS, defines the *content* field of *N_Vector* to be a structure containing the length of the vector, a pointer to the beginning of a contiguous data array, a boolean flag *own_data* which specifies the ownership of *data*, and the number of threads. Operations on the vector are threaded using POSIX threads (Pthreads).

```
struct _N_VectorContent_Pthreads {
    sunindextype length;
    booleantype own_data;
    realtype *data;
    int num_threads;
};
```

The header file to include when using this module is `nvector_pthreads.h`. The installed module library to link to is `libsundials_nvecpthreads.lib` where *.lib* is typically *.so* for shared libraries and *.a* for static libraries.

6.5.1 NVECTOR_PTHREADS accessor macros

The following macros are provided to access the content of an NVECTOR_PTHREADS vector. The suffix *_PT* in the names denotes the Pthreads version.

- NV_CONTENT_PT

This routine gives access to the contents of the Pthreads vector *N_Vector*.

The assignment `v_cont = NV_CONTENT_PT(v)` sets *v_cont* to be a pointer to the Pthreads *N_Vector* content structure.

Implementation:

```
#define NV_CONTENT_PT(v) ( (N_VectorContent_Pthreads)(v->content) )
```

- NV_OWN_DATA_PT, NV_DATA_PT, NV_LENGTH_PT, NV_NUM_THREADS_PT

These macros give individual access to the parts of the content of a Pthreads *N_Vector*.

The assignment `v_data = NV_DATA_PT(v)` sets *v_data* to be a pointer to the first component of the data for the *N_Vector* *v*. The assignment `NV_DATA_PT(v) = v_data` sets the component array of *v* to be *v_data* by storing the pointer *v_data*.

The assignment `v_len = NV_LENGTH_PT(v)` sets *v_len* to be the length of *v*. On the other hand, the call `NV_LENGTH_PT(v) = len_v` sets the length of *v* to be *len_v*.

The assignment `v_num_threads = NV_NUM_THREADS_PT(v)` sets *v_num_threads* to be the number of threads from *v*. On the other hand, the call `NV_NUM_THREADS_PT(v) = num_threads_v` sets the number of threads for *v* to be *num_threads_v*.

Implementation:

```
#define NV_OWN_DATA_PT(v) ( NV_CONTENT_PT(v)->own_data )
```

```
#define NV_DATA_PT(v) ( NV_CONTENT_PT(v)->data )
```

```
#define NV_LENGTH_PT(v) ( NV_CONTENT_PT(v)->length )
```

```
#define NV_NUM_THREADS_PT(v) ( NV_CONTENT_PT(v)->num_threads )
```

- `NV_Ith_PT`

This macro gives access to the individual components of the data array of an `N_Vector`.

The assignment `r = NV_Ith_PT(v,i)` sets `r` to be the value of the `i`-th component of `v`. The assignment `NV_Ith_PT(v,i) = r` sets the value of the `i`-th component of `v` to be `r`.

Here `i` ranges from 0 to $n - 1$ for a vector of length n .

Implementation:

```
#define NV_Ith_PT(v,i) ( NV_DATA_PT(v)[i] )
```

6.5.2 NVECTOR_PTHREADS functions

The `NVECTOR_PTHREADS` module defines Pthreads implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4. Their names are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_Pthreads` (e.g. `N_VDestroy_Pthreads`). All the standard vector operations listed in 6.2 are callable via the Fortran 2003 interface by prepending an ‘F’ (e.g. `FN_VDestroy_Pthreads`). The module `NVECTOR_PTHREADS` provides the following additional user-callable routines:

`N_VNew_Pthreads`

Prototype `N_Vector N_VNew_Pthreads(sunindextype vec_length, int num_threads)`

Description This function creates and allocates memory for a Pthreads `N_Vector`. Arguments are the vector length and number of threads.

F2003 Name This function is callable as `FN_VNew_Pthreads` when using the Fortran 2003 interface module.

`N_VNewEmpty_Pthreads`

Prototype `N_Vector N_VNewEmpty_Pthreads(sunindextype vec_length, int num_threads)`

Description This function creates a new Pthreads `N_Vector` with an empty (NULL) data array.

F2003 Name This function is callable as `FN_VNewEmpty_Pthreads` when using the Fortran 2003 interface module.

`N_VMake_Pthreads`

Prototype `N_Vector N_VMake_Pthreads(sunindextype vec_length, realtype *v_data, int num_threads);`

Description This function creates and allocates memory for a Pthreads vector with user-provided data array. This function does *not* allocate memory for `v_data` itself.

F2003 Name This function is callable as `FN_VMake_Pthreads` when using the Fortran 2003 interface module.

`N_VCloneVectorArray_Pthreads`

Prototype `N_Vector *N_VCloneVectorArray_Pthreads(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` Pthreads vectors.

`N_VCloneVectorArrayEmpty_Pthreads`

Prototype `N_Vector *N_VCloneVectorArrayEmpty_Pthreads(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` Pthreads vectors, each with an empty (NULL) data array.

N_VDestroyVectorArray_Pthreads

Prototype `void N_VDestroyVectorArray_Pthreads(N_Vector *vs, int count)`

Description This function frees memory allocated for the array of `count` variables of type `N_Vector` created with `N_VCloneVectorArray_Pthreads` or with `N_VCloneVectorArrayEmpty_Pthreads`.

N_VGetLength_Pthreads

Prototype `sunindextype N_VGetLength_Pthreads(N_Vector v)`

Description This function returns the number of vector elements.

F2003 Name This function is callable as `FN_VGetLength_Pthreads` when using the Fortran 2003 interface module.

N_VPrint_Pthreads

Prototype `void N_VPrint_Pthreads(N_Vector v)`

Description This function prints the content of a Pthreads vector to `stdout`.

F2003 Name This function is callable as `FN_VPrint_Pthreads` when using the Fortran 2003 interface module.

N_VPrintFile_Pthreads

Prototype `void N_VPrintFile_Pthreads(N_Vector v, FILE *outfile)`

Description This function prints the content of a Pthreads vector to `outfile`.

By default all fused and vector array operations are disabled in the `NVECTOR_PTHREADS` module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_Pthreads`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_Pthreads` will have the default settings for the `NVECTOR_PTHREADS` module.

N_VEnableFusedOps_Pthreads

Prototype `int N_VEnableFusedOps_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) all fused and vector array operations in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are `NULL`.

N_VEnableLinearCombination_Pthreads

Prototype `int N_VEnableLinearCombination_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) the linear combination fused operation in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are `NULL`.

N_VEnableScaleAddMulti_Pthreads

Prototype `int N_VEnableScaleAddMulti_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableDotProdMulti_Pthreads

Prototype `int N_VEnableDotProdMulti_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearSumVectorArray_Pthreads

Prototype `int N_VEnableLinearSumVectorArray_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleVectorArray_Pthreads

Prototype `int N_VEnableScaleVectorArray_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableConstVectorArray_Pthreads

Prototype `int N_VEnableConstVectorArray_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_Pthreads

Prototype `int N_VEnableWrmsNormVectorArray_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_Pthreads

Prototype `int N_VEnableWrmsNormMaskVectorArray_Pthreads(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.



[illegible]

N_VEnableLinearCombinationVectorArray_Pthreads

```
Prototype      int N_VEnableLinearCombinationVectorArray_Pthreads(N_Vector v,
```

| | |
|-------------|--|
| Description | This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the Pthreads vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL . |
|-------------|--|

- When looping over the components of an `N_Vector` `v`, it is more efficient to first obtain the component array via `v_data = NV_DATA_PT(v)` and then access `v_data[i]` within the loop than it is to use `NV_Ith_PT(v,i)` within the loop.



The NVECTOR_PTHREADS module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

The `nvector_pthreads_mod` FORTRAN module defines interfaces to most `NVECTOR_PTHREADS` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `N_VNew_Pthreads` is interfaced as `FN_VNew_Pthreads`.

The FORTRAN 2003 NVECTOR_PTHREADS interface module can be accessed with the `use` statement, i.e. `use fnvector_pthreads_mod`, and linking to the library `libsundials_fnvectorpthreads_mod.lib` in addition to the C library. For details on where the library and module file `fnvector_pthreads_mod.mod` are installed see Appendix A.

For solvers that include a FORTRAN interface module, the NVECTOR_PTHREADS module also includes a FORTRAN-callable function `FNVINITPTS(code, NEQ, NUMTHREADS, IER)`, to initialize this module. Here `code` is an input solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, 4 for ARKODE); `NEQ` is the problem size (declared so as to match C type `long int`); `NUMTHREADS` is the number of threads; and `IER` is an error return flag equal 0 for success and -1 for failure.

6.6 The NVECTOR_PARHYP implementation

The NVECTOR_PARHYP implementation of the NVECTOR module provided with SUNDIALS is a wrapper around *hypre*'s ParVector class. Most of the vector kernels simply call *hypre* vector operations. The implementation defines the *content* field of `N_Vector` to be a structure containing the global and local lengths of the vector, a pointer to an object of type `HYPRE_ParVector`, an MPI communicator, and a boolean flag *own_parvector* indicating ownership of the *hypre* parallel vector object *x*.

```
struct _N_VectorContent_ParHyp {
    sunindextype local_length;
    sunindextype global_length;
    boolean_t own_parvector;
    MPI_Comm comm;
    HYPRE_ParVector x;
};
```

The header file to include when using this module is `nvector_parhyp.h`. The installed module library to link to is `libsundials_nvecparhyp.lib` where *.lib* is typically *.so* for shared libraries and *.a* for static libraries.

Unlike native SUNDIALS vector types, NVECTOR_PARHYP does not provide macros to access its member variables. Note that NVECTOR_PARHYP requires SUNDIALS to be built with MPI support.

6.6.1 NVECTOR_PARHYP functions

The NVECTOR_PARHYP module defines implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4, except for `N_VSetArrayPointer` and `N_VGetArrayPointer`, because accessing raw vector data is handled by low-level *hypre* functions. As such, this vector is not available for use with SUNDIALS Fortran interfaces. When access to raw vector data is needed, one should extract the *hypre* vector first, and then use *hypre* methods to access the data. Usage examples of NVECTOR_PARHYP are provided in the `cvAdvDiff_non_ph.c` example program for CVODE [26] and the `ark_diurnal_kry_ph.c` example program for ARKODE [31].

The names of parhyp methods are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_ParHyp` (e.g. `N_VDestroy_ParHyp`). The module NVECTOR_PARHYP provides the following additional user-callable routines:

`N_VNewEmpty_ParHyp`

Prototype `N_Vector N_VNewEmpty_ParHyp(MPI_Comm comm, sunindextype local_length, sunindextype global_length)`

Description This function creates a new parhyp `N_Vector` with the pointer to the *hypre* vector set to NULL.

`N_VMake_ParHyp`

Prototype `N_Vector N_VMake_ParHyp(HYPRE_ParVector x)`

Description This function creates an `N_Vector` wrapper around an existing *hypre* parallel vector. It does *not* allocate memory for *x* itself.

`N_VGetVector_ParHyp`

Prototype `HYPRE_ParVector N_VGetVector_ParHyp(N_Vector v)`

Description This function returns the underlying *hypre* vector.

N_VCloneVectorArray_ParHyp

Prototype `N_Vector *N_VCloneVectorArray_ParHyp(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` parallel vectors.

N_VCloneVectorArrayEmpty_ParHyp

Prototype `N_Vector *N_VCloneVectorArrayEmpty_ParHyp(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` parallel vectors, each with an empty (NULL) data array.

N_VDestroyVectorArray_ParHyp

Prototype `void N_VDestroyVectorArray_ParHyp(N_Vector *vs, int count)`

Description This function frees memory allocated for the array of `count` variables of type `N_Vector` created with `N_VCloneVectorArray_ParHyp` or with `N_VCloneVectorArrayEmpty_ParHyp`.

N_VPrint_ParHyp

Prototype `void N_VPrint_ParHyp(N_Vector v)`

Description This function prints the local content of a parhyp vector to `stdout`.

N_VPrintFile_ParHyp

Prototype `void N_VPrintFile_ParHyp(N_Vector v, FILE *outfile)`

Description This function prints the local content of a parhyp vector to `outfile`.

By default all fused and vector array operations are disabled in the `NVECTOR_PARHYP` module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VMake_ParHyp`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VMake_ParHyp` will have the default settings for the `NVECTOR_PARHYP` module.

N_VEnableFusedOps_ParHyp

Prototype `int N_VEnableFusedOps_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) all fused and vector array operations in the parhyp vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearCombination_ParHyp

Prototype `int N_VEnableLinearCombination_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) the linear combination fused operation in the parhyp vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleAddMulti_ParHyp

Prototype `int N_VEnableScaleAddMulti_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableDotProdMulti_ParHyp

Prototype `int N_VEnableDotProdMulti_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearSumVectorArray_ParHyp

Prototype `int N_VEnableLinearSumVectorArray_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleVectorArray_ParHyp

Prototype `int N_VEnableScaleVectorArray_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableConstVectorArray_ParHyp

Prototype `int N_VEnableConstVectorArray_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_ParHyp

Prototype `int N_VEnableWrmsNormVectorArray_ParHyp(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_ParHyp

Prototype `int N_VEnableWrmsNormMaskVectorArray_ParHyp(N_Vector v, boolean_t tf)`



Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

[illegible]

N_VEnableLinearCombinationVectorArray_ParHyp

| | |
|-------------|--|
| Description | This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the parhyp vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL . |
|-------------|--|

- When there is a need to access components of an `N_Vector_ParHyp`, `v`, it is recommended to extract the *hypr* vector via `x_vec = N_VGetVector_ParHyp(v)` and then access components using appropriate *hypr* functions.



The `NVECTOR_PETSC` module is an `NVECTOR` wrapper around the PETSc vector. It defines the *content* field of a `N_Vector` to be a structure containing the global and local lengths of the vector, a pointer to the PETSc vector, an MPI communicator, and a boolean flag *own_data* indicating ownership of the wrapped PETSc vector.

The header file to include when using this module is `nvector_petsc.h`. The installed module library to link to is `libsundials_nvecpetsc.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries.

Unlike native SUNDIALS vector types, NVECTOR_PETSC does not provide macros to access its member variables. Note that NVECTOR_PETSC requires SUNDIALS to be built with MPI support.

The NVECTOR_PETSC module defines implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4, except for `N_VGetArrayPointer` and `N_VSetArrayPointer`. As such, this vector cannot be used with SUNDIALS Fortran interfaces. When access to raw vector data is needed, it is recommended to extract the PETSc vector first, and then use PETSc methods to access the data. Usage examples of NVECTOR_PETSC are provided in example programs for IDA [25].

N_VNewEmpty_Petsc

| | |
|-------------|---|
| Description | This function creates a new NVECTOR wrapper with the pointer to the wrapped PETSc vector set to (NULL). It is used by the N_VMake_Petsc and N_VClone_Petsc implementations. |
|-------------|---|

N_VMake_Petsc

| | |
|-------------|--|
| Description | This function creates and allocates memory for an NVECTOR_PETSC wrapper around a user-provided PETsc vector. It does <i>not</i> allocate memory for the vector <code>pvec</code> itself. |
|-------------|--|

N_VGetVector_Petsc

Description This function returns a pointer to the underlying PETSc vector.

N_VCloneVectorArray_Petsc

Description This function creates (by cloning) an array of `count` NVECTOR_PETSC vectors.

N_VCloneVectorArrayEmpty_Petsc

| | |
|-------------|---|
| Description | This function creates (by cloning) an array of <code>count</code> <code>NVECTOR_PETSC</code> vectors, each with pointers to PETSc vectors set to (<code>NULL</code>). |
|-------------|---|

N_VDestroyVectorArray_Petsc

| | |
|-------------|--|
| Description | This function frees memory allocated for the array of <code>count</code> variables of type <code>N_Vector</code> created with <code>N_VCloneVectorArrayPetsc</code> or with <code>N_VCloneVectorArrayEmptyPetsc</code> . |
|-------------|--|

N_VPrint_Petsc

Description This function prints the global content of a wrapped PETSc vector to `stdout`.

N_VPrintFile_Petsc

Prototype `void N_VPrintFile_Petsc(N_Vector v, const char fname[])`

Description This function prints the global content of a wrapped PETSc vector to `fname`.

By default all fused and vector array operations are disabled in the NVECTOR_PETSC module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VMake_Petsc`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VMake_Petsc` will have the default settings for the NVECTOR_PETSC module.

N_VEnableFusedOps_Petsc

Prototype `int N_VEnableFusedOps_Petsc(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) all fused and vector array operations in the PETSc vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearCombination_Petsc

Prototype `int N_VEnableLinearCombination_Petsc(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination fused operation in the PETSc vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleAddMulti_Petsc

Prototype `int N_VEnableScaleAddMulti_Petsc(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the PETSc vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableDotProdMulti_Petsc

Prototype `int N_VEnableDotProdMulti_Petsc(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the PETSc vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearSumVectorArray_Petsc

Prototype `int N_VEnableLinearSumVectorArray_Petsc(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the PETSc vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleVectorArray_Petsc

Prototype `int N_VEnableScaleVectorArray_Petsc(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the PETSc vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableConstVectorArray_Petsc

Prototype `int N_VEnableConstVectorArray_Petsc(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the PETSc vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_Petsc

Prototype `int N_VEnableWrmsNormVectorArray_Petsc(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the PETSc vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_Petsc

Prototype `int N_VEnableWrmsNormMaskVectorArray_Petsc(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the PETSc vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleAddMultiVectorArray_Petsc

Prototype `int N_VEnableScaleAddMultiVectorArray_Petsc(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector array to multiple vector arrays operation in the PETSc vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearCombinationVectorArray_Petsc

Prototype `int N_VEnableLinearCombinationVectorArray_Petsc(N_Vector v,
boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the PETSc vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

Notes

- When there is a need to access components of an `N_Vector_Petsc`, `v`, it is recommended to extract the PETSc vector via `x_vec = N_VGetVector_Petsc(v)` and then access components using appropriate PETSc functions.
- The functions `N_VNewEmpty_Petsc`, `N_VMake_Petsc`, and `N_VCloneVectorArrayEmpty_Petsc` set the field `own_data` to `SUNFALSE`. `N_VDestroy_Petsc` and `N_VDestroyVectorArray_Petsc` will not attempt to free the pointer `pvec` for any `N_Vector` with `own_data` set to `SUNFALSE`. In such a case, it is the user's responsibility to deallocate the `pvec` pointer.
- To maximize efficiency, vector operations in the NVECTOR_PETSC implementation that have more than one `N_Vector` argument do not check for consistent internal representations of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.



6.8 The NVECTOR_CUDA implementation

The NVECTOR_CUDA module is an experimental NVECTOR implementation in the CUDA language. The module allows for SUNDIALS vector kernels to run on GPU devices. It is intended for users who are already familiar with CUDA and GPU programming. Building this vector module requires a CUDA compiler and, by extension, a C++ compiler. The class `Vector` in the namespace `suncudavec` manages the vector data layout:

```
template <class T, class I>
class Vector {
    I size_;
    I mem_size_;
    I global_size_;
    T* h_vec_;
    T* d_vec_;
    ThreadPartitioning<T, I>* partStream_;
    ThreadPartitioning<T, I>* partReduce_;
    bool ownPartitioning_;
    bool ownData_;
    bool managed_mem_;
    SUNMPI_Comm comm_;
    ...
};
```

The class members are vector size (length), size of the vector data memory block, pointers to vector data on the host and the device, pointers to `ThreadPartitioning` implementations that handle thread partitioning for streaming and reduction vector kernels, a boolean flag that signals if the vector owns the thread partitioning, a boolean flag that signals if the vector owns the data, a boolean flag that signals if managed memory is used for the data arrays, and the MPI communicator. The class `Vector` inherits from the empty structure

```
struct _N_VectorContent_Cuda {};
```

to interface the C++ class with the NVECTOR C code. Due to the rapid progress of CUDA development, we expect that the `suncudavec::Vector` class will change frequently in future SUNDIALS releases. The code is structured so that it can tolerate significant changes in the `suncudavec::Vector` class without requiring changes to the user API.

When instantiated with `N_VNew_Cuda`, the class `Vector` will allocate memory on both the host and the device. Alternatively, a user can provide host and device data arrays by using the `N_VMake_Cuda` constructor. To use CUDA managed memory, the constructors `N_VNewManaged_Cuda` and `N_VMakeManaged_Cuda` are provided. Details on each of these constructors are provided below.

The NVECTOR_CUDA module can be utilized for single-node parallelism or in a distributed context with MPI. In the single-node case the header file to include `nvector_cuda.h` and the library to link to is `libsundials_nveccuda.lib`. In the a distributed setting the header file to include is `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`. The extension, `.lib`, is typically `.so` for shared libraries and `.a` for static libraries. Only one of these libraries may be linked to when creating an executable or library. SUNDIALS must be built with MPI support if the distributed library is desired.

6.8.1 NVECTOR_CUDA functions

Unlike other native SUNDIALS vector types, NVECTOR_CUDA does not provide macros to access its member variables. Instead, user should use the accessor functions:

N_VGetLength_Cuda

Prototype `sunindextype N_VGetLength_Cuda(N_Vector v)`

Description This function returns the global length of the vector.

N_VGetLocalLength_Cuda

Prototype `sunindextype N_VGetLocalLength_Cuda(N_Vector v)`

Description This function returns the local length of the vector.

Note: This function is for use in a *distributed* context and is defined in the header `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`.

N_VGetHostArrayPointer_Cuda

Prototype `realtype *N_VGetHostArrayPointer_Cuda(N_Vector v)`

Description This function returns a pointer to the vector data on the host.

N_VGetDeviceArrayPointer_Cuda

Prototype `realtype *N_VGetDeviceArrayPointer_Cuda(N_Vector v)`

Description This function returns a pointer to the vector data on the device.

N_VGetMPIComm_Cuda

Prototype `MPI_Comm N_VGetMPIComm_Cuda(N_Vector v)`

Description This function returns the MPI communicator for the vector.

Note: This function is for use in a *distributed* context and is defined in the header `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`.

N_VIsManagedMemory_Cuda

Prototype `boolean_t *N_VIsManagedMemory_Cuda(N_Vector v)`

Description This function returns a boolean flag indicating if the vector data is allocated in managed memory or not.

The NVECTOR_CUDA module defines implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4, except for `N_VGetArrayPointer` and `N_VSetArrayPointer`. As such, this vector cannot be used with the SUNDIALS Fortran interfaces, nor with the SUNDIALS direct solvers and preconditioners. Instead, the NVECTOR_CUDA module provides separate functions to access data on the host and on the device. It also provides methods for copying from the host to the device and vice versa. Usage examples of NVECTOR_CUDA are provided in some example programs for CVODE [26].

The names of vector operations are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_Cuda` (e.g. `N_VDestroy_Cuda`). The module NVECTOR_CUDA provides the following functions:

N_VNew_Cuda

Single-node usage

Prototype `N_Vector N_VNew_Cuda(sunindextype length)`

Description This function creates and allocates memory for a CUDA `N_Vector`. The vector data array is allocated on both the host and device. In the *single-node* setting, the only input is the vector length. This constructor is defined in the header `nvector_cuda.h` and the library to link to is `libsundials_nveccuda.lib`.

Distributed-memory parallel usage

Description This function creates and allocates memory for a CUDA `N_Vector`. The vector data array is allocated on both the host and device. When used in a *distributed* context with MPI, the arguments are the MPI communicator, the local vector length, and the global vector length. This constructor is defined in the header `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`.

Single-node usage

| | |
|-------------|---|
| Description | This function creates and allocates memory for a CUDA <code>N_Vector</code> on a single node. The vector data array is allocated in managed memory. In the <i>single-node</i> setting, the only input is the vector length. This constructor is defined in the header <code>nvector_cuda.h</code> and the library to link to is <code>libsundials_nveccuda.lib</code> . |
|-------------|---|

Description This function creates and allocates memory for a CUDA `N_Vector` on a single node. The vector data array is allocated in managed memory. When used in a *distributed* context with MPI, the arguments are the MPI communicator, the local vector length, and the global vector length. This constructor is defined in the header `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`.

| | |
|-------------|--|
| Description | This function creates a new NVECTOR wrapper with the pointer to the wrapped CUDA vector set to NULL. It is used by the N_VNew_Cuda, N_VMake_Cuda, and N_VClone_Cuda implementations. |
|-------------|--|

| | |
|-------------|---|
| Description | This function creates an <code>NVECTOR_CUDA</code> with user-supplied vector data arrays <code>h_vdata</code> and <code>d_vdata</code> . This function does not allocate memory for data itself. In the <i>single-node</i> setting, the inputs are the vector length, the host data array, and the device data. This constructor is defined in the header <code>nvector_cuda.h</code> and the library to link to is <code>libsundials_nveccuda.lib</code> . |
|-------------|---|

| | |
|-------------|---|
| Description | This function creates an <code>NVECTOR_CUDA</code> with user-supplied vector data arrays <code>h_vdata</code> and <code>d_vdata</code> . This function does not allocate memory for data itself. When used in a <i>distributed</i> context with MPI, the arguments are the MPI communicator, the local vector length, the global vector length, the host data array, and the device data array. |
|-------------|---|

This constructor is defined in the header `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`.

`N_VMakeManaged_Cuda`

Single-node usage

Prototype `N_Vector N_VMakeManaged_Cuda(sunindextype length, realtype *vdata)`

Description This function creates an NVECTOR_CUDA with a user-supplied managed memory data array. This function does not allocate memory for data itself. In the *single-node* setting, the inputs are the vector length and the managed data array. This constructor is defined in the header `nvector_cuda.h` and the library to link to is `libsundials_nveccuda.lib`.

Distributed-memory parallel usage

Prototype `N_Vector N_VMakeManaged_Cuda(MPI_Comm comm, sunindextype local_length, sunindextype global_length, realtype *vdata)`

Description This function creates an NVECTOR_CUDA with a user-supplied managed memory data array. This function does not allocate memory for data itself. When used in a *distributed* context with MPI, the arguments are the MPI communicator, the local vector length, the global vector length, the managed data array. This constructor is defined in the header `nvector_mpicuda.h` and the library to link to is `libsundials_nvecmpicuda.lib`.

The module NVECTOR_CUDA also provides the following user-callable routines:

`N_VSetCudaStream_Cuda`

Prototype `void N_VSetCudaStream_Cuda(N_Vector v, cudaStream_t *stream)`

Description This function sets the CUDA stream that all vector kernels will be launched on. By default an NVECTOR_CUDA uses the default CUDA stream.

Note: All vectors used in a single instance of a SUNDIALS solver must use the same CUDA stream, and the CUDA stream must be set prior to solver initialization. Additionally, if manually instantiating the stream and reduce `ThreadPartitioning` of a `suncudavec::Vector`, ensure that they use the same CUDA stream.

`N_VCopyToDevice_Cuda`

Prototype `void N_VCopyToDevice_Cuda(N_Vector v)`

Description This function copies host vector data to the device.

`N_VCopyFromDevice_Cuda`

Prototype `void N_VCopyFromDevice_Cuda(N_Vector v)`

Description This function copies vector data from the device to the host.

`N_VPrint_Cuda`

Prototype `void N_VPrint_Cuda(N_Vector v)`

Description This function prints the content of a CUDA vector to `stdout`.

N_VPrintFile_Cuda

Prototype `void N_VPrintFile_Cuda(N_Vector v, FILE *outfile)`

Description This function prints the content of a CUDA vector to `outfile`.

By default all fused and vector array operations are disabled in the NVECTOR_CUDA module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_Cuda`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_Cuda` will have the default settings for the NVECTOR_CUDA module.

N_VEnableFusedOps_Cuda

Prototype `int N_VEnableFusedOps_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) all fused and vector array operations in the CUDA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearCombination_Cuda

Prototype `int N_VEnableLinearCombination_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination fused operation in the CUDA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleAddMulti_Cuda

Prototype `int N_VEnableScaleAddMulti_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the CUDA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableDotProdMulti_Cuda

Prototype `int N_VEnableDotProdMulti_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the CUDA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableLinearSumVectorArray_Cuda

Prototype `int N_VEnableLinearSumVectorArray_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the CUDA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableScaleVectorArray_Cuda

Prototype `int N_VEnableScaleVectorArray_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the CUDA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are NULL.

N_VEnableConstVectorArray_Cuda

Prototype `int N_VEnableConstVectorArray_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the CUDA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_Cuda

Prototype `int N_VEnableWrmsNormVectorArray_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the CUDA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_Cuda

Prototype `int N_VEnableWrmsNormMaskVectorArray_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the CUDA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleAddMultiVectorArray_Cuda

Prototype `int N_VEnableScaleAddMultiVectorArray_Cuda(N_Vector v, boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector array to multiple vector arrays operation in the CUDA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearCombinationVectorArray_Cuda

Prototype `int N_VEnableLinearCombinationVectorArray_Cuda(N_Vector v,
boolean_t tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the CUDA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

Notes

- When there is a need to access components of an `N_Vector_Cuda`, `v`, it is recommended to use functions `N_VGetDeviceArrayPointer_Cuda` or `N_VGetHostArrayPointer_Cuda`.
- To maximize efficiency, vector operations in the NVECTOR_CUDA implementation that have more than one `N_Vector` argument do not check for consistent internal representations of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.



6.9 The NVECTOR_RAJA implementation

The NVECTOR_RAJA module is an experimental NVECTOR implementation using the RAJA hardware abstraction layer. In this implementation, RAJA allows for SUNDIALS vector kernels to run on GPU devices. The module is intended for users who are already familiar with RAJA and GPU programming. Building this vector module requires a C++11 compliant compiler and a CUDA software development toolkit. Besides the CUDA backend, RAJA has other backends such as serial, OpenMP, and OpenACC.

These backends are not used in this SUNDIALS release. Class `Vector` in namespace `sunrajavec` manages the vector data layout:

```
template <class T, class I>
class Vector {
    I size_;
    I mem_size_;
    I global_size_;
    T* h_vec_;
    T* d_vec_;
    SUNMPI_Comm comm_;
    ...
};
```

The class members are: vector size (length), size of the vector data memory block, the global vector size (length), pointers to vector data on the host and on the device, and the MPI communicator. The class `Vector` inherits from an empty structure

```
struct _N_VectorContent_Raja {
};
```

to interface the C++ class with the NVECTOR C code. When instantiated, the class `Vector` will allocate memory on both the host and the device. Due to the rapid progress of RAJA development, we expect that the `sunrajavec::Vector` class will change frequently in future SUNDIALS releases. The code is structured so that it can tolerate significant changes in the `sunrajavec::Vector` class without requiring changes to the user API.

The NVECTOR_RAJA module can be utilized for single-node parallelism or in a distributed context with MPI. The header file to include when using this module for single-node parallelism is `nvector_raja.h`. The header file to include when using this module in the distributed case is `nvector_mpiraja.h`. The installed module libraries to link to are `libsundials_nvecraja.lib` in the single-node case, or `libsundials_nvecmpicudaraja.lib` in the distributed case. Only one of these libraries may be linked to when creating an executable or library. SUNDIALS must be built with MPI support if the distributed library is desired.

6.9.1 NVECTOR_RAJA functions

Unlike other native SUNDIALS vector types, NVECTOR_RAJA does not provide macros to access its member variables. Instead, user should use the accessor functions:

`N_VGetLength_Raja`

Prototype `sunindextype N_VGetLength_Raja(N_Vector v)`

Description This function returns the global length of the vector.

`N_VGetLocalLength_Raja`

Prototype `sunindextype N_VGetLocalLength_Raja(N_Vector v)`

Description This function returns the local length of the vector.

Note: This function is for use in a *distributed context* and is defined in the header `nvector_mpiraja.h` and the library to link to is `libsundials_nvecmpicudaraja.lib`.

`N_VGetHostArrayPointer_Raja`

Prototype `realtype *N_VGetHostArrayPointer_Raja(N_Vector v)`

Description This function returns a pointer to the vector data on the host.


```

Prototype    realtype *N_VGetDeviceArrayPointer_Raja(N_Vector v)

```

N_VGetMPIComm_Raja

Description This function returns the MPI communicator for the vector.

The `NVECTOR_RAJA` module defines the implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4, except for `N_VDotProdMulti`, `N_VWrmsNormVectorArray`, and `N_VWrmsNormMaskVectorArray` as support for arrays of reduction vectors is not yet supported in RAJA. These function will be added to the `NVECTOR_RAJA` implementation in the future. Additionally the vector operations `N_VGetArrayPointer` and `N_VSetArrayPointer` are not implemented by the RAJA vector. As such, this vector cannot be used with the SUNDIALS Fortran interfaces, nor with the SUNDIALS direct solvers and preconditioners. The `NVECTOR_RAJA` module provides separate functions to access data on the host and on the device. It also provides methods for copying data from the host to the device and vice versa. Usage examples of `NVECTOR_RAJA` are provided in some example programs for CVODE [26].

N_VNew_Raja

```

Prototype      N_Vector N_VNew_Raja(sunindextype length)

```

Distributed-memory parallel usage

Description This function creates and allocates memory for a CUDA `N_Vector`. The vector data array is allocated on both the host and device. When used in a *distributed* context with MPI, the arguments are the MPI communicator, the local vector length, and the global vector length. This constructor is defined in the header `nvector_mpiraja.h` and the library to link to is `libsundials_nvecmpicudaraja.lib`.

| | |
|-------------|--|
| Description | This function creates a new NVECTOR wrapper with the pointer to the wrapped RAJA vector set to NULL. It is used by the N_VNew_Raja, N_VMake_Raja, and N_VClone_Raja implementations. |
|-------------|--|

N_VMake_Raja

Prototype `N_Vector N_VMake_Raja(N_VectorContent_Raja c)`

Description This function creates and allocates memory for an NVECTOR_RAJA wrapper around a user-provided `sunrajavec::Vector` class. Its only argument is of type `N_VectorContent_Raja`, which is the pointer to the class.

N_VCopyToDevice_Raja

Prototype `realtype *N_VCopyToDevice_Raja(N_Vector v)`

Description This function copies host vector data to the device.

N_VCopyFromDevice_Raja

Prototype `realtype *N_VCopyFromDevice_Raja(N_Vector v)`

Description This function copies vector data from the device to the host.

N_VPrint_Raja

Prototype `void N_VPrint_Raja(N_Vector v)`

Description This function prints the content of a RAJA vector to `stdout`.

N_VPrintFile_Raja

Prototype `void N_VPrintFile_Raja(N_Vector v, FILE *outfile)`

Description This function prints the content of a RAJA vector to `outfile`.

By default all fused and vector array operations are disabled in the NVECTOR_RAJA module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_Raja`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_Raja` will have the default settings for the NVECTOR_RAJA module.

N_VEnableFusedOps_Raja

Prototype `int N_VEnableFusedOps_Raja(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) all fused and vector array operations in the RAJA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are `NULL`.

N_VEnableLinearCombination_Raja

Prototype `int N_VEnableLinearCombination_Raja(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) the linear combination fused operation in the RAJA vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are `NULL`.

N_VEnableScaleAddMulti_Raja

Prototype `int N_VEnableScaleAddMulti_Raja(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the RAJA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearSumVectorArray_Raja

Prototype `int N_VEnableLinearSumVectorArray_Raja(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the RAJA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleVectorArray_Raja

Prototype `int N_VEnableScaleVectorArray_Raja(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the RAJA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableConstVectorArray_Raja

Prototype `int N_VEnableConstVectorArray_Raja(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the RAJA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleAddMultiVectorArray_Raja

Prototype `int N_VEnableScaleAddMultiVectorArray_Raja(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector array to multiple vector arrays operation in the RAJA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearCombinationVectorArray_Raja

Prototype `int N_VEnableLinearCombinationVectorArray_Raja(N_Vector v,
booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the RAJA vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

Notes

- When there is a need to access components of an `N_Vector_Raja`, `v`, it is recommended to use functions `N_VGetDeviceArrayPointer_Raja` or `N_VGetHostArrayPointer_Raja`.
- To maximize efficiency, vector operations in the NVECTOR_RAJA implementation that have more than one `N_Vector` argument do not check for consistent internal representations of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.



6.10 The NVECTOR_OPENMPDEV implementation

In situations where a user has access to a device such as a GPU for offloading computation, SUNDIALS provides an NVECTOR implementation using OpenMP device offloading, called NVECTOR_OPENMPDEV.

The NVECTOR_OPENMPDEV implementation defines the *content* field of the `N_Vector` to be a structure containing the length of the vector, a pointer to the beginning of a contiguous data array on the host, a pointer to the beginning of a contiguous data array on the device, and a boolean flag `own_data` which specifies the ownership of host and device data arrays.

```
struct _N_VectorContent_OpenMPDEV {
    sunindextype length;
    booleantype own_data;
    realtype *host_data;
    realtype *dev_data;
};
```

The header file to include when using this module is `nvector_openmpdev.h`. The installed module library to link to is `libsundials_nvecopenmpdev.lib` where *.lib* is typically *.so* for shared libraries and *.a* for static libraries.

6.10.1 NVECTOR_OPENMPDEV accessor macros

The following macros are provided to access the content of an NVECTOR_OPENMPDEV vector.

- **NV_CONTENT_OMPDEV**

This routine gives access to the contents of the NVECTOR_OPENMPDEV vector `N_Vector`.

The assignment `v_cont = NV_CONTENT_OMPDEV(v)` sets `v_cont` to be a pointer to the NVECTOR_OPENMPDEV `N_Vector` content structure.

Implementation:

```
#define NV_CONTENT_OMPDEV(v) ( (_N_VectorContent_OpenMPDEV)(v->content) )
```

- **NV_OWN_DATA_OMPDEV, NV_DATA_HOST_OMPDEV, NV_DATA_DEV_OMPDEV, NV_LENGTH_OMPDEV**

These macros give individual access to the parts of the content of an NVECTOR_OPENMPDEV `N_Vector`.

The assignment `v_data = NV_DATA_HOST_OMPDEV(v)` sets `v_data` to be a pointer to the first component of the data on the host for the `N_Vector` `v`. The assignment `NV_DATA_HOST_OMPDEV(v) = v_data` sets the host component array of `v` to be `v_data` by storing the pointer `v_data`.

The assignment `v_dev_data = NV_DATA_DEV_OMPDEV(v)` sets `v_dev_data` to be a pointer to the first component of the data on the device for the `N_Vector` `v`. The assignment `NV_DATA_DEV_OMPDEV(v) = v_dev_data` sets the device component array of `v` to be `v_dev_data` by storing the pointer `v_dev_data`.

The assignment `v_len = NV_LENGTH_OMPDEV(v)` sets `v_len` to be the length of `v`. On the other hand, the call `NV_LENGTH_OMPDEV(v) = len_v` sets the length of `v` to be `len_v`.

Implementation:

```
#define NV_OWN_DATA_OMPDEV(v) ( NV_CONTENT_OMPDEV(v)->own_data )
#define NV_DATA_HOST_OMPDEV(v) ( NV_CONTENT_OMPDEV(v)->host_data )
#define NV_DATA_DEV_OMPDEV(v) ( NV_CONTENT_OMPDEV(v)->dev_data )
#define NV_LENGTH_OMPDEV(v) ( NV_CONTENT_OMPDEV(v)->length )
```

6.10.2 NVECTOR_OPENMPDEV functions

The NVECTOR_OPENMPDEV module defines OpenMP device offloading implementations of all vector operations listed in Tables 6.2, 6.3, and 6.4, except for `N_VGetArrayPointer` and `N_VSetArrayPointer`. As such, this vector cannot be used with the SUNDIALS Fortran interfaces, nor with the SUNDIALS direct solvers and preconditioners. It also provides methods for copying from the host to the device and vice versa.

The names of vector operations are obtained from those in Tables 6.2, 6.3, and 6.4 by appending the suffix `_OpenMPDEV` (e.g. `N_VDestroy_OpenMPDEV`). The module NVECTOR_OPENMPDEV provides the following additional user-callable routines:

N_VNew_OpenMPDEV

Prototype `N_Vector N_VNew_OpenMPDEV(sunindextype vec_length)`

Description This function creates and allocates memory for an NVECTOR_OPENMPDEV `N_Vector`.

N_VNewEmpty_OpenMPDEV

Prototype `N_Vector N_VNewEmpty_OpenMPDEV(sunindextype vec_length)`

Description This function creates a new NVECTOR_OPENMPDEV `N_Vector` with an empty (NULL) host and device data arrays.

N_VMake_OpenMPDEV

Prototype `N_Vector N_VMake_OpenMPDEV(sunindextype vec_length, realtype *h_vdata, realtype *d_vdata)`

Description This function creates an NVECTOR_OPENMPDEV vector with user-supplied vector data arrays `h_vdata` and `d_vdata`. This function does not allocate memory for data itself.

N_VCloneVectorArray_OpenMPDEV

Prototype `N_Vector *N_VCloneVectorArray_OpenMPDEV(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` NVECTOR_OPENMPDEV vectors.

N_VCloneVectorArrayEmpty_OpenMPDEV

Prototype `N_Vector *N_VCloneVectorArrayEmpty_OpenMPDEV(int count, N_Vector w)`

Description This function creates (by cloning) an array of `count` NVECTOR_OPENMPDEV vectors, each with an empty (NULL) data array.

N_VDestroyVectorArray_OpenMPDEV

Prototype `void N_VDestroyVectorArray_OpenMPDEV(N_Vector *vs, int count)`

Description This function frees memory allocated for the array of `count` variables of type `N_Vector` created with `N_VCloneVectorArray_OpenMPDEV` or with `N_VCloneVectorArrayEmpty_OpenMPDEV`.

N_VGetLength_OpenMPDEV

Prototype `sunindextype N_VGetLength_OpenMPDEV(N_Vector v)`

Description This function returns the number of vector elements.

N_VGetHostArrayPointer_OpenMPDEV

Prototype `realtype *N_VGetHostArrayPointer_OpenMPDEV(N_Vector v)`

Description This function returns a pointer to the host data array.

N_VGetDeviceArrayPointer_OpenMPDEV

Prototype `realtype *N_VGetDeviceArrayPointer_OpenMPDEV(N_Vector v)`

Description This function returns a pointer to the device data array.

N_VPrint_OpenMPDEV

Prototype `void N_VPrint_OpenMPDEV(N_Vector v)`

Description This function prints the content of an NVECTOR_OPENMPDEV vector to `stdout`.

N_VPrintFile_OpenMPDEV

Prototype `void N_VPrintFile_OpenMPDEV(N_Vector v, FILE *outfile)`

Description This function prints the content of an NVECTOR_OPENMPDEV vector to `outfile`.

N_VCopyToDevice_OpenMPDEV

Prototype `void N_VCopyToDevice_OpenMPDEV(N_Vector v)`

Description This function copies the content of an NVECTOR_OPENMPDEV vector's host data array to the device data array.

N_VCopyFromDevice_OpenMPDEV

Prototype `void N_VCopyFromDevice_OpenMPDEV(N_Vector v)`

Description This function copies the content of an NVECTOR_OPENMPDEV vector's device data array to the host data array.

By default all fused and vector array operations are disabled in the NVECTOR_OPENMPDEV module. The following additional user-callable routines are provided to enable or disable fused and vector array operations for a specific vector. To ensure consistency across vectors it is recommended to first create a vector with `N_VNew_OpenMPDEV`, enable/disable the desired operations for that vector with the functions below, and create any additional vectors from that vector using `N_VClone`. This guarantees the new vectors will have the same operations enabled/disabled as cloned vectors inherit the same enable/disable options as the vector they are cloned from while vectors created with `N_VNew_OpenMPDEV` will have the default settings for the NVECTOR_OPENMPDEV module.

N_VEnableFusedOps_OpenMPDEV

Prototype `int N_VEnableFusedOps_OpenMPDEV(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) all fused and vector array operations in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are `NULL`.

N_VEnableLinearCombination_OpenMPDEV

Prototype `int N_VEnableLinearCombination_OpenMPDEV(N_Vector v, boolean_t tf)`

Description This function enables (`SUNTRUE`) or disables (`SUNFALSE`) the linear combination fused operation in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its `ops` structure are `NULL`.

N_VEnableScaleAddMulti_OpenMPDEV

Prototype `int N_VEnableScaleAddMulti_OpenMPDEV(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale and add a vector to multiple vectors fused operation in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableDotProdMulti_OpenMPDEV

Prototype `int N_VEnableDotProdMulti_OpenMPDEV(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the multiple dot products fused operation in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableLinearSumVectorArray_OpenMPDEV

Prototype `int N_VEnableLinearSumVectorArray_OpenMPDEV(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the linear sum operation for vector arrays in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableScaleVectorArray_OpenMPDEV

Prototype `int N_VEnableScaleVectorArray_OpenMPDEV(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the scale operation for vector arrays in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableConstVectorArray_OpenMPDEV

Prototype `int N_VEnableConstVectorArray_OpenMPDEV(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the const operation for vector arrays in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormVectorArray_OpenMPDEV

Prototype `int N_VEnableWrmsNormVectorArray_OpenMPDEV(N_Vector v, booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the WRMS norm operation for vector arrays in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

N_VEnableWrmsNormMaskVectorArray_OpenMPDEV

Prototype `int N_VEnableWrmsNormMaskVectorArray_OpenMPDEV(N_Vector v,
booleantype tf)`

Description This function enables (SUNTRUE) or disables (SUNFALSE) the masked WRMS norm operation for vector arrays in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL.

```
Prototype      int N_VEnableScaleAddMultiVectorArray_OpenMPDEVID(N_Vector v,
```

`booleantype tf)`

N_VEnableLinearCombinationVectorArray_OpenMPDEV

```
Prototype      int N_VEnableLinearCombinationVectorArray_OpenMPDEV(N_Vector v,
```

boolean_t tf)

| | |
|-------------|--|
| Description | This function enables (SUNTRUE) or disables (SUNFALSE) the linear combination operation for vector arrays in the NVECTOR_OPENMPDEV vector. The return value is 0 for success and -1 if the input vector or its ops structure are NULL . |
|-------------|--|

- When looping over the components of an `N_Vector` `v`, it is most efficient to first obtain the component array via `h_data = NV_DATA_HOST_OMPDEV(v)` for the host array or `d_data = NV_DATA_DEV_OMPDEV(v)` for the device array and then access `h_data[i]` or `d_data[i]` within the loop.
- When accessing individual components of an `N_Vector` `v` on the host remember to first copy the array back from the device with `N_VCopyFromDevice_OpenMPDEV(v)` to ensure the array is up to date.
- `N_VNewEmpty_OpenMPDEV`, `N_VMake_OpenMPDEV`, and `N_VCloneVectorArrayEmpty_OpenMPDEV` set the field `own_data = SUNFALSE`. `N_VDestroy_OpenMPDEV` and `N_VDestroyVectorArray_OpenMPDEV` will not attempt to free the pointer *data* for any `N_Vector` with `own_data` set to `SUNFALSE`. In such a case, it is the user's responsibility to deallocate the *data* pointer.
- To maximize efficiency, vector operations in the `NVECTOR_OPENMPDEV` implementation that have more than one `N_Vector` argument do not check for consistent internal representation of these vectors. It is the user's responsibility to ensure that such routines are called with `N_Vector` arguments that were all created with the same internal representations.



6.11 NVECTOR Examples

There are **NVector** examples that may be installed for the implementations provided with SUNDIALS. Each implementation makes use of the functions in `test_nvector.c`. These example functions show simple usage of the **NVector** family of functions. The input to the examples are the vector length, number of threads (if threaded implementation), and a print timing flag. The following is a list of the example functions in `test_nvector.c`:

- **Test_N_VClone:** Creates clone of vector and checks validity of clone.
- **Test_N_VCloneEmpty:** Creates clone of empty vector and checks validity of clone.
- **Test_N_VCloneVectorArray:** Creates clone of vector array and checks validity of cloned array.
- **Test_N_VCloneVectorArray:** Creates clone of empty vector array and checks validity of cloned array.
- **Test_N_VGetArrayPointer:** Get array pointer.

- `Test_N_VSetArrayPointer`: Allocate new vector, set pointer to new vector array, and check values.
- `Test_N_VLinearSum` Case 1a: Test $y = x + y$
- `Test_N_VLinearSum` Case 1b: Test $y = -x + y$
- `Test_N_VLinearSum` Case 1c: Test $y = ax + y$
- `Test_N_VLinearSum` Case 2a: Test $x = x + y$
- `Test_N_VLinearSum` Case 2b: Test $x = x - y$
- `Test_N_VLinearSum` Case 2c: Test $x = x + by$
- `Test_N_VLinearSum` Case 3: Test $z = x + y$
- `Test_N_VLinearSum` Case 4a: Test $z = x - y$
- `Test_N_VLinearSum` Case 4b: Test $z = -x + y$
- `Test_N_VLinearSum` Case 5a: Test $z = x + by$
- `Test_N_VLinearSum` Case 5b: Test $z = ax + y$
- `Test_N_VLinearSum` Case 6a: Test $z = -x + by$
- `Test_N_VLinearSum` Case 6b: Test $z = ax - y$
- `Test_N_VLinearSum` Case 7: Test $z = a(x + y)$
- `Test_N_VLinearSum` Case 8: Test $z = a(x - y)$
- `Test_N_VLinearSum` Case 9: Test $z = ax + by$
- `Test_N_VConst`: Fill vector with constant and check result.
- `Test_N_VProd`: Test vector multiply: $z = x * y$
- `Test_N_VDiv`: Test vector division: $z = x / y$
- `Test_N_VScale`: Case 1: scale: $x = cx$
- `Test_N_VScale`: Case 2: copy: $z = x$
- `Test_N_VScale`: Case 3: negate: $z = -x$
- `Test_N_VScale`: Case 4: combination: $z = cx$
- `Test_N_VAbs`: Create absolute value of vector.
- `Test_N_VAddConst`: add constant vector: $z = c + x$
- `Test_N_VDotProd`: Calculate dot product of two vectors.
- `Test_N_VMaxNorm`: Create vector with known values, find and validate the max norm.
- `Test_N_VWrmsNorm`: Create vector of known values, find and validate the weighted root mean square.
- `Test_N_VWrmsNormMask`: Create vector of known values, find and validate the weighted root mean square using all elements except one.
- `Test_N_VMin`: Create vector, find and validate the min.

- **Test_N_VWL2Norm**: Create vector, find and validate the weighted Euclidean L2 norm.
- **Test_N_VL1Norm**: Create vector, find and validate the L1 norm.
- **Test_N_VCompare**: Compare vector with constant returning and validating comparison vector.
- **Test_N_VInvTest**: Test $z[i] = 1 / x[i]$
- **Test_N_VConstrMask**: Test mask of vector x with vector c.
- **Test_N_VMinQuotient**: Fill two vectors with known values. Calculate and validate minimum quotient.
- **Test_N_VLinearCombination Case 1a**: Test $x = a x$
- **Test_N_VLinearCombination Case 1b**: Test $z = a x$
- **Test_N_VLinearCombination Case 2a**: Test $x = a x + b y$
- **Test_N_VLinearCombination Case 2b**: Test $z = a x + b y$
- **Test_N_VLinearCombination Case 3a**: Test $x = x + a y + b z$
- **Test_N_VLinearCombination Case 3b**: Test $x = a x + b y + c z$
- **Test_N_VLinearCombination Case 3c**: Test $w = a x + b y + c z$
- **Test_N_VScaleAddMulti Case 1a**: $y = a x + y$
- **Test_N_VScaleAddMulti Case 1b**: $z = a x + y$
- **Test_N_VScaleAddMulti Case 2a**: $Y[i] = c[i] x + Y[i]$, $i = 1,2,3$
- **Test_N_VScaleAddMulti Case 2b**: $Z[i] = c[i] x + Y[i]$, $i = 1,2,3$
- **Test_N_VDotProdMulti Case 1**: Calculate the dot product of two vectors
- **Test_N_VDotProdMulti Case 2**: Calculate the dot product of one vector with three other vectors in a vector array.
- **Test_N_VLinearSumVectorArray Case 1**: $z = a x + b y$
- **Test_N_VLinearSumVectorArray Case 2a**: $Z[i] = a X[i] + b Y[i]$
- **Test_N_VLinearSumVectorArray Case 2b**: $X[i] = a X[i] + b Y[i]$
- **Test_N_VLinearSumVectorArray Case 2c**: $Y[i] = a X[i] + b Y[i]$
- **Test_N_VScaleVectorArray Case 1a**: $y = c y$
- **Test_N_VScaleVectorArray Case 1b**: $z = c y$
- **Test_N_VScaleVectorArray Case 2a**: $Y[i] = c[i] Y[i]$
- **Test_N_VScaleVectorArray Case 2b**: $Z[i] = c[i] Y[i]$
- **Test_N_VScaleVectorArray Case 1a**: $z = c$
- **Test_N_VScaleVectorArray Case 1b**: $Z[i] = c$
- **Test_N_VWrmsNormVectorArray Case 1a**: Create a vector of know values, find and validate the weighted root mean square norm.
- **Test_N_VWrmsNormVectorArray Case 1b**: Create a vector array of three vectors of know values, find and validate the weighted root mean square norm of each.

- `Test_N_VWrmsNormMaskVectorArray` Case 1a: Create a vector of know values, find and validate the weighted root mean square norm using all elements except one.
- `Test_N_VWrmsNormMaskVectorArray` Case 1b: Create a vector array of three vectors of know values, find and validate the weighted root mean square norm of each using all elements except one.
- `Test_N_VScaleAddMultiVectorArray` Case 1a: $y = a x + y$
- `Test_N_VScaleAddMultiVectorArray` Case 1b: $z = a x + y$
- `Test_N_VScaleAddMultiVectorArray` Case 2a: $Y[j][0] = a[j] X[0] + Y[j][0]$
- `Test_N_VScaleAddMultiVectorArray` Case 2b: $Z[j][0] = a[j] X[0] + Y[j][0]$
- `Test_N_VScaleAddMultiVectorArray` Case 3a: $Y[0][i] = a[0] X[i] + Y[0][i]$
- `Test_N_VScaleAddMultiVectorArray` Case 3b: $Z[0][i] = a[0] X[i] + Y[0][i]$
- `Test_N_VScaleAddMultiVectorArray` Case 4a: $Y[j][i] = a[j] X[i] + Y[j][i]$
- `Test_N_VScaleAddMultiVectorArray` Case 4b: $Z[j][i] = a[j] X[i] + Y[j][i]$
- `Test_N_VLinearCombinationVectorArray` Case 1a: $x = a x$
- `Test_N_VLinearCombinationVectorArray` Case 1b: $z = a x$
- `Test_N_VLinearCombinationVectorArray` Case 2a: $x = a x + b y$
- `Test_N_VLinearCombinationVectorArray` Case 2b: $z = a x + b y$
- `Test_N_VLinearCombinationVectorArray` Case 3a: $x = a x + b y + c z$
- `Test_N_VLinearCombinationVectorArray` Case 3b: $w = a x + b y + c z$
- `Test_N_VLinearCombinationVectorArray` Case 4a: $X[0][i] = c[0] X[0][i]$
- `Test_N_VLinearCombinationVectorArray` Case 4b: $Z[i] = c[0] X[0][i]$
- `Test_N_VLinearCombinationVectorArray` Case 5a: $X[0][i] = c[0] X[0][i] + c[1] X[1][i]$
- `Test_N_VLinearCombinationVectorArray` Case 5b: $Z[i] = c[0] X[0][i] + c[1] X[1][i]$
- `Test_N_VLinearCombinationVectorArray` Case 6a: $X[0][i] = X[0][i] + c[1] X[1][i] + c[2] X[2][i]$
- `Test_N_VLinearCombinationVectorArray` Case 6b: $X[0][i] = c[0] X[0][i] + c[1] X[1][i] + c[2] X[2][i]$
- `Test_N_VLinearCombinationVectorArray` Case 6c: $Z[i] = c[0] X[0][i] + c[1] X[1][i] + c[2] X[2][i]$

Chapter 7

Description of the SUNMatrix module

For problems that involve direct methods for solving linear systems, the SUNDIALS solvers not only operate on generic vectors, but also on generic matrices (of type `SUNMatrix`), through a set of operations defined by the particular SUNMATRIX implementation. Users can provide their own specific implementation of the SUNMATRIX module, particularly in cases where they provide their own NVECTOR and/or linear solver modules, and require matrices that are compatible with those implementations. Alternately, we provide three SUNMATRIX implementations: dense, banded, and sparse. The generic operations are described below, and descriptions of the implementations provided with SUNDIALS follow.

The generic `SUNMatrix` type has been modeled after the object-oriented style of the generic `N_Vector` type. Specifically, a generic `SUNMatrix` is a pointer to a structure that has an implementation-dependent *content* field containing the description and actual data of the matrix, and an *ops* field pointing to a structure with generic matrix operations. The type `SUNMatrix` is defined as

```
typedef struct _generic_SUNMatrix *SUNMatrix;
```

```
struct _generic_SUNMatrix {  
    void *content;  
    struct _generic_SUNMatrix_Ops *ops;  
};
```

The `_generic_SUNMatrix_Ops` structure is essentially a list of pointers to the various actual matrix operations, and is defined as

```
struct _generic_SUNMatrix_Ops {  
    SUNMatrix_ID (*getid)(SUNMatrix);  
    SUNMatrix (*clone)(SUNMatrix);  
    void (*destroy)(SUNMatrix);  
    int (*zero)(SUNMatrix);  
    int (*copy)(SUNMatrix, SUNMatrix);  
    int (*scaleadd)(realtype, SUNMatrix, SUNMatrix);  
    int (*scaleaddi)(realtype, SUNMatrix);  
    int (*matvec)(SUNMatrix, N_Vector, N_Vector);  
    int (*space)(SUNMatrix, long int*, long int*);  
};
```

The generic SUNMATRIX module defines and implements the matrix operations acting on `SUNMatrix` objects. These routines are nothing but wrappers for the matrix operations defined by a particular SUNMATRIX implementation, which are accessed through the *ops* field of the `SUNMatrix` structure. To

Table 7.1: Identifiers associated with matrix kernels supplied with SUNDIALS.

| Matrix ID | Matrix type | ID Value |
|------------------|---|----------|
| SUNMATRIX_DENSE | Dense $M \times N$ matrix | 0 |
| SUNMATRIX_BAND | Band $M \times M$ matrix | 1 |
| SUNMATRIX_SPARSE | Sparse (CSR or CSC) $M \times N$ matrix | 2 |
| SUNMATRIX_CUSTOM | User-provided custom matrix | 3 |

illustrate this point we show below the implementation of a typical matrix operation from the generic SUNMATRIX module, namely `SUNMatZero`, which sets all values of a matrix `A` to zero, returning a flag denoting a successful/failed operation:

```
int SUNMatZero(SUNMatrix A)
{
    return((int) A->ops->zero(A));
}
```

Table 7.2 contains a complete list of all matrix operations defined by the generic SUNMATRIX module. A particular implementation of the SUNMATRIX module must:

- Specify the *content* field of the `SUNMatrix` object.
- Define and implement a minimal subset of the matrix operations. See the documentation for each SUNDIALS solver to determine which SUNMATRIX operations they require.

Note that the names of these routines should be unique to that implementation in order to permit using more than one SUNMATRIX module (each with different `SUNMatrix` internal data representations) in the same code.

- Define and implement user-callable constructor and destructor routines to create and free a `SUNMatrix` with the new *content* field and with *ops* pointing to the new matrix operations.
- Optionally, define and implement additional user-callable routines acting on the newly defined `SUNMatrix` (e.g., a routine to print the content for debugging purposes).
- Optionally, provide accessor macros or functions as needed for that particular implementation to access different parts of the *content* field of the newly defined `SUNMatrix`.

Each SUNMATRIX implementation included in SUNDIALS has a unique identifier specified in enumeration and shown in Table 7.1. It is recommended that a user-supplied SUNMATRIX implementation use the `SUNMATRIX_CUSTOM` identifier.

Table 7.2: Description of the `SUNMatrix` operations

| Name | Usage and Description |
|-------------------------------|---|
| SUNMatGetID | <code>id = SUNMatGetID(A);</code> Returns the type identifier for the matrix <code>A</code> . It is used to determine the matrix implementation type (e.g. dense, banded, sparse,...) from the abstract <code>SUNMatrix</code> interface. This is used to assess compatibility with SUNDIALS-provided linear solver implementations. Returned values are given in the Table 7.1. |
| <i>continued on next page</i> | |

| Name | Usage and Description |
|-----------------|---|
| SUNMatClone | <pre>B = SUNMatClone(A);</pre> <p>Creates a new SUNMatrix of the same type as an existing matrix A and sets the <i>ops</i> field. It does not copy the matrix, but rather allocates storage for the new matrix.</p> |
| SUNMatDestroy | <pre>SUNMatDestroy(A);</pre> <p>Destroys the SUNMatrix A and frees memory allocated for its internal data.</p> |
| SUNMatSpace | <pre>ier = SUNMatSpace(A, &lrw, &liw);</pre> <p>Returns the storage requirements for the matrix A. lrw is a long int containing the number of realtype words and liw is a long int containing the number of integer words. The return value is an integer flag denoting success/failure of the operation.</p> <p>This function is advisory only, for use in determining a user's total space requirements; it could be a dummy function in a user-supplied SUNMATRIX module if that information is not of interest.</p> |
| SUNMatZero | <pre>ier = SUNMatZero(A);</pre> <p>Performs the operation $A_{ij} = 0$ for all entries of the matrix <i>A</i>. The return value is an integer flag denoting success/failure of the operation.</p> |
| SUNMatCopy | <pre>ier = SUNMatCopy(A,B);</pre> <p>Performs the operation $B_{ij} = A_{i,j}$ for all entries of the matrices <i>A</i> and <i>B</i>. The return value is an integer flag denoting success/failure of the operation.</p> |
| SUNMatScaleAdd | <pre>ier = SUNMatScaleAdd(c, A, B);</pre> <p>Performs the operation $A = cA + B$. The return value is an integer flag denoting success/failure of the operation.</p> |
| SUNMatScaleAddI | <pre>ier = SUNMatScaleAddI(c, A);</pre> <p>Performs the operation $A = cA + I$. The return value is an integer flag denoting success/failure of the operation.</p> |
| SUNMatMatvec | <pre>ier = SUNMatMatvec(A, x, y);</pre> <p>Performs the matrix-vector product operation, $y = Ax$. It should only be called with vectors x and y that are compatible with the matrix A – both in storage type and dimensions. The return value is an integer flag denoting success/failure of the operation.</p> |

We note that not all `SUNMATRIX` types are compatible with all `NVECTOR` types provided with `SUNDIALS`. This is primarily due to the need for compatibility within the `SUNMatMatvec` routine; however, compatibility between `SUNMATRIX` and `NVECTOR` implementations is more crucial when considering their interaction within `SUNLINSOL` objects, as will be described in more detail in Chapter 8. More specifically, in Table 7.3 we show the matrix interfaces available as `SUNMATRIX` modules, and the compatible vector implementations.

Table 7.3: SUNDIALS matrix interfaces and vector implementations that can be used for each.

| Matrix Interface | Serial | Parallel (MPI) | OpenMP | pThreads | <i>hypr</i> Vec. | PETSc Vec. | CUDA | RAJA | User Suppl. |
|------------------|--------|----------------|--------|----------|------------------|------------|------|------|-------------|
| Dense | ✓ | | ✓ | ✓ | | | | | ✓ |

continued on next page

| Matrix Interface | Serial | Parallel (MPI) | OpenMP | pThreads | hybre Vec. | PETSc Vec. | CUDA | RAJA | User Suppl. |
|------------------|--------|----------------|--------|----------|------------|------------|------|------|-------------|
| Band | ✓ | | ✓ | ✓ | | | | | ✓ |
| Sparse | ✓ | | ✓ | ✓ | | | | | ✓ |
| User supplied | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ | ✓ |

7.1 SUNMatrix functions used by IDA

In Table 7.4, we list the matrix functions in the SUNMATRIX module used within the IDA package. The table also shows, for each function, which of the code modules uses the function. The main IDA integrator does not call any SUNMATRIX functions directly, so the table columns are specific to the IDALS interface and the IDABBDPRE preconditioner module. We further note that the IDALS interface only utilizes these routines when supplied with a *matrix-based* linear solver, i.e., the SUNMATRIX object passed to `IDASetLinearSolver` was not NULL.

At this point, we should emphasize that the IDA user does not need to know anything about the usage of matrix functions by the IDA code modules in order to use IDA. The information is presented as an implementation detail for the interested reader.

Table 7.4: List of matrix functions usage by IDA code modules

| | IDALS | IDABBDPRE |
|---------------|-------|-----------|
| SUNMatGetID | ✓ | |
| SUNMatDestroy | | ✓ |
| SUNMatZero | ✓ | ✓ |
| SUNMatSpace | | † |

The matrix functions listed in Table 7.2 with a † symbol are optionally used, in that these are only called if they are implemented in the SUNMATRIX module that is being used (i.e. their function pointers are non-NULL). The matrix functions listed in Table 7.2 that are *not* used by IDA are: `SUNMatCopy`, `SUNMatClone`, `SUNMatScaleAdd`, `SUNMatScaleAddI` and `SUNMatMatvec`. Therefore a user-supplied SUNMATRIX module for IDA could omit these functions.

7.2 The SUNMatrix_Dense implementation

The dense implementation of the SUNMATRIX module provided with SUNDIALS, `SUNMATRIX_DENSE`, defines the *content* field of `SUNMatrix` to be the following structure:

```
struct _SUNMatrixContent_Dense {
    sunindextype M;
    sunindextype N;
    realtype *data;
    sunindextype ldata;
    realtype **cols;
};
```

These entries of the *content* field contain the following information:

M - number of rows

N - number of columns

data - pointer to a contiguous block of `realtype` variables. The elements of the dense matrix are stored columnwise, i.e. the (i,j) -th element of a dense SUNMATRIX **A** (with $0 \leq i < M$ and $0 \leq j < N$) may be accessed via `data[j*M+i]`.

ldata - length of the data array ($= M \cdot N$).

cols - array of pointers. `cols[j]` points to the first element of the j -th column of the matrix in the array **data**. The (i,j) -th element of a dense SUNMATRIX **A** (with $0 \leq i < M$ and $0 \leq j < N$) may be accessed via `cols[j][i]`.

The header file to include when using this module is `sunmatrix/sunmatrix_dense.h`. The SUNMATRIX_DENSE module is accessible from all SUNDIALS solvers *without* linking to the `libsundials_sunmatrixdense` module library.

7.2.1 SUNMatrix_Dense accessor macros

The following macros are provided to access the content of a SUNMATRIX_DENSE matrix. The prefix **SM_** in the names denotes that these macros are for *SUNMatrix* implementations, and the suffix **_D** denotes that these are specific to the *dense* version.

- **SM_CONTENT_D**

This macro gives access to the contents of the dense SUNMatrix.

The assignment `A_cont = SM_CONTENT_D(A)` sets **A_cont** to be a pointer to the dense SUNMatrix content structure.

Implementation:

```
#define SM_CONTENT_D(A)      ( (SUNMatrixContent_Dense)(A->content) )
```

- **SM_ROWS_D**, **SM_COLUMNS_D**, and **SM_LDATA_D**

These macros give individual access to various lengths relevant to the content of a dense SUNMatrix.

These may be used either to retrieve or to set these values. For example, the assignment `A_rows = SM_ROWS_D(A)` sets **A_rows** to be the number of rows in the matrix **A**. Similarly, the assignment `SM_COLUMNS_D(A) = A_cols` sets the number of columns in **A** to equal **A_cols**.

Implementation:

```
#define SM_ROWS_D(A)         ( SM_CONTENT_D(A)->M )
#define SM_COLUMNS_D(A)      ( SM_CONTENT_D(A)->N )
#define SM_LDATA_D(A)        ( SM_CONTENT_D(A)->ldata )
```

- **SM_DATA_D** and **SM_COLS_D**

These macros give access to the **data** and **cols** pointers for the matrix entries.

The assignment `A_data = SM_DATA_D(A)` sets **A_data** to be a pointer to the first component of the data array for the dense SUNMatrix **A**. The assignment `SM_DATA_D(A) = A_data` sets the data array of **A** to be **A_data** by storing the pointer **A_data**.

Similarly, the assignment `A_cols = SM_COLS_D(A)` sets **A_cols** to be a pointer to the array of column pointers for the dense SUNMatrix **A**. The assignment `SM_COLS_D(A) = A_cols` sets the column pointer array of **A** to be **A_cols** by storing the pointer **A_cols**.

Implementation:

```
#define SM_DATA_D(A)         ( SM_CONTENT_D(A)->data )
#define SM_COLS_D(A)         ( SM_CONTENT_D(A)->cols )
```

- `SM_COLUMN_D` and `SM_ELEMENT_D`

These macros give access to the individual columns and entries of the data array of a dense `SUNMatrix`.

The assignment `col_j = SM_COLUMN_D(A,j)` sets `col_j` to be a pointer to the first entry of the j -th column of the $M \times N$ dense matrix `A` (with $0 \leq j < N$). The type of the expression `SM_COLUMN_D(A,j)` is `realtype *`. The pointer returned by the call `SM_COLUMN_D(A,j)` can be treated as an array which is indexed from 0 to $M - 1$.

The assignments `SM_ELEMENT_D(A,i,j) = a_ij` and `a_ij = SM_ELEMENT_D(A,i,j)` reference the (i,j) -th element of the $M \times N$ dense matrix `A` (with $0 \leq i < M$ and $0 \leq j < N$).

Implementation:

```
#define SM_COLUMN_D(A,j)    ( (SM_CONTENT_D(A)->cols)[j] )
#define SM_ELEMENT_D(A,i,j) ( (SM_CONTENT_D(A)->cols)[j][i] )
```

7.2.2 SUNMatrix_Dense functions

The `SUNMATRIX_DENSE` module defines dense implementations of all matrix operations listed in Table 7.2. Their names are obtained from those in Table 7.2 by appending the suffix `_Dense` (e.g. `SUNMatCopy_Dense`). All the standard matrix operations listed in 7.2 with the suffix `_Dense` appended are callable via the FORTRAN 2003 interface by prepending an ‘F’ (e.g. `FSUNMatCopy_Dense`).

The module `SUNMATRIX_DENSE` provides the following additional user-callable routines:

`SUNDenseMatrix`

Prototype `SUNMatrix SUNDenseMatrix(sunindextype M, sunindextype N)`

Description This constructor function creates and allocates memory for a dense `SUNMatrix`. Its arguments are the number of rows, `M`, and columns, `N`, for the dense matrix.

F2003 Name This function is callable as `FSUNDenseMatrix` when using the Fortran 2003 interface module.

`SUNDenseMatrix_Print`

Prototype `void SUNDenseMatrix_Print(SUNMatrix A, FILE* outfile)`

Description This function prints the content of a dense `SUNMatrix` to the output stream specified by `outfile`. Note: `stdout` or `stderr` may be used as arguments for `outfile` to print directly to standard output or standard error, respectively.

`SUNDenseMatrix_Rows`

Prototype `sunindextype SUNDenseMatrix_Rows(SUNMatrix A)`

Description This function returns the number of rows in the dense `SUNMatrix`.

F2003 Name This function is callable as `FSUNDenseMatrix_Rows` when using the Fortran 2003 interface module.

`SUNDenseMatrix_Columns`

Prototype `sunindextype SUNDenseMatrix_Columns(SUNMatrix A)`

Description This function returns the number of columns in the dense `SUNMatrix`.

F2003 Name This function is callable as `FSUNDenseMatrix_Columns` when using the Fortran 2003 interface module.

SUNDenseMatrix_LData

Prototype `sunindextype SUNDenseMatrix_LData(SUNMatrix A)`

Description This function returns the length of the data array for the dense **SUNMatrix**.

F2003 Name This function is callable as **FSUNDenseMatrix_LData** when using the Fortran 2003 interface module.

SUNDenseMatrix_Data

Prototype `realtype* SUNDenseMatrix_Data(SUNMatrix A)`

Description This function returns a pointer to the data array for the dense **SUNMatrix**.

F2003 Name This function is callable as **FSUNDenseMatrix_Data** when using the Fortran 2003 interface module.

SUNDenseMatrix_Cols

Prototype `realtype** SUNDenseMatrix_Cols(SUNMatrix A)`

Description This function returns a pointer to the cols array for the dense **SUNMatrix**.

SUNDenseMatrix_Column

Prototype `realtype* SUNDenseMatrix_Column(SUNMatrix A, sunindextype j)`

Description This function returns a pointer to the first entry of the *j*th column of the dense **SUNMatrix**. The resulting pointer should be indexed over the range 0 to $M - 1$.

F2003 Name This function is callable as **FSUNDenseMatrix_Column** when using the Fortran 2003 interface module.

Notes

- When looping over the components of a dense **SUNMatrix** *A*, the most efficient approaches are to:
 - First obtain the component array via `A_data = SM_DATA_D(A)` or `A_data = SUNDenseMatrix_Data(A)` and then access `A_data[i]` within the loop.
 - First obtain the array of column pointers via `A_cols = SM_COLS_D(A)` or `A_cols = SUNDenseMatrix_Cols(A)`, and then access `A_cols[j][i]` within the loop.
 - Within a loop over the columns, access the column pointer via `A_colj = SUNDenseMatrix_Column(A, j)` and then to access the entries within that column using `A_colj[i]` within the loop.

All three of these are more efficient than using `SM_ELEMENT_D(A, i, j)` within a double loop.

- Within the **SUNMatMatvec_Dense** routine, internal consistency checks are performed to ensure that the matrix is called with consistent **NVECTOR** implementations. These are currently limited to: **NVECTOR_SERIAL**, **NVECTOR_OPENMP**, and **NVECTOR_PTHREADS**. As additional compatible vector implementations are added to **SUNDIALS**, these will be included within this compatibility check.

**7.2.3 SUNMatrix_Dense Fortran interfaces**

The **SUNMATRIX_DENSE** module provides a **FORTTRAN 2003** module as well as **FORTTRAN 77** style interface functions for use from **FORTTRAN** applications.

FORTTRAN 2003 interface module

The `fsunmatrix_dense_mod` FORTRAN module defines interfaces to most `SUNMATRIX_DENSE` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNDenseMatrix` is interfaced as `FSUNDenseMatrix`.

The FORTRAN 2003 `SUNMATRIX_DENSE` interface module can be accessed with the `use` statement, i.e. `use fsunmatrix_dense_mod`, and linking to the library `libsundials.fsunmatrixdense_mod.lib` in addition to the C library. For details on where the library and module file `fsunmatrix_dense_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials.fsunmatrixdense_mod` library.

FORTTRAN 77 interface functions

For solvers that include a FORTRAN interface module, the `SUNMATRIX_DENSE` module also includes the FORTRAN-callable function `FSUNDenseMatInit(code, M, N, ier)` to initialize this `SUNMATRIX_DENSE` module for a given SUNDIALS solver. Here `code` is an integer input solver id (1 for `CVODE`, 2 for `IDA`, 3 for `KINSOL`, 4 for `ARKODE`); `M` and `N` are the corresponding dense matrix construction arguments (declared to match C type `long int`); and `ier` is an error return flag equal to 0 for success and -1 for failure. Both `code` and `ier` are declared to match C type `int`. Additionally, when using `ARKODE` with a non-identity mass matrix, the FORTRAN-callable function `FSUNDenseMassMatInit(M, N, ier)` initializes this `SUNMATRIX_DENSE` module for storing the mass matrix.

7.3 The SUNMatrix_Band implementation

The banded implementation of the `SUNMATRIX` module provided with SUNDIALS, `SUNMATRIX_BAND`, defines the *content* field of `SUNMatrix` to be the following structure:

```
struct _SUNMatrixContent_Band {
    sunindextype M;
    sunindextype N;
    sunindextype mu;
    sunindextype ml;
    sunindextype s_mu;
    sunindextype ldim;
    realtype *data;
    sunindextype ldata;
    realtype **cols;
};
```

A diagram of the underlying data representation in a banded matrix is shown in Figure 7.1. A more complete description of the parts of this *content* field is given below:

- `M` - number of rows
- `N` - number of columns ($N = M$)
- `mu` - upper half-bandwidth, $0 \leq \mu < N$
- `ml` - lower half-bandwidth, $0 \leq ml < N$
- `s_mu` - storage upper bandwidth, $\mu \leq s_mu < N$. The LU decomposition routines in the associated `SUNLINSOL_BAND` and `SUNLINSOL_LAPACKBAND` modules write the LU factors into the storage for `A`. The upper triangular factor `U`, however, may have an upper bandwidth as big as $\min(N-1, \mu+ml)$ because of partial pivoting. The `s_mu` field holds the upper half-bandwidth allocated for `A`.
- `ldim` - leading dimension ($ldim \geq s_mu+ml+1$)




Figure 7.1: Diagram of the storage for the SUNMATRIX_BAND module. Here A is an $N \times N$ band matrix with upper and lower half-bandwidths μ and m , respectively. The rows and columns of A are numbered from 0 to $N - 1$ and the (i, j) -th element of A is denoted $A(i, j)$. The greyed out areas of the underlying component storage are used by the associated SUNLINSOL_BAND linear solver.

data - pointer to a contiguous block of **realtype** variables. The elements of the banded matrix are stored columnwise (i.e. columns are stored one on top of the other in memory). Only elements within the specified half-bandwidths are stored. **data** is a pointer to **ldata** contiguous locations which hold the elements within the band of A .

ldata - length of the data array ($= \text{ldim} \cdot N$)

cols - array of pointers. **cols**[j] is a pointer to the uppermost element within the band in the j -th column. This pointer may be treated as an array indexed from **s_mu** - μ (to access the uppermost element within the band in the j -th column) to **s_mu** + m (to access the lowest element within the band in the j -th column). Indices from 0 to **s_mu** - μ - 1 give access to extra storage elements required by the LU decomposition function. Finally, **cols**[j][$i - j + \text{s_mu}$] is the (i, j) -th element with $j - \mu \leq i \leq j + m$.

The header file to include when using this module is **sunmatrix/sunmatrix.band.h**. The SUNMATRIX_BAND module is accessible from all SUNDIALS solvers *without* linking to the **libsundials_sunmatrixband** module library.

7.3.1 SUNMatrix_Band accessor macros

The following macros are provided to access the content of a SUNMATRIX_BAND matrix. The prefix `SM_` in the names denotes that these macros are for *SUNMatrix* implementations, and the suffix `_B` denotes that these are specific to the *banded* version.

- `SM_CONTENT_B`

This routine gives access to the contents of the banded SUNMatrix.

The assignment `A_cont = SM_CONTENT_B(A)` sets `A_cont` to be a pointer to the banded SUNMatrix content structure.

Implementation:

```
#define SM_CONTENT_B(A)      ( (SUNMatrixContent_Band)(A->content) )
```

- `SM_ROWS_B`, `SM_COLUMNS_B`, `SM_UBAND_B`, `SM_LBAND_B`, `SM_SUBAND_B`, `SM_LDIM_B`, and `SM_LDATA_B`

These macros give individual access to various lengths relevant to the content of a banded SUNMatrix.

These may be used either to retrieve or to set these values. For example, the assignment `A_rows = SM_ROWS_B(A)` sets `A_rows` to be the number of rows in the matrix `A`. Similarly, the assignment `SM_COLUMNS_B(A) = A_cols` sets the number of columns in `A` to equal `A_cols`.

Implementation:

```
#define SM_ROWS_B(A)         ( SM_CONTENT_B(A)->M )
#define SM_COLUMNS_B(A)      ( SM_CONTENT_B(A)->N )
#define SM_UBAND_B(A)        ( SM_CONTENT_B(A)->mu )
#define SM_LBAND_B(A)        ( SM_CONTENT_B(A)->m1 )
#define SM_SUBAND_B(A)       ( SM_CONTENT_B(A)->s_mu )
#define SM_LDIM_B(A)         ( SM_CONTENT_B(A)->ldim )
#define SM_LDATA_B(A)        ( SM_CONTENT_B(A)->ldata )
```

- `SM_DATA_B` and `SM_COLS_B`

These macros give access to the `data` and `cols` pointers for the matrix entries.

The assignment `A_data = SM_DATA_B(A)` sets `A_data` to be a pointer to the first component of the data array for the banded SUNMatrix `A`. The assignment `SM_DATA_B(A) = A_data` sets the data array of `A` to be `A_data` by storing the pointer `A_data`.

Similarly, the assignment `A_cols = SM_COLS_B(A)` sets `A_cols` to be a pointer to the array of column pointers for the banded SUNMatrix `A`. The assignment `SM_COLS_B(A) = A_cols` sets the column pointer array of `A` to be `A_cols` by storing the pointer `A_cols`.

Implementation:

```
#define SM_DATA_B(A)         ( SM_CONTENT_B(A)->data )
#define SM_COLS_B(A)         ( SM_CONTENT_B(A)->cols )
```

- `SM_COLUMN_B`, `SM_COLUMN_ELEMENT_B`, and `SM_ELEMENT_B`

These macros give access to the individual columns and entries of the data array of a banded SUNMatrix.

The assignments `SM_ELEMENT_B(A,i,j) = a_ij` and `a_ij = SM_ELEMENT_B(A,i,j)` reference the (i,j) -th element of the $N \times N$ band matrix `A`, where $0 \leq i, j \leq N - 1$. The location (i,j) should further satisfy $j - \mu \leq i \leq j + m1$.

The assignment `col_j = SM_COLUMN_B(A,j)` sets `col_j` to be a pointer to the diagonal element of the j -th column of the $N \times N$ band matrix `A`, $0 \leq j \leq N - 1$. The type of the expression

`SM_COLUMN_B(A,j)` is `realtype *`. The pointer returned by the call `SM_COLUMN_B(A,j)` can be treated as an array which is indexed from $-\mu$ to m_l .

The assignments `SM_COLUMN_ELEMENT_B(col_j,i,j) = a_ij` and `a_ij = SM_COLUMN_ELEMENT_B(col_j,i,j)` reference the (i,j) -th entry of the band matrix `A` when used in conjunction with `SM_COLUMN_B` to reference the j -th column through `col_j`. The index (i,j) should satisfy $j-\mu \leq i \leq j+m_l$.

Implementation:

```
#define SM_COLUMN_B(A,j)      ( ((SM_CONTENT_B(A)->cols)[j])+SM_SUBBAND_B(A) )

#define SM_COLUMN_ELEMENT_B(col_j,i,j) (col_j[(i)-(j)])

#define SM_ELEMENT_B(A,i,j)
    ( (SM_CONTENT_B(A)->cols)[j][(i)-(j)+SM_SUBBAND_B(A)] )
```

7.3.2 SUNMatrix_Band functions

The `SUNMATRIX_BAND` module defines banded implementations of all matrix operations listed in Table 7.2. Their names are obtained from those in Table 7.2 by appending the suffix `_Band` (e.g. `SUNMatCopy_Band`). All the standard matrix operations listed in 7.2 with the suffix `_Band` appended are callable via the FORTRAN 2003 interface by prepending an ‘F’ (e.g. `FSUNMatCopy_Band`).

The module `SUNMATRIX_BAND` provides the following additional user-callable routines:

SUNBandMatrix

Prototype `SUNMatrix SUNBandMatrix(sunindextype N, sunindextype mu, sunindextype ml)`

Description This constructor function creates and allocates memory for a banded `SUNMatrix`. Its arguments are the matrix size, `N`, and the upper and lower half-bandwidths of the matrix, `mu` and `ml`. The stored upper bandwidth is set to `mu+ml` to accommodate subsequent factorization in the `SUNLINSOL_BAND` and `SUNLINSOL_LAPACKBAND` modules.

F2003 Name This function is callable as `FSUNBandMatrix` when using the Fortran 2003 interface module.

SUNBandMatrixStorage

Prototype `SUNMatrix SUNBandMatrixStorage(sunindextype N, sunindextype mu, sunindextype ml, sunindextype smu)`

Description This constructor function creates and allocates memory for a banded `SUNMatrix`. Its arguments are the matrix size, `N`, the upper and lower half-bandwidths of the matrix, `mu` and `ml`, and the stored upper bandwidth, `smu`. When creating a band `SUNMatrix`, this value should be

- at least $\min(N-1, \mu+m_l)$ if the matrix will be used by the `SUNLINSOL_BAND` module;
- exactly equal to `mu+ml` if the matrix will be used by the `SUNLINSOL_LAPACKBAND` module;
- at least `mu` if used in some other manner.

Note: it is strongly recommended that users call the default constructor, `SUNBandMatrix`, in all standard use cases. This advanced constructor is used internally within SUNDIALS solvers, and is provided to users who require banded matrices for non-default purposes.

SUNBandMatrix_Print

Prototype `void SUNBandMatrix_Print(SUNMatrix A, FILE* outfile)`

Description This function prints the content of a banded **SUNMatrix** to the output stream specified by **outfile**. Note: **stdout** or **stderr** may be used as arguments for **outfile** to print directly to standard output or standard error, respectively.

SUNBandMatrix_Rows

Prototype `sunindextype SUNBandMatrix_Rows(SUNMatrix A)`

Description This function returns the number of rows in the banded **SUNMatrix**.

F2003 Name This function is callable as **FSUNBandMatrix_Rows** when using the Fortran 2003 interface module.

SUNBandMatrix_Columns

Prototype `sunindextype SUNBandMatrix_Columns(SUNMatrix A)`

Description This function returns the number of columns in the banded **SUNMatrix**.

F2003 Name This function is callable as **FSUNBandMatrix_Columns** when using the Fortran 2003 interface module.

SUNBandMatrix_LowerBandwidth

Prototype `sunindextype SUNBandMatrix_LowerBandwidth(SUNMatrix A)`

Description This function returns the lower half-bandwidth of the banded **SUNMatrix**.

F2003 Name This function is callable as **FSUNBandMatrix_LowerBandwidth** when using the Fortran 2003 interface module.

SUNBandMatrix_UpperBandwidth

Prototype `sunindextype SUNBandMatrix_UpperBandwidth(SUNMatrix A)`

Description This function returns the upper half-bandwidth of the banded **SUNMatrix**.

F2003 Name This function is callable as **FSUNBandMatrix_UpperBandwidth** when using the Fortran 2003 interface module.

SUNBandMatrix_StoredUpperBandwidth

Prototype `sunindextype SUNBandMatrix_StoredUpperBandwidth(SUNMatrix A)`

Description This function returns the stored upper half-bandwidth of the banded **SUNMatrix**.

F2003 Name This function is callable as **FSUNBandMatrix_StoredUpperBandwidth** when using the Fortran 2003 interface module.

SUNBandMatrix_LDim

Prototype `sunindextype SUNBandMatrix_LDim(SUNMatrix A)`

Description This function returns the length of the leading dimension of the banded **SUNMatrix**.

F2003 Name This function is callable as **FSUNBandMatrix_LDim** when using the Fortran 2003 interface module.

SUNBandMatrix_Data

Prototype `realtype* SUNBandMatrix_Data(SUNMatrix A)`

Description This function returns a pointer to the data array for the banded SUNMatrix.

F2003 Name This function is callable as `FSUNBandMatrix_Data` when using the Fortran 2003 interface module.

SUNBandMatrix_Cols

Prototype `realtype** SUNBandMatrix_Cols(SUNMatrix A)`

Description This function returns a pointer to the cols array for the banded SUNMatrix.

SUNBandMatrix_Column

Prototype `realtype* SUNBandMatrix_Column(SUNMatrix A, sunindextype j)`

Description This function returns a pointer to the diagonal entry of the j -th column of the banded SUNMatrix. The resulting pointer should be indexed over the range $-\mu$ to $m1$.

F2003 Name This function is callable as `FSUNBandMatrix_Column` when using the Fortran 2003 interface module.

Notes

- When looping over the components of a banded SUNMatrix A, the most efficient approaches are to:
 - First obtain the component array via `A_data = SM_DATA_B(A)` or `A_data = SUNBandMatrix_Data(A)` and then access `A_data[i]` within the loop.
 - First obtain the array of column pointers via `A_cols = SM_COLS_B(A)` or `A_cols = SUNBandMatrix_Cols(A)`, and then access `A_cols[j][i]` within the loop.
 - Within a loop over the columns, access the column pointer via `A_colj = SUNBandMatrix_Column(A,j)` and then to access the entries within that column using `SM_COLUMN_ELEMENT_B(A_colj,i,j)`.

All three of these are more efficient than using `SM_ELEMENT_B(A,i,j)` within a double loop.

- Within the `SUNMatMatvec_Band` routine, internal consistency checks are performed to ensure that the matrix is called with consistent NVECTOR implementations. These are currently limited to: `NVECTOR_SERIAL`, `NVECTOR_OPENMP`, and `NVECTOR_PTHREADS`. As additional compatible vector implementations are added to SUNDIALS, these will be included within this compatibility check.

**7.3.3 SUNMatrix_Band Fortran interfaces**

The `SUNMATRIX_BAND` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `fsunmatrix_band_mod` FORTRAN module defines interfaces to most `SUNMATRIX_BAND` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNBandMatrix` is interfaced as `FSUNBandMatrix`.

The FORTRAN 2003 `SUNMATRIX_BAND` interface module can be accessed with the `use` statement, i.e. `use fsunmatrix_band_mod`, and linking to the library `libsundials_fsunmatrixband_mod.lib` in

addition to the C library. For details on where the library and module file `fsunmatrix.band.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials.fsunmatrixband.mod` library.

FORTRAN 77 interface functions

For solvers that include a FORTRAN interface module, the `SUNMATRIX_BAND` module also includes the FORTRAN-callable function `FSUNBandMatInit(code, N, mu, ml, ier)` to initialize this `SUNMATRIX_BAND` module for a given SUNDIALS solver. Here `code` is an integer input solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, 4 for ARKODE); `N`, `mu`, and `ml` are the corresponding band matrix construction arguments (declared to match C type `long int`); and `ier` is an error return flag equal to 0 for success and -1 for failure. Both `code` and `ier` are declared to match C type `int`. Additionally, when using ARKODE with a non-identity mass matrix, the FORTRAN-callable function `FSUNBandMassMatInit(N, mu, ml, ier)` initializes this `SUNMATRIX_BAND` module for storing the mass matrix.

7.4 The SUNMatrix_Sparse implementation

The sparse implementation of the `SUNMATRIX` module provided with SUNDIALS, `SUNMATRIX_SPARSE`, is designed to work with either *compressed-sparse-column* (CSC) or *compressed-sparse-row* (CSR) sparse matrix formats. To this end, it defines the *content* field of `SUNMatrix` to be the following structure:

```
struct _SUNMatrixContent_Sparse {
    sunindextype M;
    sunindextype N;
    sunindextype NNZ;
    sunindextype NP;
    realtype *data;
    int sparsetype;
    sunindextype *indexvals;
    sunindextype *indexptrs;
    /* CSC indices */
    sunindextype **rowvals;
    sunindextype **colptrs;
    /* CSR indices */
    sunindextype **colvals;
    sunindextype **rowptrs;
};
```

A diagram of the underlying data representation for a CSC matrix is shown in Figure 7.2 (the CSR format is similar). A more complete description of the parts of this *content* field is given below:

| | |
|-------------------------|---|
| <code>M</code> | - number of rows |
| <code>N</code> | - number of columns |
| <code>NNZ</code> | - maximum number of nonzero entries in the matrix (allocated length of <code>data</code> and <code>indexvals</code> arrays) |
| <code>NP</code> | - number of index pointers (e.g. number of column pointers for CSC matrix). For CSC matrices <code>NP = N</code> , and for CSR matrices <code>NP = M</code> . This value is set automatically based the input for <code>sparsetype</code> . |
| <code>data</code> | - pointer to a contiguous block of <code>realtype</code> variables (of length <code>NNZ</code>), containing the values of the nonzero entries in the matrix |
| <code>sparsetype</code> | - type of the sparse matrix (<code>CSC_MAT</code> or <code>CSR_MAT</code>) |
| <code>indexvals</code> | - pointer to a contiguous block of <code>int</code> variables (of length <code>NNZ</code>), containing the row indices (if CSC) or column indices (if CSR) of each nonzero matrix entry held in <code>data</code> |

indexptrs - pointer to a contiguous block of **int** variables (of length **NP+1**). For CSC matrices each entry provides the index of the first column entry into the **data** and **indexvals** arrays, e.g. if **indexptr[3]=7**, then the first nonzero entry in the fourth column of the matrix is located in **data[7]**, and is located in row **indexvals[7]** of the matrix. The last entry contains the total number of nonzero values in the matrix and hence points one past the end of the active data in the **data** and **indexvals** arrays. For CSR matrices, each entry provides the index of the first row entry into the **data** and **indexvals** arrays.

The following pointers are added to the **SlsMat** type for user convenience, to provide a more intuitive interface to the CSC and CSR sparse matrix data structures. They are set automatically when creating a sparse SUNMATRIX, based on the sparse matrix storage type.

rowvals - pointer to **indexvals** when **sparsetype** is **CSC_MAT**, otherwise set to **NULL**.

colptrs - pointer to **indexptrs** when **sparsetype** is **CSC_MAT**, otherwise set to **NULL**.

colvals - pointer to **indexvals** when **sparsetype** is **CSR_MAT**, otherwise set to **NULL**.

rowptrs - pointer to **indexptrs** when **sparsetype** is **CSR_MAT**, otherwise set to **NULL**.

For example, the 5×4 CSC matrix

$$\begin{bmatrix} 0 & 3 & 1 & 0 \\ 3 & 0 & 0 & 2 \\ 0 & 7 & 0 & 0 \\ 1 & 0 & 0 & 9 \\ 0 & 0 & 0 & 5 \end{bmatrix}$$

could be stored in this structure as either

```
M = 5;
N = 4;
NNZ = 8;
NP = N;
data = {3.0, 1.0, 3.0, 7.0, 1.0, 2.0, 9.0, 5.0};
sparsetype = CSC_MAT;
indexvals = {1, 3, 0, 2, 0, 1, 3, 4};
indexptrs = {0, 2, 4, 5, 8};
```

or

```
M = 5;
N = 4;
NNZ = 10;
NP = N;
data = {3.0, 1.0, 3.0, 7.0, 1.0, 2.0, 9.0, 5.0, *, *};
sparsetype = CSC_MAT;
indexvals = {1, 3, 0, 2, 0, 1, 3, 4, *, *};
indexptrs = {0, 2, 4, 5, 8};
```

where the first has no unused space, and the second has additional storage (the entries marked with ***** may contain any values). Note in both cases that the final value in **indexptrs** is 8, indicating the total number of nonzero entries in the matrix.

Similarly, in CSR format, the same matrix could be stored as

```
M = 5;
N = 4;
NNZ = 8;
NP = N;
data = {3.0, 1.0, 3.0, 2.0, 7.0, 1.0, 9.0, 5.0};
sparsetype = CSR_MAT;
indexvals = {1, 2, 0, 3, 1, 0, 3, 3};
indexptrs = {0, 2, 4, 5, 7, 8};
```




Figure 7.2: Diagram of the storage for a compressed-sparse-column matrix. Here A is an $M \times N$ sparse matrix with storage for up to NNZ nonzero entries (the allocated length of both `data` and `indexvals`). The entries in `indexvals` may assume values from 0 to $M - 1$, corresponding to the row index (zero-based) of each nonzero value. The entries in `data` contain the values of the nonzero entries, with the row i , column j entry of A (again, zero-based) denoted as $A(i, j)$. The `indexptrs` array contains $N + 1$ entries; the first N denote the starting index of each column within the `indexvals` and `data` arrays, while the final entry points one past the final nonzero entry. Here, although NNZ values are allocated, only `nz` are actually filled in; the greyed-out portions of `data` and `indexvals` indicate extra allocated space.

The header file to include when using this module is `sunmatrix/sunmatrix.sparse.h`. The `SUNMATRIX_SPARSE` module is accessible from all SUNDIALS solvers *without* linking to the `libsundials_sunmatrixsparse` module library.

7.4.1 SUNMatrix_Sparse accessor macros

The following macros are provided to access the content of a `SUNMATRIX_SPARSE` matrix. The prefix `SM_` in the names denotes that these macros are for *SUNMatrix* implementations, and the suffix `_S` denotes that these are specific to the *sparse* version.

- `SM_CONTENT_S`

This routine gives access to the contents of the sparse `SUNMatrix`.

The assignment `A_cont = SM_CONTENT_S(A)` sets `A_cont` to be a pointer to the sparse `SUNMatrix` content structure.

Implementation:

```
#define SM_CONTENT_S(A)      ( (SUNMatrixContent_Sparse)(A->content) )
```

- `SM_ROWS_S`, `SM_COLUMNS_S`, `SM_NNZ_S`, `SM_NP_S`, and `SM_SPARSETYPE_S`

These macros give individual access to various lengths relevant to the content of a sparse `SUNMatrix`.

These may be used either to retrieve or to set these values. For example, the assignment `A_rows = SM_ROWS_S(A)` sets `A_rows` to be the number of rows in the matrix `A`. Similarly, the assignment `SM_COLUMNS_S(A) = A_cols` sets the number of columns in `A` to equal `A_cols`.

Implementation:

```
#define SM_ROWS_S(A)          ( SM_CONTENT_S(A)->M )
#define SM_COLUMNS_S(A)       ( SM_CONTENT_S(A)->N )
#define SM_NNZ_S(A)           ( SM_CONTENT_S(A)->NNZ )
#define SM_NP_S(A)            ( SM_CONTENT_S(A)->NP )
#define SM_SPARSETYPE_S(A)    ( SM_CONTENT_S(A)->sparsetype )
```

- `SM_DATA_S`, `SM_INDEXVALS_S`, and `SM_INDEXPTRS_S`

These macros give access to the `data` and index arrays for the matrix entries.

The assignment `A_data = SM_DATA_S(A)` sets `A_data` to be a pointer to the first component of the data array for the sparse `SUNMatrix` `A`. The assignment `SM_DATA_S(A) = A_data` sets the data array of `A` to be `A_data` by storing the pointer `A_data`.

Similarly, the assignment `A_indexvals = SM_INDEXVALS_S(A)` sets `A_indexvals` to be a pointer to the array of index values (i.e. row indices for a CSC matrix, or column indices for a CSR matrix) for the sparse `SUNMatrix` `A`. The assignment `A_indexptrs = SM_INDEXPTRS_S(A)` sets `A_indexptrs` to be a pointer to the array of index pointers (i.e. the starting indices in the data/indexvals arrays for each row or column in CSR or CSC formats, respectively).

Implementation:

```
#define SM_DATA_S(A)          ( SM_CONTENT_S(A)->data )
#define SM_INDEXVALS_S(A)     ( SM_CONTENT_S(A)->indexvals )
#define SM_INDEXPTRS_S(A)     ( SM_CONTENT_S(A)->indexptrs )
```

The `SUNMATRIX_SPARSE` module defines sparse implementations of all matrix operations listed in Table 7.2. Their names are obtained from those in Table 7.2 by appending the suffix `_Sparse` (e.g. `SUNMatCopy_Sparse`). All the standard matrix operations listed in 7.2 with the suffix `_Sparse` appended are callable via the FORTRAN 2003 interface by prepending an ‘F’ (e.g. `FSUNMatCopy_Sparse`).

The module `SUNMATRIX_SPARSE` provides the following additional user-callable routines:

[illegible]

| | |
|------------|--|
| F2003 Name | This function is callable as <code>FSUNSparseMatrix</code> when using the Fortran 2003 interface module. |
|------------|--|

[illegible]

Requirements:

- `A` must have type `SUNMATRIX_DENSE`;
- `droptol` must be non-negative;
- `sparsetype` must be either `CSC_MAT` or `CSR_MAT`.

The function returns `NULL` if any requirements are violated, or if the matrix storage request cannot be satisfied.

| | |
|------------|---|
| F2003 Name | This function is callable as <code>FSUNSparseFromDenseMatrix</code> when using the Fortran 2003 interface module. |
|------------|---|

[illegible]

Requirements:

- `A` must have type `SUNMATRIX_BAND`;
- `droptol` must be non-negative;
- `sparsetype` must be either `CSC_MAT` or `CSR_MAT`.

The function returns `NULL` if any requirements are violated, or if the matrix storage request cannot be satisfied.

| | |
|------------|--|
| F2003 Name | This function is callable as <code>FSUNSparseFromBandMatrix</code> when using the Fortran 2003 interface module. |
|------------|--|

SUNSparseMatrix_Realloc

Prototype `int SUNSparseMatrix_Realloc(SUNMatrix A)`

Description This function reallocates internal storage arrays in a sparse matrix so that the resulting sparse matrix has no wasted space (i.e. the space allocated for nonzero entries equals the actual number of nonzeros, `indexptrs[NP]`). Returns 0 on success and 1 on failure (e.g. if the input matrix is not sparse).

F2003 Name This function is callable as `FSUNSparseMatrix_Realloc` when using the Fortran 2003 interface module.

SUNSparseMatrix_Reallocate

Prototype `int SUNSparseMatrix_Reallocate(SUNMatrix A, sunindextype NNZ)`

Description This function reallocates internal storage arrays in a sparse matrix so that the resulting sparse matrix has storage for a specified number of nonzeros. Returns 0 on success and 1 on failure (e.g. if the input matrix is not sparse or if NNZ is negative).

F2003 Name This function is callable as `FSUNSparseMatrix_Reallocate` when using the Fortran 2003 interface module.

SUNSparseMatrix_Print

Prototype `void SUNSparseMatrix_Print(SUNMatrix A, FILE* outfile)`

Description This function prints the content of a sparse `SUNMatrix` to the output stream specified by `outfile`. Note: `stdout` or `stderr` may be used as arguments for `outfile` to print directly to standard output or standard error, respectively.

SUNSparseMatrix_Rows

Prototype `sunindextype SUNSparseMatrix_Rows(SUNMatrix A)`

Description This function returns the number of rows in the sparse `SUNMatrix`.

F2003 Name This function is callable as `FSUNSparseMatrix_Rows` when using the Fortran 2003 interface module.

SUNSparseMatrix_Columns

Prototype `sunindextype SUNSparseMatrix_Columns(SUNMatrix A)`

Description This function returns the number of columns in the sparse `SUNMatrix`.

F2003 Name This function is callable as `FSUNSparseMatrix_Columns` when using the Fortran 2003 interface module.

SUNSparseMatrix_NNZ

Prototype `sunindextype SUNSparseMatrix_NNZ(SUNMatrix A)`

Description This function returns the number of entries allocated for nonzero storage for the sparse matrix `SUNMatrix`.

F2003 Name This function is callable as `FSUNSparseMatrix_NNZ` when using the Fortran 2003 interface module.

SUNSparseMatrix_NP

Prototype `sunindextype SUNSparseMatrix_NP(SUNMatrix A)`

Description This function returns the number of columns/rows for the sparse **SUNMatrix**, depending on whether the matrix uses **CSC/CSR** format, respectively. The **indexptrs** array has **NP+1** entries.

F2003 Name This function is callable as **FSUNSparseMatrix_NP** when using the Fortran 2003 interface module.

SUNSparseMatrix_SparseType

Prototype `int SUNSparseMatrix_SparseType(SUNMatrix A)`

Description This function returns the storage type (**CSR_MAT** or **CSC_MAT**) for the sparse **SUNMatrix**.

F2003 Name This function is callable as **FSUNSparseMatrix_SparseType** when using the Fortran 2003 interface module.

SUNSparseMatrix_Data

Prototype `realtype* SUNSparseMatrix_Data(SUNMatrix A)`

Description This function returns a pointer to the data array for the sparse **SUNMatrix**.

F2003 Name This function is callable as **FSUNSparseMatrix_Data** when using the Fortran 2003 interface module.

SUNSparseMatrix_IndexValues

Prototype `sunindextype* SUNSparseMatrix_IndexValues(SUNMatrix A)`

Description This function returns a pointer to index value array for the sparse **SUNMatrix**: for **CSR** format this is the column index for each nonzero entry, for **CSC** format this is the row index for each nonzero entry.

F2003 Name This function is callable as **FSUNSparseMatrix_IndexValues** when using the Fortran 2003 interface module.

SUNSparseMatrix_IndexPointers

Prototype `sunindextype* SUNSparseMatrix_IndexPointers(SUNMatrix A)`

Description This function returns a pointer to the index pointer array for the sparse **SUNMatrix**: for **CSR** format this is the location of the first entry of each row in the **data** and **indexvalues** arrays, for **CSC** format this is the location of the first entry of each column.

F2003 Name This function is callable as **FSUNSparseMatrix_IndexPointers** when using the Fortran 2003 interface module.



Within the **SUNMatMatvec_Sparse** routine, internal consistency checks are performed to ensure that the matrix is called with consistent **NVECTOR** implementations. These are currently limited to: **NVECTOR_SERIAL**, **NVECTOR_OPENMP**, and **NVECTOR_PTHREADS**. As additional compatible vector implementations are added to **SUNDIALS**, these will be included within this compatibility check.

7.4.3 SUNMatrix_Sparse Fortran interfaces

The **SUNMATRIX_SPARSE** module provides a **FORTRAN 2003** module as well as **FORTRAN 77** style interface functions for use from **FORTRAN** applications.

FORTRAN 2003 interface module

The `fsunmatrix_sparse_mod` FORTRAN module defines interfaces to most SUNMATRIX_SPARSE C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNSparseMatrix` is interfaced as `FSUNSparseMatrix`.

The FORTRAN 2003 SUNMATRIX_SPARSE interface module can be accessed with the `use` statement, i.e. `use fsunmatrix_sparse_mod`, and linking to the library `libsundials_fsunmatrixsparse_mod.lib` in addition to the C library. For details on where the library and module file `fsunmatrix_sparse_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunmatrixsparse_mod` library.

FORTRAN 77 interface functions

For solvers that include a Fortran interface module, the SUNMATRIX_SPARSE module also includes the Fortran-callable function `FSUNSparseMatInit(code, M, N, NNZ, sparsetype, ier)` to initialize this SUNMATRIX_SPARSE module for a given SUNDIALS solver. Here `code` is an integer input for the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, 4 for ARKODE); `M`, `N` and `NNZ` are the corresponding sparse matrix construction arguments (declared to match C type `long int`); `sparsetype` is an integer flag indicating the sparse storage type (0 for CSC, 1 for CSR); and `ier` is an error return flag equal to 0 for success and -1 for failure. Each of `code`, `sparsetype` and `ier` are declared so as to match C type `int`. Additionally, when using ARKODE with a non-identity mass matrix, the Fortran-callable function `FSUNSparseMassMatInit(M, N, NNZ, sparsetype, ier)` initializes this SUNMATRIX_SPARSE module for storing the mass matrix.

Chapter 8

Description of the SUNLinearSolver module

For problems that involve the solution of linear systems of equations, the SUNDIALS packages operate using generic linear solver modules defined through the SUNLINSOL API. This allows SUNDIALS packages to utilize any valid SUNLINSOL implementation that provides a set of required functions. These functions can be divided into three categories. The first are the core linear solver functions. The second group consists of “set” routines to supply the linear solver object with functions provided by the SUNDIALS package, or for modification of solver parameters. The last group consists of “get” routines for retrieving artifacts (statistics, residual vectors, etc.) from the linear solver. All of these functions are defined in the header file `sundials/sundials_linearsolver.h`.

The implementations provided with SUNDIALS work in coordination with the SUNDIALS generic NVECTOR and SUNMATRIX modules to provide a set of compatible data structures and solvers for the solution of linear systems using direct or iterative (matrix-based or matrix-free) methods. Moreover, advanced users can provide a customized **SUNLinearSolver** implementation to any SUNDIALS package, particularly in cases where they provide their own NVECTOR and/or SUNMATRIX modules.

Historically, the SUNDIALS packages have been designed to specifically leverage the use of either *direct linear solvers* or matrix-free, *scaled, preconditioned, iterative linear solvers*. However, matrix-based iterative linear solvers are also supported.

The iterative linear solvers packaged with SUNDIALS leverage scaling and preconditioning, as applicable, to balance error between solution components and to accelerate convergence of the linear solver. To this end, instead of solving the linear system $Ax = b$ directly, these apply the underlying iterative algorithm to the transformed system

$$\tilde{A}\tilde{x} = \tilde{b} \tag{8.1}$$

where

$$\begin{aligned} \tilde{A} &= S_1 P_1^{-1} A P_2^{-1} S_2^{-1}, \\ \tilde{b} &= S_1 P_1^{-1} b, \\ \tilde{x} &= S_2 P_2 x, \end{aligned} \tag{8.2}$$

and where

- P_1 is the left preconditioner,
- P_2 is the right preconditioner,
- S_1 is a diagonal matrix of scale factors for $P_1^{-1}b$,
- S_2 is a diagonal matrix of scale factors for P_2x .

SUNDIALS packages request that iterative linear solvers stop based on the 2-norm of the scaled pre-conditioned residual meeting a prescribed tolerance

$$\|\tilde{b} - \tilde{A}\tilde{x}\|_2 < \text{tol}.$$

When provided an iterative SUNLINSOL implementation that does not support the scaling matrices S_1 and S_2 , SUNDIALS' packages will adjust the value of tol accordingly (see §8.4.2 for more details). In this case, they instead request that iterative linear solvers stop based on the criteria

$$\|P_1^{-1}b - P_1^{-1}Ax\|_2 < \text{tol}.$$

We note that the corresponding adjustments to tol in this case are non-optimal, in that they cannot balance error between specific entries of the solution x , only the aggregate error in the overall solution vector.

We further note that not all of the SUNDIALS-provided iterative linear solvers support the full range of the above options (e.g., separate left/right preconditioning), and that some of the SUNDIALS packages only utilize a subset of these options. Further details on these exceptions are described in the documentation for each SUNLINSOL implementation, or for each SUNDIALS package.

For users interested in providing their own SUNLINSOL module, the following section presents the SUNLINSOL API and its implementation beginning with the definition of SUNLINSOL functions in sections 8.1.1 – 8.1.3. This is followed by the definition of functions supplied to a linear solver implementation in section 8.1.4. A table of linear solver return codes is given in section 8.1.5. The `SUNLinearSolver` type and the generic SUNLINSOL module are defined in section 8.1.6. The section 8.2 discusses compatibility between the SUNDIALS-provided SUNLINSOL modules and SUNMATRIX modules. Section 8.3 lists the requirements for supplying a custom SUNLINSOL module and discusses some intended use cases. Users wishing to supply their own SUNLINSOL module are encouraged to use the SUNLINSOL implementations provided with SUNDIALS as a template for supplying custom linear solver modules. The SUNLINSOL functions required by this SUNDIALS package as well as other package specific details are given in section 8.4. The remaining sections of this chapter present the SUNLINSOL modules provided with SUNDIALS.

8.1 The SUNLinearSolver API

The SUNLINSOL API defines several linear solver operations that enable SUNDIALS packages to utilize any SUNLINSOL implementation that provides the required functions. These functions can be divided into three categories. The first are the core linear solver functions. The second group of functions consists of set routines to supply the linear solver with functions provided by the SUNDIALS time integrators and to modify solver parameters. The final group consists of get routines for retrieving linear solver statistics. All of these functions are defined in the header file `sundials/sundials_linearsolver.h`.

8.1.1 SUNLinearSolver core functions

The core linear solver functions consist of four required routines to get the linear solver type (`SUNLinSolGetType`), initialize the linear solver object once all solver-specific options have been set (`SUNLinSolInitialize`), set up the linear solver object to utilize an updated matrix A (`SUNLinSolSetup`), and solve the linear system $Ax = b$ (`SUNLinSolSolve`). The remaining routine for destruction of the linear solver object (`SUNLinSolFree`) is optional.

| |
|-------------------------------|
| <code>SUNLinSolGetType</code> |
|-------------------------------|

Call `type = SUNLinSolGetType(LS);`

Description The *required* function `SUNLinSolGetType` returns the type identifier for the linear solver LS. It is used to determine the solver type (direct, iterative, or matrix-iterative) from the abstract `SUNLinearSolver` interface.

Arguments `LS` (`SUNLinearSolver`) a `SUNLINSOL` object.

Return value The return value `type` (of type `int`) will be one of the following:

- `SUNLINEARSOLVER_DIRECT` – 0, the `SUNLINSOL` module requires a matrix, and computes an ‘exact’ solution to the linear system defined by that matrix.
- `SUNLINEARSOLVER_ITERATIVE` – 1, the `SUNLINSOL` module does not require a matrix (though one may be provided), and computes an inexact solution to the linear system using a matrix-free iterative algorithm. That is it solves the linear system defined by the package-supplied `ATimes` routine (see `SUNLinSolSetATimes` below), even if that linear system differs from the one encoded in the matrix object (if one is provided). As the solver computes the solution only inexactly (or may diverge), the linear solver should check for solution convergence/accuracy as appropriate.
- `SUNLINEARSOLVER_MATRIX_ITERATIVE` – 2, the `SUNLINSOL` module requires a matrix, and computes an inexact solution to the linear system defined by that matrix using an iterative algorithm. That is it solves the linear system defined by the matrix object even if that linear system differs from that encoded by the package-supplied `ATimes` routine. As the solver computes the solution only inexactly (or may diverge), the linear solver should check for solution convergence/accuracy as appropriate.

Notes See section 8.3.1 for more information on intended use cases corresponding to the linear solver type.

`SUNLinSolInitialize`

Call `retval = SUNLinSolInitialize(LS);`

Description The *required* function `SUNLinSolInitialize` performs linear solver initialization (assuming that all solver-specific options have been set).

Arguments `LS` (`SUNLinearSolver`) a `SUNLINSOL` object.

Return value This should return zero for a successful call, and a negative value for a failure, ideally returning one of the generic error codes listed in Table 8.1.

`SUNLinSolSetup`

Call `retval = SUNLinSolSetup(LS, A);`

Description The *required* function `SUNLinSolSetup` performs any linear solver setup needed, based on an updated system `SUNMATRIX A`. This may be called frequently (e.g., with a full Newton method) or infrequently (for a modified Newton method), based on the type of integrator and/or nonlinear solver requesting the solves.

Arguments `LS` (`SUNLinearSolver`) a `SUNLINSOL` object.
`A` (`SUNMatrix`) a `SUNMATRIX` object.

Return value This should return zero for a successful call, a positive value for a recoverable failure and a negative value for an unrecoverable failure, ideally returning one of the generic error codes listed in Table 8.1.

`SUNLinSolSolve`

Call `retval = SUNLinSolSolve(LS, A, x, b, tol);`

Description The *required* function `SUNLinSolSolve` solves a linear system $Ax = b$.

Arguments `LS` (`SUNLinearSolver`) a `SUNLINSOL` object.
`A` (`SUNMatrix`) a `SUNMATRIX` object.

| | |
|--------------|---|
| | x (N_Vector) a NVECTOR object containing the initial guess for the solution of the linear system, and the solution to the linear system upon return. |
| | b (N_Vector) a NVECTOR object containing the linear system right-hand side. |
| | tol (realtype) the desired linear solver tolerance. |
| Return value | This should return zero for a successful call, a positive value for a recoverable failure and a negative value for an unrecoverable failure, ideally returning one of the generic error codes listed in Table 8.1. |
| Notes | <p>Direct solvers: can ignore the tol argument.</p> <p>Matrix-free solvers: (those that identify as SUNLINEARSOLVER_ITERATIVE) can ignore the SUNMATRIX input A, and should instead rely on the matrix-vector product function supplied through the routine SUNLinSolSetATimes.</p> <p>Iterative solvers: (those that identify as SUNLINEARSOLVER_ITERATIVE or SUNLINEARSOLVER_MATRIX_ITERATIVE) should attempt to solve to the specified tolerance tol in a weighted 2-norm. If the solver does not support scaling then it should just use a 2-norm.</p> |

SUNLinSolFree

| | |
|--------------|--|
| Call | <code>retval = SUNLinSolFree(LS);</code> |
| Description | The <i>optional</i> function SUNLinSolFree frees memory allocated by the linear solver. |
| Arguments | LS (SUNLinearSolver) a SUNLINSOL object. |
| Return value | This should return zero for a successful call and a negative value for a failure. |

8.1.2 SUNLinearSolver set functions

The following set functions are used to supply linear solver modules with functions defined by the SUNDIALS packages and to modify solver parameters. Only the routine for setting the matrix-vector product routine is required, and that is only for matrix-free linear solver modules. Otherwise, all other set functions are optional. **SUNLINSOL** implementations that do not provide the functionality for any optional routine should leave the corresponding function pointer **NULL** instead of supplying a dummy routine.

SUNLinSolSetATimes

| | |
|--------------|---|
| Call | <code>retval = SUNLinSolSetATimes(LS, A_data, ATimes);</code> |
| Description | <p>The function SUNLinSolSetATimes is <i>required for matrix-free linear solvers</i>; otherwise it is optional.</p> <p>This routine provides an ATimesFn function pointer, as well as a void* pointer to a data structure used by this routine, to a linear solver object. SUNDIALS packages will call this function to set the matrix-vector product function to either a solver-provided difference-quotient via vector operations or a user-supplied solver-specific routine.</p> |
| Arguments | <p>LS (SUNLinearSolver) a SUNLINSOL object.</p> <p>A_data (void*) data structure passed to ATimes.</p> <p>ATimes (ATimesFn) function pointer implementing the matrix-vector product routine.</p> |
| Return value | This routine should return zero for a successful call, and a negative value for a failure, ideally returning one of the generic error codes listed in Table 8.1. |

SUNLinSolSetPreconditioner

- Call** `retval = SUNLinSolSetPreconditioner(LS, Pdata, Pset, Psol);`
- Description** The *optional* function `SUNLinSolSetPreconditioner` provides `PSetupFn` and `PSolveFn` function pointers that implement the preconditioner solves P_1^{-1} and P_2^{-1} from equations (8.1)-(8.2). This routine will be called by a SUNDIALS package, which will provide translation between the generic `Pset` and `Psol` calls and the package- or user-supplied routines.
- Arguments** `LS` (`SUNLinearSolver`) a SUNLINSOL object.
`Pdata` (`void*`) data structure passed to both `Pset` and `Psol`.
`Pset` (`PSetupFn`) function pointer implementing the preconditioner setup.
`Psol` (`PSolveFn`) function pointer implementing the preconditioner solve.
- Return value** This routine should return zero for a successful call, and a negative value for a failure, ideally returning one of the generic error codes listed in Table 8.1.

SUNLinSolSetScalingVectors

- Call** `retval = SUNLinSolSetScalingVectors(LS, s1, s2);`
- Description** The *optional* function `SUNLinSolSetScalingVectors` provides left/right scaling vectors for the linear system solve. Here, `s1` and `s2` are `NVECTOR` of positive scale factors containing the diagonal of the matrices S_1 and S_2 from equations (8.1)-(8.2), respectively. Neither of these vectors need to be tested for positivity, and a `NULL` argument for either indicates that the corresponding scaling matrix is the identity.
- Arguments** `LS` (`SUNLinearSolver`) a SUNLINSOL object.
`s1` (`N_Vector`) diagonal of the matrix S_1
`s2` (`N_Vector`) diagonal of the matrix S_2
- Return value** This routine should return zero for a successful call, and a negative value for a failure, ideally returning one of the generic error codes listed in Table 8.1.

8.1.3 SUNLinearSolver get functions

The following get functions allow SUNDIALS packages to retrieve results from a linear solve. All routines are optional.

SUNLinSolNumIters

- Call** `its = SUNLinSolNumIters(LS);`
- Description** The *optional* function `SUNLinSolNumIters` should return the number of linear iterations performed in the last ‘solve’ call.
- Arguments** `LS` (`SUNLinearSolver`) a SUNLINSOL object.
- Return value** `int` containing the number of iterations

SUNLinSolResNorm

- Call** `rnorm = SUNLinSolResNorm(LS);`
- Description** The *optional* function `SUNLinSolResNorm` should return the final residual norm from the last ‘solve’ call.
- Arguments** `LS` (`SUNLinearSolver`) a SUNLINSOL object.
- Return value** `realtype` containing the final residual norm

SUNLinSolResid

Call `rvec = SUNLinSolResid(LS);`

Description If an iterative method computes the preconditioned initial residual and returns with a successful solve without performing any iterations (i.e., either the initial guess or the preconditioner is sufficiently accurate), then this *optional* routine may be called by the SUNDIALS package. This routine should return the NVECTOR containing the preconditioned initial residual vector.

Arguments `LS` (`SUNLinearSolver`) a SUNLINSOL object.

Return value `N_Vector` containing the final residual vector

Notes Since `N_Vector` is actually a pointer, and the results are not modified, this routine should *not* require additional memory allocation. If the SUNLINSOL object does not retain a vector for this purpose, then this function pointer should be set to `NULL` in the implementation.

SUNLinSolLastFlag

Call `lflag = SUNLinSolLastFlag(LS);`

Description The *optional* function `SUNLinSolLastFlag` should return the last error flag encountered within the linear solver. This is not called by the SUNDIALS packages directly; it allows the user to investigate linear solver issues after a failed solve.

Arguments `LS` (`SUNLinearSolver`) a SUNLINSOL object.

Return value `long int` containing the most recent error flag

SUNLinSolSpace

Call `retval = SUNLinSolSpace(LS, &lrw, &liw);`

Description The *optional* function `SUNLinSolSpace` should return the storage requirements for the linear solver `LS`.

Arguments `LS` (`SUNLinearSolver`) a SUNLINSOL object.

`lrw` (`long int*`) the number of realtype words stored by the linear solver.

`liw` (`long int*`) the number of integer words stored by the linear solver.

Return value This should return zero for a successful call, and a negative value for a failure, ideally returning one of the generic error codes listed in Table 8.1.

Notes This function is advisory only, for use in determining a user's total space requirements.

8.1.4 Functions provided by SUNDIALS packages

To interface with the SUNLINSOL modules, the SUNDIALS packages supply a variety of routines for evaluating the matrix-vector product, and setting up and applying the preconditioner. These package-provided routines translate between the user-supplied ODE, DAE, or nonlinear systems and the generic interfaces to the linear systems of equations that result in their solution. The types for functions provided to a SUNLINSOL module are defined in the header file `sundials/sundials_iterative.h`, and are described below.

ATimesFn

Definition `typedef int (*ATimesFn)(void *A_data, N_Vector v, N_Vector z);`

Purpose These functions compute the action of a matrix on a vector, performing the operation $z = Av$. Memory for `z` should already be allocated prior to calling this function. The vector `v` should be left unchanged.

Arguments **A_data** is a pointer to client data, the same as that supplied to `SUNLinSolSetATimes`.
v is the input vector to multiply.
z is the output vector computed.

Return value This routine should return 0 if successful and a non-zero value if unsuccessful.

PSetupFn

Definition `typedef int (*PSetupFn)(void *P_data)`

Purpose These functions set up any requisite problem data in preparation for calls to the corresponding `PSolveFn`.

Arguments **P_data** is a pointer to client data, the same pointer as that supplied to the routine `SUNLinSolSetPreconditioner`.

Return value This routine should return 0 if successful and a non-zero value if unsuccessful.

PSolveFn

Definition `typedef int (*PSolveFn)(void *P_data, N_Vector r, N_Vector z, realtype tol, int lr)`

Purpose These functions solve the preconditioner equation $Pz = r$ for the vector z . Memory for z should already be allocated prior to calling this function. The parameter **P_data** is a pointer to any information about P which the function needs in order to do its job (set up by the corresponding `PSetupFn`). The parameter **lr** is input, and indicates whether P is to be taken as the left preconditioner or the right preconditioner: **lr** = 1 for left and **lr** = 2 for right. If preconditioning is on one side only, **lr** can be ignored. If the preconditioner is iterative, then it should strive to solve the preconditioner equation so that

$$\|Pz - r\|_{\text{wrms}} < \text{tol}$$

where the weight vector for the WRMS norm may be accessed from the main package memory structure. The vector **r** should not be modified by the `PSolveFn`.

Arguments **P_data** is a pointer to client data, the same pointer as that supplied to the routine `SUNLinSolSetPreconditioner`.

r is the right-hand side vector for the preconditioner system.

z is the solution vector for the preconditioner system.

tol is the desired tolerance for an iterative preconditioner.

lr is flag indicating whether the routine should perform left (1) or right (2) preconditioning.

Return value This routine should return 0 if successful and a non-zero value if unsuccessful. On a failure, a negative return value indicates an unrecoverable condition, while a positive value indicates a recoverable one, in which the calling routine may reattempt the solution after updating preconditioner data.

8.1.5 SUNLinearSolver return codes

The functions provided to SUNLINSOL modules by each SUNDIALS package, and functions within the SUNDIALS-provided SUNLINSOL implementations utilize a common set of return codes, shown in Table 8.1. These adhere to a common pattern: 0 indicates success, a positive value corresponds to a recoverable failure, and a negative value indicates a non-recoverable failure. Aside from this pattern, the actual values of each error code are primarily to provide additional information to the user in case of a linear solver failure.

Table 8.1: Description of the SUNLinearSolver error codes

| Name | Value | Description |
|--------------------------|-------|--|
| SUNLS_SUCCESS | 0 | successful call or converged solve |
| SUNLS_MEM_NULL | -1 | the memory argument to the function is NULL |
| SUNLS_ILL_INPUT | -2 | an illegal input has been provided to the function |
| SUNLS_MEM_FAIL | -3 | failed memory access or allocation |
| SUNLS_ATHES_FAIL_UNREC | -4 | an unrecoverable failure occurred in the ATHES routine |
| SUNLS_PSET_FAIL_UNREC | -5 | an unrecoverable failure occurred in the Pset routine |
| SUNLS_PSOLVE_FAIL_UNREC | -6 | an unrecoverable failure occurred in the Psolve routine |
| SUNLS_PACKAGE_FAIL_UNREC | -7 | an unrecoverable failure occurred in an external linear solver package |
| SUNLS_GS_FAIL | -8 | a failure occurred during Gram-Schmidt orthogonalization (SUNLINSOL_SPGMR/SUNLINSOL_SPFGMR) |
| SUNLS_QRSOL_FAIL | -9 | a singular R matrix was encountered in a QR factorization (SUNLINSOL_SPGMR/SUNLINSOL_SPFGMR) |
| SUNLS_RES_REDUCED | 1 | an iterative solver reduced the residual, but did not converge to the desired tolerance |
| SUNLS_CONV_FAIL | 2 | an iterative solver did not converge (and the residual was not reduced) |
| SUNLS_ATHES_FAIL_REC | 3 | a recoverable failure occurred in the ATHES routine |
| SUNLS_PSET_FAIL_REC | 4 | a recoverable failure occurred in the Pset routine |
| SUNLS_PSOLVE_FAIL_REC | 5 | a recoverable failure occurred in the Psolve routine |
| SUNLS_PACKAGE_FAIL_REC | 6 | a recoverable failure occurred in an external linear solver package |
| SUNLS_QRFACT_FAIL | 7 | a singular matrix was encountered during a QR factorization (SUNLINSOL_SPGMR/SUNLINSOL_SPFGMR) |
| SUNLS_LUFACT_FAIL | 8 | a singular matrix was encountered during a LU factorization (SUNLINSOL_DENSE/SUNLINSOL_BAND) |

8.1.6 The generic SUNLinearSolver module

SUNDIALS packages interact with specific SUNLINSOL implementations through the generic SUNLINSOL module on which all other SUNLINSOL implementations are built. The `SUNLinearSolver` type is a pointer to a structure containing an implementation-dependent *content* field, and an *ops* field. The type `SUNLinearSolver` is defined as

```
typedef struct _generic_SUNLinearSolver *SUNLinearSolver;

struct _generic_SUNLinearSolver {
    void *content;
    struct _generic_SUNLinearSolver_Ops *ops;
};
```

where the `_generic_SUNLinearSolver_Ops` structure is a list of pointers to the various actual linear solver operations provided by a specific implementation. The `_generic_SUNLinearSolver_Ops` structure is defined as

```
struct _generic_SUNLinearSolver_Ops {
    SUNLinearSolver_Type (*gettype)(SUNLinearSolver);
```

```

int      (*setatimes)(SUNLinearSolver, void*, ATimesFn);
int      (*setpreconditioner)(SUNLinearSolver, void*,
                             PSetupFn, PSolveFn);
int      (*setscalingvectors)(SUNLinearSolver,
                             N_Vector, N_Vector);
int      (*initialize)(SUNLinearSolver);
int      (*setup)(SUNLinearSolver, SUNMatrix);
int      (*solve)(SUNLinearSolver, SUNMatrix, N_Vector,
                 N_Vector, realtype);
int      (*numiters)(SUNLinearSolver);
realtype (*resnorm)(SUNLinearSolver);
long int (*lastflag)(SUNLinearSolver);
int      (*space)(SUNLinearSolver, long int*, long int*);
N_Vector (*resid)(SUNLinearSolver);
int      (*free)(SUNLinearSolver);
};

```

The generic SUNLINSOL module defines and implements the linear solver operations defined in Sections 8.1.1-8.1.3. These routines are in fact only wrappers to the linear solver operations defined by a particular SUNLINSOL implementation, which are accessed through the *ops* field of the `SUNLinearSolver` structure. To illustrate this point we show below the implementation of a typical linear solver operation from the generic SUNLINSOL module, namely `SUNLinSolInitialize`, which initializes a SUNLINSOL object for use after it has been created and configured, and returns a flag denoting a successful/failed operation:

```

int SUNLinSolInitialize(SUNLinearSolver S)
{
    return ((int) S->ops->initialize(S));
}

```

8.2 Compatibility of SUNLinearSolver modules

We note that not all SUNLINSOL types are compatible with all SUNMATRIX and NVECTOR types provided with SUNDIALS. In Table 8.2 we show the matrix-based linear solvers available as SUNLINSOL modules, and the compatible matrix implementations. Recall that Table 4.1 shows the compatibility between all SUNLINSOL modules and vector implementations.

Table 8.2: SUNDIALS matrix-based linear solvers and matrix implementations that can be used for each.

| Linear Solver Interface | Dense Matrix | Banded Matrix | Sparse Matrix | User Supplied |
|-------------------------|--------------|---------------|---------------|---------------|
| Dense | ✓ | | | ✓ |
| Band | | ✓ | | ✓ |
| LapackDense | ✓ | | | ✓ |
| LapackBand | | ✓ | | ✓ |
| KLU | | | ✓ | ✓ |
| SUPERLUMT | | | ✓ | ✓ |
| User supplied | ✓ | ✓ | ✓ | ✓ |

8.3 Implementing a custom SUNLinearSolver module

A particular implementation of the SUNLINSOL module must:

- Specify the *content* field of the `SUNLinearSolver` object.
- Define and implement a minimal subset of the linear solver operations. See the section 8.4 to determine which SUNLINSOL operations are required for this SUNDIALS package.

Note that the names of these routines should be unique to that implementation in order to permit using more than one SUNLINSOL module (each with different `SUNLinearSolver` internal data representations) in the same code.

- Define and implement user-callable constructor and destructor routines to create and free a `SUNLinearSolver` with the new *content* field and with *ops* pointing to the new linear solver operations.

We note that the function pointers for all unsupported optional routines should be set to `NULL` in the *ops* structure. This allows the SUNDIALS package that is using the SUNLINSOL object to know that the associated functionality is not supported.

Additionally, a SUNLINSOL implementation *may* do the following:

- Define and implement additional user-callable “set” routines acting on the `SUNLinearSolver`, e.g., for setting various configuration options to tune the linear solver to a particular problem.
- Provide additional user-callable “get” routines acting on the `SUNLinearSolver` object, e.g., for returning various solve statistics.

8.3.1 Intended use cases

The SUNLINSOL (and SUNMATRIX) APIs are designed to require a minimal set of routines to ease interfacing with custom or third-party linear solver libraries. External solvers provide similar routines with the necessary functionality and thus will require minimal effort to wrap within custom SUNMATRIX and SUNLINSOL implementations. Sections 7.1 and 8.4 include a list of the required set of routines that compatible SUNMATRIX and SUNLINSOL implementations must provide. As SUNDIALS packages utilize generic SUNLINSOL modules allowing for user-supplied `SUNLinearSolver` implementations, there exists a wide range of possible linear solver combinations. Some intended use cases for both the SUNDIALS-provided and user-supplied SUNLINSOL modules are discussed in the following sections.

Direct linear solvers

Direct linear solver modules require a matrix and compute an ‘exact’ solution to the linear system *defined by the matrix*. Multiple matrix formats and associated direct linear solvers are supplied with SUNDIALS through different SUNMATRIX and SUNLINSOL implementations. SUNDIALS packages strive to amortize the high cost of matrix construction by reusing matrix information for multiple nonlinear iterations. As a result, each package’s linear solver interface recomputes Jacobian information as infrequently as possible.

Alternative matrix storage formats and compatible linear solvers that are not currently provided by, or interfaced with, SUNDIALS can leverage this infrastructure with minimal effort. To do so, a user must implement custom SUNMATRIX and SUNLINSOL wrappers for the desired matrix format and/or linear solver following the APIs described in Chapters 7 and 8. *This user-supplied SUNLINSOL module must then self-identify as having `SUNLINEARSOLVER_DIRECT` type.*

Matrix-free iterative linear solvers

Matrix-free iterative linear solver modules do not require a matrix and compute an inexact solution to the linear system *defined by the package-supplied `ATimes` routine*. SUNDIALS supplies multiple scaled, preconditioned iterative linear solver (spils) SUNLINSOL modules that support scaling to allow users to handle non-dimensionalization (as best as possible) within each SUNDIALS package and retain variables and define equations as desired in their applications. For linear solvers that do not support left/right scaling, the tolerance supplied to the linear solver is adjusted to compensate (see section 8.4.2 for

more details); however, this use case may be non-optimal and cannot handle situations where the magnitudes of different solution components or equations vary dramatically within a single problem.

To utilize alternative linear solvers that are not currently provided by, or interfaced with, SUNDIALS a user must implement a custom SUNLINSOL wrapper for the linear solver following the API described in Chapter 8. *This user-supplied SUNLINSOL module must then self-identify as having SUNLINEARSOLVER_ITERATIVE type.*

Matrix-based iterative linear solvers (reusing A)

Matrix-based iterative linear solver modules require a matrix and compute an inexact solution to the linear system *defined by the matrix*. This matrix will be updated infrequently and reused across multiple solves to amortize cost of matrix construction. As in the direct linear solver case, only wrappers for the matrix and linear solver in SUNMATRIX and SUNLINSOL implementations need to be created to utilize a new linear solver. *This user-supplied SUNLINSOL module must then self-identify as having SUNLINEARSOLVER_MATRIX_ITERATIVE type.*

At present, SUNDIALS has one example problem that uses this approach for wrapping a structured-grid matrix, linear solver, and preconditioner from the *hypr* library that may be used as a template for other customized implementations (see `examples/arkode/CXX_parhyp/ark_heat2D_hypr.cpp`).

Matrix-based iterative linear solvers (current A)

For users who wish to utilize a matrix-based iterative linear solver module where the matrix is *purely for preconditioning* and the linear system is *defined by the package-supplied ATimes routine*, we envision two current possibilities.

The preferred approach is for users to employ one of the SUNDIALS spils SUNLINSOL implementations (SUNLINSOL_SPGMR, SUNLINSOL_SPFGRM, SUNLINSOL_SPBCGS, SUNLINSOL_SPTFQMR, or SUNLINSOL_PCG) as the outer solver. The creation and storage of the preconditioner matrix, and interfacing with the corresponding linear solver, can be handled through a package's preconditioner 'setup' and 'solve' functionality (see §4.5.8.2) without creating SUNMATRIX and SUNLINSOL implementations. This usage mode is recommended primarily because the SUNDIALS-provided spils modules support the scaling as described above.

A second approach supported by the linear solver APIs is as follows. If the SUNLINSOL implementation is matrix-based, *self-identifies as having SUNLINEARSOLVER_ITERATIVE type*, and *also provides a non-NULL SUNLinSolSetATimes routine*, then each SUNDIALS package will call that routine to attach its package-specific matrix-vector product routine to the SUNLINSOL object. The SUNDIALS package will then call the SUNLINSOL-provided SUNLinSolSetup routine (infrequently) to update matrix information, but will provide current matrix-vector products to the SUNLINSOL implementation through the package-supplied ATimesFn routine.

8.4 IDA SUNLinearSolver interface

Table 8.3 below lists the SUNLINSOL module linear solver functions used within the IDALS interface. As with the SUNMATRIX module, we emphasize that the IDA user does not need to know detailed usage of linear solver functions by the IDA code modules in order to use IDA. The information is presented as an implementation detail for the interested reader.

The linear solver functions listed below are marked with ✓ to indicate that they are required, or with † to indicate that they are only called if they are non-NULL in the SUNLINSOL implementation that is being used. Note:

1. Although IDALS does not call `SUNLinSolLastFlag` directly, this routine is available for users to query linear solver issues directly.
2. Although IDALS does not call `SUNLinSolFree` directly, this routine should be available for users to call when cleaning up from a simulation.

Table 8.3: List of linear solver function usage in the IDALS interface

| | DIRECT | ITERATIVE | MATRIX_ITERATIVE |
|--------------------------------|--------|-----------|------------------|
| SUNLinSolGetType | ✓ | ✓ | ✓ |
| SUNLinSolSetATimes | † | ✓ | † |
| SUNLinSolSetPreconditioner | † | † | † |
| SUNLinSolSetScalingVectors | † | † | † |
| SUNLinSolInitialize | ✓ | ✓ | ✓ |
| SUNLinSolSetup | ✓ | ✓ | ✓ |
| SUNLinSolSolve | ✓ | ✓ | ✓ |
| SUNLinSolNumIters | | ✓ | ✓ |
| SUNLinSolResid | | ✓ | ✓ |
| ¹ SUNLinSolLastFlag | | | |
| ² SUNLinSolFree | | | |
| SUNLinSolSpace | † | † | † |

Since there are a wide range of potential SUNLINSOL use cases, the following subsections describe some details of the IDALS interface, in the case that interested users wish to develop custom SUNLINSOL modules.

8.4.1 Lagged matrix information

If the SUNLINSOL object self-identifies as having type `SUNLINEARSOLVER_DIRECT` or `SUNLINEARSOLVER_MATRIX_ITERATIVE`, then the SUNLINSOL object solves a linear system *defined* by a `SUNMATRIX` object. CVLS will update the matrix information infrequently according to the strategies outlined in §2.1. When solving a linear system $J\bar{x} = b$, it is likely that the value $\bar{\alpha}$ used to construct J differs from the current value of α in the BDF method, since J is updated infrequently. Therefore, after calling the SUNLINSOL-provided `SUNLinSolSolve` routine, we test whether $\alpha/\bar{\alpha} \neq 1$, and if this is the case we scale the solution \bar{x} to obtain the desired linear system solution x via

$$x = \frac{2}{1 + \alpha/\bar{\alpha}} \bar{x}. \quad (8.3)$$

For values of $\alpha/\bar{\alpha}$ that are “close” to 1, this rescaling approximately solves the original linear system.

8.4.2 Iterative linear solver tolerance

If the SUNLINSOL object self-identifies as having type `SUNLINEARSOLVER_ITERATIVE` or `SUNLINEARSOLVER_MATRIX_ITERATIVE` then IDALS will set the input tolerance `delta` as described in §2.1. However, if the iterative linear solver does not support scaling matrices (i.e., the `SUNLinSolSetScalingVectors` routine is `NULL`), then IDALS will attempt to adjust the linear solver tolerance to account for this lack of functionality. To this end, the following assumptions are made:

1. All solution components have similar magnitude; hence the error weight vector W used in the WRMS norm (see §2.1) should satisfy the assumption

$$W_i \approx W_{mean}, \quad \text{for } i = 0, \dots, n-1.$$

2. The SUNLINSOL object uses a standard 2-norm to measure convergence.

Since IDA uses identical left and right scaling matrices, $S_1 = S_2 = S = \text{diag}(W)$, then the linear solver convergence requirement is converted as follows (using the notation from equations (8.1)-(8.2)):

$$\begin{aligned}
 & \left\| \tilde{b} - \tilde{A}\tilde{x} \right\|_2 < \text{tol} \\
 \Leftrightarrow & \left\| SP_1^{-1}b - SP_1^{-1}Ax \right\|_2 < \text{tol} \\
 \Leftrightarrow & \sum_{i=0}^{n-1} [W_i (P_1^{-1}(b - Ax))_i]^2 < \text{tol}^2 \\
 \Leftrightarrow & W_{mean}^2 \sum_{i=0}^{n-1} [(P_1^{-1}(b - Ax))_i]^2 < \text{tol}^2 \\
 \Leftrightarrow & \sum_{i=0}^{n-1} [(P_1^{-1}(b - Ax))_i]^2 < \left(\frac{\text{tol}}{W_{mean}} \right)^2 \\
 \Leftrightarrow & \left\| P_1^{-1}(b - Ax) \right\|_2 < \frac{\text{tol}}{W_{mean}}
 \end{aligned}$$

Therefore the tolerance scaling factor

$$W_{mean} = \|W\|_2 / \sqrt{n}$$

is computed and the scaled tolerance `delta` = `tol`/`Wmean` is supplied to the SUNLINSOL object.

8.5 The SUNLinearSolver_Dense implementation

This section describes the SUNLINSOL implementation for solving dense linear systems. The SUNLINSOL_DENSE module is designed to be used with the corresponding SUNMATRIX_DENSE matrix type, and one of the serial or shared-memory NVECTOR implementations (NVECTOR_SERIAL, NVECTOR_OPENMP, or NVECTOR_PTHREADS).

To access the SUNLINSOL_DENSE module, include the header file `sunlinsol/sunlinsol_dense.h`. We note that the SUNLINSOL_DENSE module is accessible from SUNDIALS packages *without* separately linking to the `libsundials_sunlinsoldense` module library.

8.5.1 SUNLinearSolver_Dense description

This solver is constructed to perform the following operations:

- The “setup” call performs a LU factorization with partial (row) pivoting ($\mathcal{O}(N^3)$ cost), $PA = LU$, where P is a permutation matrix, L is a lower triangular matrix with 1’s on the diagonal, and U is an upper triangular matrix. This factorization is stored in-place on the input SUNMATRIX_DENSE object A , with pivoting information encoding P stored in the `pivots` array.
- The “solve” call performs pivoting and forward and backward substitution using the stored `pivots` array and the LU factors held in the SUNMATRIX_DENSE object ($\mathcal{O}(N^2)$ cost).

8.5.2 SUNLinearSolver_Dense functions

The SUNLINSOL_DENSE module provides the following user-callable constructor for creating a SUNLinearSolver object.

| | |
|------------------------|---|
| SUNLinSol_Dense | |
| Call | <code>LS = SUNLinSol_Dense(y, A);</code> |
| Description | The function <code>SUNLinSol_Dense</code> creates and allocates memory for a dense <code>SUNLinearSolver</code> object. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver <code>A</code> (<code>SUNMatrix</code>) a <code>SUNMATRIX_DENSE</code> matrix template for cloning matrices needed within the solver |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>A</code> or <code>y</code> are incompatible then this routine will return <code>NULL</code> . |
| Notes | This routine will perform consistency checks to ensure that it is called with consistent <code>NVECTOR</code> and <code>SUNMATRIX</code> implementations. These are currently limited to the <code>SUNMATRIX_DENSE</code> matrix type and the <code>NVECTOR_SERIAL</code> , <code>NVECTOR_OPENMP</code> , and <code>NVECTOR_PTHREADS</code> vector types. As additional compatible matrix and vector implementations are added to <code>SUNDIALS</code> , these will be included within this compatibility check. |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNDenseLinearSolver</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_Dense</code> when using the Fortran 2003 interface module. |

The `SUNLINSOL_DENSE` module defines implementations of all “direct” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_Dense`
- `SUNLinSolInitialize_Dense` – this does nothing, since all consistency checks are performed at solver creation.
- `SUNLinSolSetup_Dense` – this performs the *LU* factorization.
- `SUNLinSolSolve_Dense` – this uses the *LU* factors and `pivots` array to perform the solve.
- `SUNLinSolLastFlag_Dense`
- `SUNLinSolSpace_Dense` – this only returns information for the storage *within* the solver object, i.e. storage for `N`, `last_flag`, and `pivots`.
- `SUNLinSolFree_Dense`

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

8.5.3 SUNLinearSolver_Dense Fortran interfaces

The `SUNLINSOL_DENSE` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `fsunlinsol_dense_mod` FORTRAN module defines interfaces to all `SUNLINSOL_DENSE` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_Dense` is interfaced as `FSUNLinSol_Dense`.

The FORTRAN 2003 `SUNLINSOL_DENSE` interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_dense_mod`, and linking to the library `libsundials_fsunlinsoldense_mod.lib` in

addition to the C library. For details on where the library and module file `fsunlinsol_dense_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials.fsunlinsoldense_mod` library.

FORTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the SUNLINSOL_DENSE module also includes a Fortran-callable function for creating a **SUNLinearSolver** object.

FSUNDENSELINSOLINIT

| | |
|--------------|--|
| Call | FSUNDENSELINSOLINIT(<i>code</i> , <i>ier</i>) |
| Description | The function FSUNDENSELINSOLINIT can be called for Fortran programs to create a dense SUNLinearSolver object. |
| Arguments | <i>code</i> (<i>int*</i>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). |
| Return value | <i>ier</i> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX objects have been initialized. |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_DENSE module includes a Fortran-callable function for creating a **SUNLinearSolver** mass matrix solver object.

FSUNMASSDENSELINSOLINIT

| | |
|--------------|---|
| Call | FSUNMASSDENSELINSOLINIT(<i>ier</i>) |
| Description | The function FSUNMASSDENSELINSOLINIT can be called for Fortran programs to create a dense SUNLinearSolver object for mass matrix linear systems. |
| Arguments | None |
| Return value | <i>ier</i> is a <i>int</i> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX mass-matrix objects have been initialized. |

8.5.4 SUNLinearSolver_Dense content

The SUNLINSOL_DENSE module defines the *content* field of a **SUNLinearSolver** as the following structure:

```
struct _SUNLinearSolverContent_Dense {
    sunindextype N;
    sunindextype *pivots;
    long int last_flag;
};
```

These entries of the *content* field contain the following information:

- N* - size of the linear system,
- pivots* - index array for partial pivoting in LU factorization,
- last_flag* - last error return flag from internal function evaluations.

8.6 The SUNLinearSolver_Band implementation

This section describes the SUNLINSOL implementation for solving banded linear systems. The SUNLINSOL_BAND module is designed to be used with the corresponding SUNMATRIX_BAND matrix type, and one of the serial or shared-memory NVECTOR implementations (NVECTOR_SERIAL, NVECTOR_OPENMP, or NVECTOR_PTHREADS).

To access the SUNLINSOL_BAND module, include the header file `sunlinsol/sunlinsol_band.h`. We note that the SUNLINSOL_BAND module is accessible from SUNDIALS packages *without* separately linking to the `libsundials_sunlinsolband` module library.

8.6.1 SUNLinearSolver_Band description

This solver is constructed to perform the following operations:

- The “setup” call performs a LU factorization with partial (row) pivoting, $PA = LU$, where P is a permutation matrix, L is a lower triangular matrix with 1’s on the diagonal, and U is an upper triangular matrix. This factorization is stored in-place on the input SUNMATRIX_BAND object A , with pivoting information encoding P stored in the `pivots` array.
- The “solve” call performs pivoting and forward and backward substitution using the stored `pivots` array and the LU factors held in the SUNMATRIX_BAND object.
- A must be allocated to accommodate the increase in upper bandwidth that occurs during factorization. More precisely, if A is a band matrix with upper bandwidth `mu` and lower bandwidth `m1`, then the upper triangular factor U can have upper bandwidth as big as `smu = MIN(N-1,mu+m1)`. The lower triangular factor L has lower bandwidth `m1`.



8.6.2 SUNLinearSolver_Band functions

The SUNLINSOL_BAND module provides the following user-callable constructor for creating a SUNLinearSolver object.

| SUNLinSol_Band | |
|-----------------|---|
| Call | <code>LS = SUNLinSol_Band(y, A);</code> |
| Description | The function <code>SUNLinSol_Band</code> creates and allocates memory for a band <code>SUNLinearSolver</code> object. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver <code>A</code> (<code>SUNMatrix</code>) a <code>SUNMATRIX_BAND</code> matrix template for cloning matrices needed within the solver |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>A</code> or <code>y</code> are incompatible then this routine will return <code>NULL</code> . |
| Notes | This routine will perform consistency checks to ensure that it is called with consistent <code>NVECTOR</code> and <code>SUNMATRIX</code> implementations. These are currently limited to the <code>SUNMATRIX_BAND</code> matrix type and the <code>NVECTOR_SERIAL</code> , <code>NVECTOR_OPENMP</code> , and <code>NVECTOR_PTHREADS</code> vector types. As additional compatible matrix and vector implementations are added to SUNDIALS, these will be included within this compatibility check. Additionally, this routine will verify that the input matrix <code>A</code> is allocated with appropriate upper bandwidth storage for the LU factorization. |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNBandLinearSolver</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_Band</code> when using the Fortran 2003 interface module. |

The SUNLINSOL_BAND module defines band implementations of all “direct” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_Band`
- `SUNLinSolInitialize_Band` – this does nothing, since all consistency checks are performed at solver creation.
- `SUNLinSolSetup_Band` – this performs the *LU* factorization.
- `SUNLinSolSolve_Band` – this uses the *LU* factors and `pivots` array to perform the solve.
- `SUNLinSolLastFlag_Band`
- `SUNLinSolSpace_Band` – this only returns information for the storage *within* the solver object, i.e. storage for `N`, `last_flag`, and `pivots`.
- `SUNLinSolFree_Band`

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

8.6.3 SUNLinearSolver_Band Fortran interfaces

The SUNLINSOL_BAND module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTTRAN 2003 interface module

The `fsunlinsol_band.mod` FORTRAN module defines interfaces to all SUNLINSOL_BAND C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_Band` is interfaced as `FSUNLinSol_Band`.

The FORTRAN 2003 SUNLINSOL_BAND interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_band.mod`, and linking to the library `libsundials_fsunlinsolband.mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_band.mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunlinsolband.mod` library.

FORTTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the SUNLINSOL_BAND module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

| |
|---------------------------|
| FSUNBANDLINSOLINIT |
|---------------------------|

| | |
|--------------|--|
| Call | <code>FSUNBANDLINSOLINIT(code, ier)</code> |
| Description | The function <code>FSUNBANDLINSOLINIT</code> can be called for Fortran programs to create a band <code>SUNLinearSolver</code> object. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for <code>CVODE</code> , 2 for <code>IDA</code> , 3 for <code>KINSOL</code> , and 4 for <code>ARKODE</code>). |
| Return value | <code>ier</code> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the <code>NVECTOR</code> and <code>SUNMATRIX</code> objects have been initialized. |

Additionally, when using `ARKODE` with a non-identity mass matrix, the `SUNLINSOL_BAND` module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

FSUNMASSBANDLINSOLINIT

| | |
|--------------|---|
| Call | FSUNMASSBANDLINSOLINIT(<i>ier</i>) |
| Description | The function FSUNMASSBANDLINSOLINIT can be called for Fortran programs to create a band SUNLinearSolver object for mass matrix linear systems. |
| Arguments | None |
| Return value | <i>ier</i> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX mass-matrix objects have been initialized. |

8.6.4 SUNLinearSolver_Band content

The SUNLINSOL_BAND module defines the *content* field of a SUNLinearSolver as the following structure:

```
struct _SUNLinearSolverContent_Band {
    sunindextype N;
    sunindextype *pivots;
    long int last_flag;
};
```

These entries of the *content* field contain the following information:

N - size of the linear system,
pivots - index array for partial pivoting in LU factorization,
last_flag - last error return flag from internal function evaluations.

8.7 The SUNLinearSolver_LapackDense implementation

This section describes the SUNLINSOL implementation for solving dense linear systems with LAPACK. The SUNLINSOL_LAPACKDENSE module is designed to be used with the corresponding SUNMATRIX_DENSE matrix type, and one of the serial or shared-memory NVECTOR implementations (NVECTOR_SERIAL, NVECTOR_OPENMP, or NVECTOR_PTHREADS).

To access the SUNLINSOL_LAPACKDENSE module, include the header file `sunlinsol/sunlinsol_lapackdense.h`. The installed module library to link to is `libsundials_sunlinsollapackdense.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries.

The SUNLINSOL_LAPACKDENSE module is a SUNLINSOL wrapper for the LAPACK dense matrix factorization and solve routines, `*GETRF` and `*GETRS`, where `*` is either `D` or `S`, depending on whether SUNDIALS was configured to have `realtype` set to `double` or `single`, respectively (see Section 4.2). In order to use the SUNLINSOL_LAPACKDENSE module it is assumed that LAPACK has been installed on the system prior to installation of SUNDIALS, and that SUNDIALS has been configured appropriately to link with LAPACK (see Appendix A for details). We note that since there do not exist 128-bit floating-point factorization and solve routines in LAPACK, this interface cannot be compiled when using `extended` precision for `realtype`. Similarly, since there do not exist 64-bit integer LAPACK routines, the SUNLINSOL_LAPACKDENSE module also cannot be compiled when using 64-bit integers for the `sunindextype`.



8.7.1 SUNLinearSolver_LapackDense description

This solver is constructed to perform the following operations:

- The “setup” call performs a LU factorization with partial (row) pivoting ($\mathcal{O}(N^3)$ cost), $PA = LU$, where P is a permutation matrix, L is a lower triangular matrix with 1’s on the diagonal, and U is an upper triangular matrix. This factorization is stored in-place on the input SUNMATRIX_DENSE object A , with pivoting information encoding P stored in the `pivots` array.
- The “solve” call performs pivoting and forward and backward substitution using the stored `pivots` array and the LU factors held in the SUNMATRIX_DENSE object ($\mathcal{O}(N^2)$ cost).

8.7.2 SUNLinearSolver_LapackDense functions

The SUNLINSOL_LAPACKDENSE module provides the following user-callable constructor for creating a SUNLinearSolver object.

| |
|-----------------------|
| SUNLinSol_LapackDense |
|-----------------------|

| | |
|-----------------|---|
| Call | <code>LS = SUNLinSol_LapackDense(y, A);</code> |
| Description | The function <code>SUNLinSol_LapackDense</code> creates and allocates memory for a LAPACK-based, dense <code>SUNLinearSolver</code> object. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver <code>A</code> (<code>SUNMatrix</code>) a SUNMATRIX_DENSE matrix template for cloning matrices needed within the solver |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>A</code> or <code>y</code> are incompatible then this routine will return <code>NULL</code> . |
| Notes | This routine will perform consistency checks to ensure that it is called with consistent <code>NVECTOR</code> and <code>SUNMATRIX</code> implementations. These are currently limited to the <code>SUNMATRIX_DENSE</code> matrix type and the <code>NVECTOR_SERIAL</code> , <code>NVECTOR_OPENMP</code> , and <code>NVECTOR_PTHREADS</code> vector types. As additional compatible matrix and vector implementations are added to <code>SUNDIALS</code> , these will be included within this compatibility check. |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNLapackDense</code> with identical input and output arguments is also provided. |

The SUNLINSOL_LAPACKDENSE module defines dense implementations of all “direct” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_LapackDense`
- `SUNLinSolInitialize_LapackDense` – this does nothing, since all consistency checks are performed at solver creation.
- `SUNLinSolSetup_LapackDense` – this calls either `DGETRF` or `SGETRF` to perform the LU factorization.
- `SUNLinSolSolve_LapackDense` – this calls either `DGETRS` or `SGETRS` to use the LU factors and `pivots` array to perform the solve.
- `SUNLinSolLastFlag_LapackDense`
- `SUNLinSolSpace_LapackDense` – this only returns information for the storage *within* the solver object, i.e. storage for `N`, `last_flag`, and `pivots`.
- `SUNLinSolFree_LapackDense`

8.7.3 SUNLinearSolver_LapackDense Fortran interfaces

For solvers that include a FORTRAN 77 interface module, the SUNLINSOL_LAPACKDENSE module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNLAPACKDENSEINIT

| | |
|--------------|--|
| Call | FSUNLAPACKDENSEINIT(<i>code</i> , <i>ier</i>) |
| Description | The function FSUNLAPACKDENSEINIT can be called for Fortran programs to create a LAPACK-based dense SUNLinearSolver object. |
| Arguments | <i>code</i> (<i>int*</i>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). |
| Return value | <i>ier</i> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX objects have been initialized. |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_LAPACKDENSE module includes a Fortran-callable function for creating a SUNLinearSolver mass matrix solver object.

FSUNMASSLAPACKDENSEINIT

| | |
|--------------|--|
| Call | FSUNMASSLAPACKDENSEINIT(<i>ier</i>) |
| Description | The function FSUNMASSLAPACKDENSEINIT can be called for Fortran programs to create a LAPACK-based, dense SUNLinearSolver object for mass matrix linear systems. |
| Arguments | None |
| Return value | <i>ier</i> is a <i>int</i> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX mass-matrix objects have been initialized. |

8.7.4 SUNLinearSolver_LapackDense content

The SUNLINSOL_LAPACKDENSE module defines the *content* field of a SUNLinearSolver as the following structure:

```
struct _SUNLinearSolverContent_Dense {
    sunindextype N;
    sunindextype *pivots;
    long int last_flag;
};
```

These entries of the *content* field contain the following information:

N - size of the linear system,
pivots - index array for partial pivoting in LU factorization,
last_flag - last error return flag from internal function evaluations.

8.8 The SUNLinearSolver_LapackBand implementation

This section describes the SUNLINSOL implementation for solving banded linear systems with LAPACK. The SUNLINSOL_LAPACKBAND module is designed to be used with the corresponding SUNMATRIX_BAND matrix type, and one of the serial or shared-memory NVECTOR implementations (NVECTOR_SERIAL, NVECTOR_OPENMP, or NVECTOR_PTHREADS).

To access the SUNLINSOL_LAPACKBAND module, include the header file `sunlinsol/sunlinsol_lapackband.h`. The installed module library to link to is `libsundials_sunlinsollapackband.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries.

The SUNLINSOL_LAPACKBAND module is a SUNLINSOL wrapper for the LAPACK band matrix factorization and solve routines, `*GBTRF` and `*GBTRS`, where `*` is either `D` or `S`, depending on whether SUNDIALS was configured to have `realtype` set to `double` or `single`, respectively (see Section 4.2). In order to use the SUNLINSOL_LAPACKBAND module it is assumed that LAPACK has been installed on the system prior to installation of SUNDIALS, and that SUNDIALS has been configured appropriately to link with LAPACK (see Appendix A for details). We note that since there do not exist 128-bit floating-point factorization and solve routines in LAPACK, this interface cannot be compiled when using `extended` precision for `realtype`. Similarly, since there do not exist 64-bit integer LAPACK routines, the SUNLINSOL_LAPACKBAND module also cannot be compiled when using 64-bit integers for the `sunindextype`.



8.8.1 SUNLinearSolver_LapackBand description

This solver is constructed to perform the following operations:

- The “setup” call performs a LU factorization with partial (row) pivoting, $PA = LU$, where P is a permutation matrix, L is a lower triangular matrix with 1’s on the diagonal, and U is an upper triangular matrix. This factorization is stored in-place on the input `SUNMATRIX_BAND` object A , with pivoting information encoding P stored in the `pivots` array.
- The “solve” call performs pivoting and forward and backward substitution using the stored `pivots` array and the LU factors held in the `SUNMATRIX_BAND` object.
- A must be allocated to accommodate the increase in upper bandwidth that occurs during factorization. More precisely, if A is a band matrix with upper bandwidth `mu` and lower bandwidth `m1`, then the upper triangular factor U can have upper bandwidth as big as `smu = MIN(N-1, mu+m1)`. The lower triangular factor L has lower bandwidth `m1`.



8.8.2 SUNLinearSolver_LapackBand functions

The SUNLINSOL_LAPACKBAND module provides the following user-callable constructor for creating a `SUNLinearSolver` object.

`SUNLinSol_LapackBand`

| | |
|-----------------|---|
| Call | <code>LS = SUNLinSol_LapackBand(y, A);</code> |
| Description | The function <code>SUNLinSol_LapackBand</code> creates and allocates memory for a LAPACK-based, band <code>SUNLinearSolver</code> object. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver <code>A</code> (<code>SUNMatrix</code>) a <code>SUNMATRIX_BAND</code> matrix template for cloning matrices needed within the solver |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>A</code> or <code>y</code> are incompatible then this routine will return <code>NULL</code> . |
| Notes | This routine will perform consistency checks to ensure that it is called with consistent <code>NVECTOR</code> and <code>SUNMATRIX</code> implementations. These are currently limited to the <code>SUNMATRIX_BAND</code> matrix type and the <code>NVECTOR_SERIAL</code> , <code>NVECTOR_OPENMP</code> , and <code>NVECTOR_PTHREADS</code> vector types. As additional compatible matrix and vector implementations are added to SUNDIALS, these will be included within this compatibility check. Additionally, this routine will verify that the input matrix <code>A</code> is allocated with appropriate upper bandwidth storage for the LU factorization. |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNLapackBand</code> with identical input and output arguments is also provided. |

The `SUNLINSOL_LAPACKBAND` module defines band implementations of all “direct” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_LapackBand`
- `SUNLinSolInitialize_LapackBand` – this does nothing, since all consistency checks are performed at solver creation.
- `SUNLinSolSetup_LapackBand` – this calls either `DGBTRF` or `SGBTRF` to perform the LU factorization.
- `SUNLinSolSolve_LapackBand` – this calls either `DGBTRS` or `SGBTRS` to use the LU factors and `pivots` array to perform the solve.
- `SUNLinSolLastFlag_LapackBand`
- `SUNLinSolSpace_LapackBand` – this only returns information for the storage *within* the solver object, i.e. storage for `N`, `last_flag`, and `pivots`.
- `SUNLinSolFree_LapackBand`

8.8.3 `SUNLinearSolver_LapackBand` Fortran interfaces

For solvers that include a FORTRAN 77 interface module, the `SUNLINSOL_LAPACKBAND` module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

`FSUNLAPACKDENSEINIT`

| | |
|--------------|--|
| Call | <code>FSUNLAPACKBANDINIT(code, ier)</code> |
| Description | The function <code>FSUNLAPACKBANDINIT</code> can be called for Fortran programs to create a LAPACK-based band <code>SUNLinearSolver</code> object. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for <code>CVODE</code> , 2 for <code>IDA</code> , 3 for <code>KINSOL</code> , and 4 for <code>ARKODE</code>). |
| Return value | <code>ier</code> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the <code>NVECTOR</code> and <code>SUNMATRIX</code> objects have been initialized. |

Additionally, when using `ARKODE` with a non-identity mass matrix, the `SUNLINSOL_LAPACKBAND` module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

`FSUNMASSLAPACKBANDINIT`

| | |
|--------------|--|
| Call | <code>FSUNMASSLAPACKBANDINIT(ier)</code> |
| Description | The function <code>FSUNMASSLAPACKBANDINIT</code> can be called for Fortran programs to create a LAPACK-based, band <code>SUNLinearSolver</code> object for mass matrix linear systems. |
| Arguments | None |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the <code>NVECTOR</code> and <code>SUNMATRIX</code> mass-matrix objects have been initialized. |

8.8.4 SUNLinearSolver_LapackBand content

The SUNLINSOL_LAPACKBAND module defines the *content* field of a SUNLinearSolver as the following structure:

```
struct _SUNLinearSolverContent_Band {
    sunindextype N;
    sunindextype *pivots;
    long int last_flag;
};
```

These entries of the *content* field contain the following information:

N - size of the linear system,
pivots - index array for partial pivoting in LU factorization,
last_flag - last error return flag from internal function evaluations.

8.9 The SUNLinearSolver_KLU implementation

This section describes the SUNLINSOL implementation for solving sparse linear systems with KLU. The SUNLINSOL_KLU module is designed to be used with the corresponding SUNMATRIX_SPARSE matrix type, and one of the serial or shared-memory NVECTOR implementations (NVECTOR_SERIAL, NVECTOR_OPENMP, or NVECTOR_PTHREADS).

The header file to include when using this module is `sunlinsol/sunlinsol_klu.h`. The installed module library to link to is `libsundials_sunlinsolklu.lib` where *.lib* is typically *.so* for shared libraries and *.a* for static libraries.

The SUNLINSOL_KLU module is a SUNLINSOL wrapper for the KLU sparse matrix factorization and solver library written by Tim Davis [1, 15]. In order to use the SUNLINSOL_KLU interface to KLU, it is assumed that KLU has been installed on the system prior to installation of SUNDIALS, and that SUNDIALS has been configured appropriately to link with KLU (see Appendix A for details). Additionally, this wrapper only supports double-precision calculations, and therefore cannot be compiled if SUNDIALS is configured to have `realtype` set to either `extended` or `single` (see Section 4.2). Since the KLU library supports both 32-bit and 64-bit integers, this interface will be compiled for either of the available `sunindextype` options.



8.9.1 SUNLinearSolver_KLU description

The KLU library has a symbolic factorization routine that computes the permutation of the linear system matrix to block triangular form and the permutations that will pre-order the diagonal blocks (the only ones that need to be factored) to reduce fill-in (using AMD, COLAMD, CHOLAMD, natural, or an ordering given by the user). Of these ordering choices, the default value in the SUNLINSOL_KLU module is the COLAMD ordering.

KLU breaks the factorization into two separate parts. The first is a symbolic factorization and the second is a numeric factorization that returns the factored matrix along with final pivot information. KLU also has a refactor routine that can be called instead of the numeric factorization. This routine will reuse the pivot information. This routine also returns diagnostic information that a user can examine to determine if numerical stability is being lost and a full numerical factorization should be done instead of the refactor.

Since the linear systems that arise within the context of SUNDIALS calculations will typically have identical sparsity patterns, the SUNLINSOL_KLU module is constructed to perform the following operations:

- The first time that the “setup” routine is called, it performs the symbolic factorization, followed by an initial numerical factorization.

- On subsequent calls to the “setup” routine, it calls the appropriate KLU “refactor” routine, followed by estimates of the numerical conditioning using the relevant “rcond”, and if necessary “condest”, routine(s). If these estimates of the condition number are larger than $\varepsilon^{-2/3}$ (where ε is the double-precision unit roundoff), then a new factorization is performed.
- The module includes the routine `SUNKLUReInit`, that can be called by the user to force a full or partial refactorization at the next “setup” call.
- The “solve” call performs pivoting and forward and backward substitution using the stored KLU data structures. We note that in this solve KLU operates on the native data arrays for the right-hand side and solution vectors, without requiring costly data copies.

8.9.2 SUNLinearSolver_KLU functions

The `SUNLINSOL_KLU` module provides the following user-callable constructor for creating a `SUNLinearSolver` object.

| <code>SUNLinSol_KLU</code> | |
|----------------------------|--|
| Call | <code>LS = SUNLinSol_KLU(y, A);</code> |
| Description | The function <code>SUNLinSol_KLU</code> creates and allocates memory for a KLU-based <code>SUNLinearSolver</code> object. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver <code>A</code> (<code>SUNMatrix</code>) a <code>SUNMATRIX_SPARSE</code> matrix template for cloning matrices needed within the solver |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>A</code> or <code>y</code> are incompatible then this routine will return <code>NULL</code> . |
| Notes | This routine will perform consistency checks to ensure that it is called with consistent <code>NVECTOR</code> and <code>SUNMATRIX</code> implementations. These are currently limited to the <code>SUNMATRIX_SPARSE</code> matrix type (using either CSR or CSC storage formats) and the <code>NVECTOR_SERIAL</code> , <code>NVECTOR_OPENMP</code> , and <code>NVECTOR_PTHREADS</code> vector types. As additional compatible matrix and vector implementations are added to <code>SUNDIALS</code> , these will be included within this compatibility check. |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNKLU</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_KLU</code> when using the Fortran 2003 interface module. |

The `SUNLINSOL_KLU` module defines implementations of all “direct” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_KLU`
- `SUNLinSolInitialize_KLU` – this sets the `first_factorize` flag to 1, forcing both symbolic and numerical factorizations on the subsequent “setup” call.
- `SUNLinSolSetup_KLU` – this performs either a *LU* factorization or refactorization of the input matrix.
- `SUNLinSolSolve_KLU` – this calls the appropriate KLU solve routine to utilize the *LU* factors to solve the linear system.
- `SUNLinSolLastFlag_KLU`
- `SUNLinSolSpace_KLU` – this only returns information for the storage within the solver *interface*, i.e. storage for the integers `last_flag` and `first_factorize`. For additional space requirements, see the KLU documentation.

- SUNLinSolFree_KLU

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

The SUNLINSOL_KLU module also defines the following additional user-callable functions.

| |
|---------------------|
| SUNLinSol_KLUReInit |
|---------------------|

| | | | |
|-----------------|--|---|--|
| Call | <code>retval = SUNLinSol_KLUReInit(LS, A, nnz, reinit_type);</code> | | |
| Description | The function <code>SUNLinSol_KLUReInit</code> reinitializes memory and flags for a new factorization (symbolic and numeric) to be conducted at the next solver setup call. This routine is useful in the cases where the number of nonzeros has changed or if the structure of the linear system has changed which would require a new symbolic (and numeric factorization). | | |
| Arguments | <code>LS</code> | (SUNLinearSolver) a template for cloning vectors needed within the solver | |
| | <code>A</code> | (SUNMatrix) a SUNMATRIX_SPARSE matrix template for cloning matrices needed within the solver | |
| | <code>nnz</code> | (sunindextype) the new number of nonzeros in the matrix | |
| | <code>reinit_type</code> | (int) flag governing the level of reinitialization. The allowed values are: <ul style="list-style-type: none">• <code>SUNKLU_REINIT_FULL</code> – The Jacobian matrix will be destroyed and a new one will be allocated based on the <code>nnz</code> value passed to this call. New symbolic and numeric factorizations will be completed at the next solver setup.• <code>SUNKLU_REINIT_PARTIAL</code> – Only symbolic and numeric factorizations will be completed. It is assumed that the Jacobian size has not exceeded the size of <code>nnz</code> given in the sparse matrix provided to the original constructor routine (or the previous <code>SUNLinSol_KLUReInit</code> call). | |
| Return value | The return values from this function are <code>SUNLS_MEM_NULL</code> (either <code>S</code> or <code>A</code> are <code>NULL</code>), <code>SUNLS_ILL_INPUT</code> (<code>A</code> does not have type <code>SUNMATRIX_SPARSE</code> or <code>reinit_type</code> is invalid), <code>SUNLS_MEM_FAIL</code> (reallocation of the sparse matrix failed) or <code>SUNLS_SUCCESS</code> . | | |
| Notes | <p>This routine will perform consistency checks to ensure that it is called with consistent <code>NVECTOR</code> and <code>SUNMATRIX</code> implementations. These are currently limited to the <code>SUNMATRIX_SPARSE</code> matrix type (using either <code>CSR</code> or <code>CSC</code> storage formats) and the <code>NVECTOR_SERIAL</code>, <code>NVECTOR_OPENMP</code>, and <code>NVECTOR_PTHREADS</code> vector types. As additional compatible matrix and vector implementations are added to <code>SUNDIALS</code>, these will be included within this compatibility check.</p> <p>This routine assumes no other changes to solver use are necessary.</p> | | |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNKLUReInit</code> with identical input and output arguments is also provided. | | |
| F2003 Name | This function is callable as <code>FSUNLinSol_KLUReInit</code> when using the Fortran 2003 interface module. | | |

| |
|--------------------------|
| SUNLinSol_KLUSetOrdering |
|--------------------------|

| | | | |
|-------------|--|---|--|
| Call | <code>retval = SUNLinSol_KLUSetOrdering(LS, ordering);</code> | | |
| Description | This function sets the ordering used by KLU for reducing fill in the linear solve. | | |
| Arguments | LS | (SUNLinearSolver) the SUNLINSOL_KLU object | |
| | ordering | (int) flag indicating the reordering algorithm to use, the options are: | |

- 0 AMD,
- 1 COLAMD, and
- 2 the natural ordering.

The default is 1 for COLAMD.

| | |
|-----------------|---|
| Return value | The return values from this function are <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>), <code>SUNLS_ILL_INPUT</code> (invalid ordering choice), or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNKLUSetOrdering</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_KLUSetOrdering</code> when using the Fortran 2003 interface module. |

8.9.3 SUNLinearSolver_KLU Fortran interfaces

The `SUNLINSOL_KLU` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `fsunlinsol_klu.mod` FORTRAN module defines interfaces to all `SUNLINSOL_KLU` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_klu` is interfaced as `FSUNLinSol_klu`.

The FORTRAN 2003 `SUNLINSOL_KLU` interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_klu.mod`, and linking to the library `libsundials_fsunlinsolklu.mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_klu.mod.mod` are installed see [Appendix A](#).

FORTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the `SUNLINSOL_KLU` module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNKLUINIT

| | |
|--------------|--|
| Call | <code>FSUNKLUINIT(code, ier)</code> |
| Description | The function <code>FSUNKLUINIT</code> can be called for Fortran programs to create a <code>SUNLINSOL_KLU</code> object. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for <code>CVODE</code> , 2 for <code>IDA</code> , 3 for <code>KINSOL</code> , and 4 for <code>ARKODE</code>). |
| Return value | <code>ier</code> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the <code>NVECTOR</code> and <code>SUNMATRIX</code> objects have been initialized. |

Additionally, when using `ARKODE` with a non-identity mass matrix, the `SUNLINSOL_KLU` module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

FSUNMASSKLUINIT

| | |
|-------------|--|
| Call | <code>FSUNMASSKLUINIT(ier)</code> |
| Description | The function <code>FSUNMASSKLUINIT</code> can be called for Fortran programs to create a KLU-based <code>SUNLinearSolver</code> object for mass matrix linear systems. |

Arguments None

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes This routine must be called *after* both the NVECTOR and SUNMATRIX mass-matrix objects have been initialized.

The SUNLinSol_KLUReInit and SUNLinSol_KLUSetOrdering routines also support FORTRAN interfaces for the system and mass matrix solvers:

FSUNKLUREINIT

Call FSUNKLUREINIT(**code**, **nnz**, **reinit_type**, **ier**)

Description The function FSUNKLUREINIT can be called for Fortran programs to re-initialize a SUNLINSOL_KLU object.

Arguments **code** (**int***) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).
nnz (**sunindextype***) the new number of nonzeros in the matrix
reinit_type (**int***) flag governing the level of reinitialization. The allowed values are:

- 1 – The Jacobian matrix will be destroyed and a new one will be allocated based on the **nnz** value passed to this call. New symbolic and numeric factorizations will be completed at the next solver setup.
- 2 – Only symbolic and numeric factorizations will be completed. It is assumed that the Jacobian size has not exceeded the size of **nnz** given in the sparse matrix provided to the original constructor routine (or the previous SUNLinSol_KLUReInit call).

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See SUNLinSol_KLUReInit for complete further documentation of this routine.

FSUNMASSKLUREINIT

Call FSUNMASSKLUREINIT(**nnz**, **reinit_type**, **ier**)

Description The function FSUNMASSKLUREINIT can be called for Fortran programs to re-initialize a SUNLINSOL_KLU object for mass matrix linear systems.

Arguments The arguments are identical to FSUNKLUREINIT above, except that **code** is not needed since mass matrix linear systems only arise in ARKODE.

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See SUNLinSol_KLUReInit for complete further documentation of this routine.

FSUNKLUSETORDERING

Call FSUNKLUSETORDERING(**code**, **ordering**, **ier**)

Description The function FSUNKLUSETORDERING can be called for Fortran programs to change the reordering algorithm used by KLU.

Arguments **code** (**int***) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).
ordering (**int***) flag indication the reordering algorithm to use. Options include:

- 0 AMD,
- 1 COLAMD, and

2 the natural ordering.

The default is 1 for COLAMD.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_KLUSetOrdering` for complete further documentation of this routine.

FSUNMASSKLUSETORDERING

Call `FSUNMASSKLUSETORDERING(ier)`

Description The function `FSUNMASSKLUSETORDERING` can be called for Fortran programs to change the reordering algorithm used by KLU for mass matrix linear systems.

Arguments The arguments are identical to `FSUNKLUSETORDERING` above, except that `code` is not needed since mass matrix linear systems only arise in ARKODE.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_KLUSetOrdering` for complete further documentation of this routine.

8.9.4 SUNLinearSolver_KLU content

The `SUNLINSOL_KLU` module defines the *content* field of a `SUNLinearSolver` as the following structure:

```
struct _SUNLinearSolverContent_KLU {
    long int      last_flag;
    int           first_factorize;
    sun_klu_symbolic *symbolic;
    sun_klu_numeric *numeric;
    sun_klu_common common;
    sunindextype  (*klu_solver)(sun_klu_symbolic*, sun_klu_numeric*,
                                sunindextype, sunindextype,
                                double*, sun_klu_common*);
};
```

These entries of the *content* field contain the following information:

`last_flag` - last error return flag from internal function evaluations,
`first_factorize` - flag indicating whether the factorization has ever been performed,
`symbolic` - KLU storage structure for symbolic factorization components,
`numeric` - KLU storage structure for numeric factorization components,
`common` - storage structure for common KLU solver components,
`klu_solver` - pointer to the appropriate KLU solver function (depending on whether it is using a CSR or CSC sparse matrix).

8.10 The SUNLinearSolver_SuperLUMT implementation

This section describes the `SUNLINSOL` implementation for solving sparse linear systems with SuperLU_MT. The `SUPERLUMT` module is designed to be used with the corresponding `SUNMATRIX_SPARSE` matrix type, and one of the serial or shared-memory `NVECTOR` implementations (`NVECTOR_SERIAL`, `NVECTOR_OPENMP`, or `NVECTOR_PTHREADS`). While these are compatible, it is not recommended to use a threaded vector module with `SUNLINSOL_SUPERLUMT` unless it is the `NVECTOR_OPENMP` module and the `SUPERLUMT` library has also been compiled with OpenMP.

The header file to include when using this module is `sunlinsol/sunlinsol_superluml.h`. The installed module library to link to is `libsundials_sunlinsolsuperluml.lib` where `.lib` is typically `.so` for shared libraries and `.a` for static libraries.

The SUNLINSOL_SUPERLUMT module is a SUNLINSOL wrapper for the SUPERLUMT sparse matrix factorization and solver library written by X. Sherry Li [2, 29, 17]. The package performs matrix factorization using threads to enhance efficiency in shared memory parallel environments. It should be noted that threads are only used in the factorization step. In order to use the SUNLINSOL_SUPERLUMT interface to SUPERLUMT, it is assumed that SUPERLUMT has been installed on the system prior to installation of SUNDIALS, and that SUNDIALS has been configured appropriately to link with SUPERLUMT (see Appendix A for details). Additionally, this wrapper only supports single- and double-precision calculations, and therefore cannot be compiled if SUNDIALS is configured to have `realtype` set to `extended` (see Section 4.2). Moreover, since the SUPERLUMT library may be installed to support either 32-bit or 64-bit integers, it is assumed that the SUPERLUMT library is installed using the same integer precision as the SUNDIALS `sunindextype` option.



8.10.1 SUNLinearSolver_SuperLUMT description

The SUPERLUMT library has a symbolic factorization routine that computes the permutation of the linear system matrix to reduce fill-in on subsequent *LU* factorizations (using COLAMD, minimal degree ordering on $A^T * A$, minimal degree ordering on $A^T + A$, or natural ordering). Of these ordering choices, the default value in the SUNLINSOL_SUPERLUMT module is the COLAMD ordering.

Since the linear systems that arise within the context of SUNDIALS calculations will typically have identical sparsity patterns, the SUNLINSOL_SUPERLUMT module is constructed to perform the following operations:

- The first time that the “setup” routine is called, it performs the symbolic factorization, followed by an initial numerical factorization.
- On subsequent calls to the “setup” routine, it skips the symbolic factorization, and only refactors the input matrix.
- The “solve” call performs pivoting and forward and backward substitution using the stored SUPERLUMT data structures. We note that in this solve SUPERLUMT operates on the native data arrays for the right-hand side and solution vectors, without requiring costly data copies.

8.10.2 SUNLinearSolver_SuperLUMT functions

The module SUNLINSOL_SUPERLUMT provides the following user-callable constructor for creating a `SUNLinearSolver` object.

| SUNLinSol_SuperLUMT | |
|---------------------|--|
| Call | <code>LS = SUNLinSol_SuperLUMT(y, A, num_threads);</code> |
| Description | The function <code>SUNLinSol_SuperLUMT</code> creates and allocates memory for a SuperLU_MT-based <code>SUNLinearSolver</code> object. |
| Arguments | <p><code>y</code> (N_Vector) a template for cloning vectors needed within the solver</p> <p><code>A</code> (SUNMatrix) a SUNMATRIX_SPARSE matrix template for cloning matrices needed within the solver</p> <p><code>num_threads</code> (int) desired number of threads (OpenMP or Pthreads, depending on how SUPERLUMT was installed) to use during the factorization steps</p> |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>A</code> or <code>y</code> are incompatible then this routine will return <code>NULL</code> . |

| | |
|-----------------|--|
| Notes | <p>This routine analyzes the input matrix and vector to determine the linear system size and to assess compatibility with the SUPERLUMT library.</p> <p>This routine will perform consistency checks to ensure that it is called with consistent NVECTOR and SUNMATRIX implementations. These are currently limited to the SUNMATRIX_SPARSE matrix type (using either CSR or CSC storage formats) and the NVECTOR_SERIAL, NVECTOR_OPENMP, and NVECTOR_PTHREADS vector types. As additional compatible matrix and vector implementations are added to SUNDIALS, these will be included within this compatibility check.</p> <p>The <code>num_threads</code> argument is not checked and is passed directly to SUPERLUMT routines.</p> |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSuperLUMT</code> with identical input and output arguments is also provided. |

The `SUNLINSOL_SUPERLUMT` module defines implementations of all “direct” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_SuperLUMT`
- `SUNLinSolInitialize_SuperLUMT` – this sets the `first_factorize` flag to 1 and resets the internal SUPERLUMT statistics variables.
- `SUNLinSolSetup_SuperLUMT` – this performs either a *LU* factorization or refactorization of the input matrix.
- `SUNLinSolSolve_SuperLUMT` – this calls the appropriate SUPERLUMT solve routine to utilize the *LU* factors to solve the linear system.
- `SUNLinSolLastFlag_SuperLUMT`
- `SUNLinSolSpace_SuperLUMT` – this only returns information for the storage within the solver *interface*, i.e. storage for the integers `last_flag` and `first_factorize`. For additional space requirements, see the SUPERLUMT documentation.
- `SUNLinSolFree_SuperLUMT`

The `SUNLINSOL_SUPERLUMT` module also defines the following additional user-callable function.

| |
|---|
| <code>SUNLinSol_SuperLUMTSetOrdering</code> |
|---|

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_SuperLUMTSetOrdering(LS, ordering);</code> |
| Description | This function sets the ordering used by SUPERLUMT for reducing fill in the linear solve. |
| Arguments | <p><code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SUPERLUMT</code> object</p> <p><code>ordering</code> (<code>int</code>) a flag indicating the ordering algorithm to use, the options are:</p> <ul style="list-style-type: none"> 0 natural ordering 1 minimal degree ordering on $A^T A$ 2 minimal degree ordering on $A^T + A$ 3 COLAMD ordering for unsymmetric matrices <p>The default is 3 for COLAMD.</p> |
| Return value | The return values from this function are <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>), <code>SUNLS_ILL_INPUT</code> (invalid ordering choice), or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSuperLUMTSetOrdering</code> with identical input and output arguments is also provided. |

8.10.3 SUNLinearSolver_SuperLUMT Fortran interfaces

For solvers that include a Fortran interface module, the SUNLINSOL_SUPERLUMT module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNSUPERLUMTINIT

| | |
|--------------|--|
| Call | FSUNSUPERLUMTINIT(<i>code</i> , <i>num_threads</i> , <i>ier</i>) |
| Description | The function FSUNSUPERLUMTINIT can be called for Fortran programs to create a SUNLINSOL_KLU object. |
| Arguments | <p><i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).</p> <p><i>num_threads</i> (int*) desired number of threads (OpenMP or Pthreads, depending on how SUPERLUMT was installed) to use during the factorization steps</p> |
| Return value | <i>ier</i> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX objects have been initialized. |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_SUPERLUMT module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

FSUNMASSSUPERLUMTINIT

| | |
|--------------|--|
| Call | FSUNMASSSUPERLUMTINIT(<i>num_threads</i> , <i>ier</i>) |
| Description | The function FSUNMASSSUPERLUMTINIT can be called for Fortran programs to create a SuperLU_MT-based <code>SUNLinearSolver</code> object for mass matrix linear systems. |
| Arguments | <i>num_threads</i> (int*) desired number of threads (OpenMP or Pthreads, depending on how SUPERLUMT was installed) to use during the factorization steps. |
| Return value | <i>ier</i> is a int return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> both the NVECTOR and SUNMATRIX mass-matrix objects have been initialized. |

The `SUNLinSol_SuperLUMTSetOrdering` routine also supports Fortran interfaces for the system and mass matrix solvers:

FSUNSUPERLUMTSETORDERING

| | |
|--------------|--|
| Call | FSUNSUPERLUMTSETORDERING(<i>code</i> , <i>ordering</i> , <i>ier</i>) |
| Description | The function FSUNSUPERLUMTSETORDERING can be called for Fortran programs to update the ordering algorithm in a SUNLINSOL_SUPERLUMT object. |
| Arguments | <p><i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).</p> <p><i>ordering</i> (int*) a flag indicating the ordering algorithm, options are:</p> <ul style="list-style-type: none"> 0 natural ordering 1 minimal degree ordering on $A^T A$ 2 minimal degree ordering on $A^T + A$ 3 COLAMD ordering for unsymmetric matrices <p>The default is 3 for COLAMD.</p> |
| Return value | <i>ier</i> is a int return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |

Notes See `SUNLinSol_SuperLUMTSetOrdering` for complete further documentation of this routine.

FSUNMASSUPERLUMTSETORDERING

Call `FSUNMASSUPERLUMTSETORDERING(ordering, ier)`

Description The function `FSUNMASSUPERLUMTSETORDERING` can be called for Fortran programs to update the ordering algorithm in a `SUNLINSOL_SUPERLUMT` object for mass matrix linear systems.

Arguments `ordering` (`int*`) a flag indicating the ordering algorithm, options are:

- 0 natural ordering
- 1 minimal degree ordering on $A^T A$
- 2 minimal degree ordering on $A^T + A$
- 3 COLAMD ordering for unsymmetric matrices

The default is 3 for COLAMD.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SuperLUMTSetOrdering` for complete further documentation of this routine.

8.10.4 SUNLinearSolver_SuperLUMT content

The `SUNLINSOL_SUPERLUMT` module defines the *content* field of a `SUNLinearSolver` as the following structure:

```
struct _SUNLinearSolverContent_SuperLUMT {
    long int    last_flag;
    int         first_factorize;
    SuperMatrix *A, *AC, *L, *U, *B;
    Gstat_t     *Gstat;
    sunindextype *perm_r, *perm_c;
    sunindextype N;
    int         num_threads;
    realtype    diag_pivot_thresh;
    int         ordering;
    superlumt_options_t *options;
};
```

These entries of the *content* field contain the following information:

- `last_flag` - last error return flag from internal function evaluations,
- `first_factorize` - flag indicating whether the factorization has ever been performed,
- `A, AC, L, U, B` - `SuperMatrix` pointers used in solve,
- `Gstat` - `GStat_t` object used in solve,
- `perm_r, perm_c` - permutation arrays used in solve,
- `N` - size of the linear system,
- `num_threads` - number of OpenMP/Pthreads threads to use,
- `diag_pivot_thresh` - threshold on diagonal pivoting,
- `ordering` - flag for which reordering algorithm to use,
- `options` - pointer to `SUPERLUMT` options structure.

8.11 The SUNLinearSolver_SPGMR implementation

This section describes the SUNLINSOL implementation of the SPGMR (Scaled, Preconditioned, Generalized Minimum Residual [33]) iterative linear solver. The SUNLINSOL_SPGMR module is designed to be compatible with any NVECTOR implementation that supports a minimal subset of operations (N_VClone, N_VDotProd, N_VScale, N_VLinearSum, N_VProd, N_VConst, N_VDiv, and N_VDestroy). When using Classical Gram-Schmidt, the optional function N_VDotProdMulti may be supplied for increased efficiency.

To access the SUNLINSOL_SPGMR module, include the header file `sunlinsol/sunlinsol_spgmr.h`. We note that the SUNLINSOL_SPGMR module is accessible from SUNDIALS packages *without* separately linking to the `libsundials_sunlinsolspgmr` module library.

8.11.1 SUNLinearSolver_SPGMR description

This solver is constructed to perform the following operations:

- During construction, the `xcor` and `vtemp` arrays are cloned from a template NVECTOR that is input, and default solver parameters are set.
- User-facing “set” routines may be called to modify default solver parameters.
- Additional “set” routines are called by the SUNDIALS solver that interfaces with SUNLINSOL_SPGMR to supply the `ATimes`, `PSetup`, and `Psolve` function pointers and `s1` and `s2` scaling vectors.
- In the “initialize” call, the remaining solver data is allocated (`V`, `Hes`, `givens`, and `yg`)
- In the “setup” call, any non-NULL `PSetup` function is called. Typically, this is provided by the SUNDIALS solver itself, that translates between the generic `PSetup` function and the solver-specific routine (solver-supplied or user-supplied).
- In the “solve” call, the GMRES iteration is performed. This will include scaling, preconditioning, and restarts if those options have been supplied.

8.11.2 SUNLinearSolver_SPGMR functions

The SUNLINSOL_SPGMR module provides the following user-callable constructor for creating a `SUNLinearSolver` object.

| <code>SUNLinSol_SPGMR</code> | |
|------------------------------|---|
| Call | <code>LS = SUNLinSol_SPGMR(y, pretype, maxl);</code> |
| Description | The function <code>SUNLinSol_SPGMR</code> creates and allocates memory for a SPGMR <code>SUNLinearSolver</code> object. |
| Arguments | <div> <code>y</code> (N_Vector) a template for cloning vectors needed within the solver </div> <div> <code>pretype</code> (int) flag indicating the desired type of preconditioning, allowed values are: <ul style="list-style-type: none"> • <code>PREC_NONE</code> (0) • <code>PREC_LEFT</code> (1) • <code>PREC_RIGHT</code> (2) • <code>PREC_BOTH</code> (3) Any other integer input will result in the default (no preconditioning). </div> <div> <code>maxl</code> (int) the number of Krylov basis vectors to use. Values ≤ 0 will result in the default value (5). </div> |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>y</code> is incompatible then this routine will return <code>NULL</code> . |

| | |
|-----------------|--|
| Notes | <p>This routine will perform consistency checks to ensure that it is called with a consistent NVECTOR implementation (i.e. that it supplies the requisite vector operations). If <code>y</code> is incompatible, then this routine will return <code>NULL</code>.</p> <p>We note that some SUNDIALS solvers are designed to only work with left preconditioning (IDA and IDAS) and others with only right preconditioning (KINSOL). While it is possible to configure a <code>SUNLINSOL_SPGMR</code> object to use any of the preconditioning options with these solvers, this use mode is not supported and may result in inferior performance.</p> |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPGMR</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPGMR</code> when using the Fortran 2003 interface module. |

The `SUNLINSOL_SPGMR` module defines implementations of all “iterative” linear solver operations listed in Sections [8.1.1](#) – [8.1.3](#):

- `SUNLinSolGetType_SPGMR`
- `SUNLinSolInitialize_SPGMR`
- `SUNLinSolSetATimes_SPGMR`
- `SUNLinSolSetPreconditioner_SPGMR`
- `SUNLinSolSetScalingVectors_SPGMR`
- `SUNLinSolSetup_SPGMR`
- `SUNLinSolSolve_SPGMR`
- `SUNLinSolNumIters_SPGMR`
- `SUNLinSolResNorm_SPGMR`
- `SUNLinSolResid_SPGMR`
- `SUNLinSolLastFlag_SPGMR`
- `SUNLinSolSpace_SPGMR`
- `SUNLinSolFree_SPGMR`

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

The `SUNLINSOL_SPGMR` module also defines the following additional user-callable functions.

| |
|---|
| <code>SUNLinSol_SPGMRSetPrecType</code> |
|---|

| | |
|-----------------|---|
| Call | <code>retval = SUNLinSol_SPGMRSetPrecType(LS, pretype);</code> |
| Description | The function <code>SUNLinSol_SPGMRSetPrecType</code> updates the type of preconditioning to use in the <code>SUNLINSOL_SPGMR</code> object. |
| Arguments | <p><code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPGMR</code> object to update</p> <p><code>pretype</code> (<code>int</code>) flag indicating the desired type of preconditioning, allowed values match those discussed in <code>SUNLinSol_SPGMR</code>.</p> |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal <code>pretype</code>), <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPGMRSetPrecType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPGMRSetPrecType</code> when using the Fortran 2003 interface module. |

SUNLinSol_SPGMRSetGSType

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_SPGMRSetGSType(LS, gstype);</code> |
| Description | The function <code>SUNLinSol_SPGMRSetPrecType</code> sets the type of Gram-Schmidt orthogonalization to use in the <code>SUNLINSOL_SPGMR</code> object. |
| Arguments | <p><code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPGMR</code> object to update</p> <p><code>gstype</code> (<code>int</code>) flag indicating the desired orthogonalization algorithm; allowed values are:</p> <ul style="list-style-type: none"> • <code>MODIFIED_GS</code> (1) • <code>CLASSICAL_GS</code> (2) <p>Any other integer input will result in a failure, returning error code <code>SUNLS_ILL_INPUT</code>.</p> |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal pretype), <code>SUNLS_MEM_NULL</code> (S is NULL) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPGMRSetGSType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPGMRSetGSType</code> when using the Fortran 2003 interface module. |

SUNLinSol_SPGMRSetMaxRestarts

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_SPGMRSetMaxRestarts(LS, maxrs);</code> |
| Description | The function <code>SUNLinSol_SPGMRSetMaxRestarts</code> sets the number of GMRES restarts to allow in the <code>SUNLINSOL_SPGMR</code> object. |
| Arguments | <p><code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPGMR</code> object to update</p> <p><code>maxrs</code> (<code>int</code>) integer indicating number of restarts to allow. A negative input will result in the default of 0.</p> |
| Return value | This routine will return with one of the error codes <code>SUNLS_MEM_NULL</code> (S is NULL) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPGMRSetMaxRestarts</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPGMRSetMaxRestarts</code> when using the Fortran 2003 interface module. |

8.11.3 SUNLinearSolver_SPGMR Fortran interfaces

The `SUNLINSOL_SPGMR` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `fsunlinsol_spgmr_mod` FORTRAN module defines interfaces to all `SUNLINSOL_SPGMR` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading 'F'. For example, the function `SUNLinSol_SPGMR` is interfaced as `FSUNLinSol_SPGMR`.

The FORTRAN 2003 `SUNLINSOL_SPGMR` interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_spgmr_mod`, and linking to the library `libsundials_fsunlinsolspgmr_mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_spgmr_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunlinsolspgmr_mod` library.

FORTTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the SUNLINSOL_SPGMR module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNSPGMRINIT

| | |
|--------------|--|
| Call | FSUNSPGMRINIT(<i>code</i> , <i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNSPGMRINIT can be called for Fortran programs to create a SUNLINSOL_SPGMR object. |
| Arguments | <i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>pretype</i> (int*) flag indicating desired preconditioning type <i>maxl</i> (int*) flag indicating Krylov subspace size |
| Return value | <i>ier</i> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function SUNLinSol_SPGMR. |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_SPGMR module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

FSUNMASSSPGMRINIT

| | |
|--------------|--|
| Call | FSUNMASSSPGMRINIT(<i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNMASSSPGMRINIT can be called for Fortran programs to create a SUNLINSOL_SPGMR object for mass matrix linear systems. |
| Arguments | <i>pretype</i> (int*) flag indicating desired preconditioning type <i>maxl</i> (int*) flag indicating Krylov subspace size |
| Return value | <i>ier</i> is a int return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function SUNLinSol_SPGMR. |

The SUNLinSol_SPGMRSetPrecType, SUNLinSol_SPGMRSetGStype and SUNLinSol_SPGMRSetMaxRestarts routines also support Fortran interfaces for the system and mass matrix solvers.

FSUNSPGMRSETGSTYPE

| | |
|--------------|--|
| Call | FSUNSPGMRSETGSTYPE(<i>code</i> , <i>gstype</i> , <i>ier</i>) |
| Description | The function FSUNSPGMRSETGSTYPE can be called for Fortran programs to change the Gram-Schmidt orthogonalization algorithm. |
| Arguments | <i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>gstype</i> (int*) flag indicating the desired orthogonalization algorithm. |
| Return value | <i>ier</i> is a int return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPGMRSetGStype for complete further documentation of this routine. |

FSUNMASSSPGMRSETGSTYPE

| | |
|--------------|--|
| Call | <code>FSUNMASSSPGMRSETGSTYPE(gstype, ier)</code> |
| Description | The function <code>FSUNMASSSPGMRSETGSTYPE</code> can be called for Fortran programs to change the Gram-Schmidt orthogonalization algorithm for mass matrix linear systems. |
| Arguments | The arguments are identical to <code>FSUNSPGMRSETGSTYPE</code> above, except that <code>code</code> is not needed since mass matrix linear systems only arise in <code>ARKODE</code> . |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See <code>SUNLinSol_SPGMRSetGStype</code> for complete further documentation of this routine. |

FSUNSPGMRSETPRECTYPE

| | |
|--------------|--|
| Call | <code>FSUNSPGMRSETPRECTYPE(code, pretype, ier)</code> |
| Description | The function <code>FSUNSPGMRSETPRECTYPE</code> can be called for Fortran programs to change the type of preconditioning to use. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for <code>CVODE</code> , 2 for <code>IDA</code> , 3 for <code>KINSOL</code> , and 4 for <code>ARKODE</code>). <code>pretype</code> (<code>int*</code>) flag indicating the type of preconditioning to use. |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See <code>SUNLinSol_SPGMRSetPrecType</code> for complete further documentation of this routine. |

FSUNMASSSPGMRSETPRECTYPE

| | |
|--------------|--|
| Call | <code>FSUNMASSSPGMRSETPRECTYPE(pretype, ier)</code> |
| Description | The function <code>FSUNMASSSPGMRSETPRECTYPE</code> can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems. |
| Arguments | The arguments are identical to <code>FSUNSPGMRSETPRECTYPE</code> above, except that <code>code</code> is not needed since mass matrix linear systems only arise in <code>ARKODE</code> . |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See <code>SUNLinSol_SPGMRSetPrecType</code> for complete further documentation of this routine. |

FSUNSPGMRSETMAXRS

| | |
|--------------|--|
| Call | <code>FSUNSPGMRSETMAXRS(code, maxrs, ier)</code> |
| Description | The function <code>FSUNSPGMRSETMAXRS</code> can be called for Fortran programs to change the maximum number of restarts allowed for <code>SPGMR</code> . |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for <code>CVODE</code> , 2 for <code>IDA</code> , 3 for <code>KINSOL</code> , and 4 for <code>ARKODE</code>). <code>maxrs</code> (<code>int*</code>) maximum allowed number of restarts. |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See <code>SUNLinSol_SPGMRSetMaxRestarts</code> for complete further documentation of this routine. |

| |
|-----------------------|
| FSUNMASSSPGMRSETMAXRS |
|-----------------------|

| | |
|--------------|---|
| Call | FSUNMASSSPGMRSETMAXRS(maxrs, ier) |
| Description | The function FSUNMASSSPGMRSETMAXRS can be called for Fortran programs to change the maximum number of restarts allowed for SPGMR for mass matrix linear systems. |
| Arguments | The arguments are identical to FSUNSPGMRSETMAXRS above, except that <code>code</code> is not needed since mass matrix linear systems only arise in ARKODE. |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPGMRSetMaxRestarts for complete further documentation of this routine. |

8.11.4 SUNLinearSolver_SPGMR content

The SUNLINSOL_SPGMR module defines the *content* field of a SUNLinearSolver as the following structure:

```
struct _SUNLinearSolverContent_SPGMR {
    int maxl;
    int pretype;
    int gstype;
    int max_restarts;
    int numiters;
    realtype resnorm;
    long int last_flag;
    ATimesFn ATimes;
    void* ATData;
    PSetupFn Psetup;
    PSolveFn Psolve;
    void* PData;
    N_Vector s1;
    N_Vector s2;
    N_Vector *V;
    realtype **Hes;
    realtype *givens;
    N_Vector xcor;
    realtype *yg;
    N_Vector vtemp;
};
```

These entries of the *content* field contain the following information:

| | |
|---------------------------|---|
| <code>maxl</code> | - number of GMRES basis vectors to use (default is 5), |
| <code>pretype</code> | - flag for type of preconditioning to employ (default is none), |
| <code>gstype</code> | - flag for type of Gram-Schmidt orthogonalization (default is modified Gram-Schmidt), |
| <code>max_restarts</code> | - number of GMRES restarts to allow (default is 0), |
| <code>numiters</code> | - number of iterations from the most-recent solve, |
| <code>resnorm</code> | - final linear residual norm from the most-recent solve, |
| <code>last_flag</code> | - last error return flag from an internal function, |
| <code>ATimes</code> | - function pointer to perform Av product, |
| <code>ATData</code> | - pointer to structure for <code>ATimes</code> , |
| <code>Psetup</code> | - function pointer to preconditioner setup routine, |

| | |
|---------------|--|
| Psolve | - function pointer to preconditioner solve routine, |
| PData | - pointer to structure for Psetup and Psolve , |
| s1, s2 | - vector pointers for supplied scaling matrices (default is NULL), |
| V | - the array of Krylov basis vectors $v_1, \dots, v_{\text{maxl}+1}$, stored in V[0] , ..., V[maxl] . Each v_i is a vector of type NVECTOR ., |
| Hes | - the $(\text{maxl} + 1) \times \text{maxl}$ Hessenberg matrix. It is stored row-wise so that the (i,j) th element is given by Hes[i][j] ., |
| givens | - a length $2*\text{maxl}$ array which represents the Givens rotation matrices that arise in the GMRES algorithm. These matrices are F_0, F_1, \dots, F_j , where |

$$F_i = \begin{bmatrix} 1 & & & & & & & \\ & \ddots & & & & & & \\ & & 1 & & & & & \\ & & & c_i & -s_i & & & \\ & & & s_i & c_i & & & \\ & & & & & 1 & & \\ & & & & & & \ddots & \\ & & & & & & & 1 \end{bmatrix},$$

are represented in the **givens** vector as **givens[0] = c_0** , **givens[1] = s_0** , **givens[2] = c_1** , **givens[3] = s_1** , ... **givens[2j] = c_j** , **givens[2j+1] = s_j** .,

| | |
|--------------|--|
| xcor | - a vector which holds the scaled, preconditioned correction to the initial guess, |
| yg | - a length $(\text{maxl}+1)$ array of realtype values used to hold “short” vectors (e.g. y and g), |
| vtemp | - temporary vector storage. |

8.12 The SUNLinearSolver_SPFGMR implementation

This section describes the SUNLINSOL implementation of the SPFGMR (Scaled, Preconditioned, Flexible, Generalized Minimum Residual [32]) iterative linear solver. The SUNLINSOL_SPFGMR module is designed to be compatible with any **NVECTOR** implementation that supports a minimal subset of operations (**N_VClone**, **N_VDotProd**, **N_VScale**, **N_VLinearSum**, **N_VProd**, **N_VConst**, **N_VDiv**, and **N_VDestroy**). When using Classical Gram-Schmidt, the optional function **N_VDotProdMulti** may be supplied for increased efficiency. Unlike the other Krylov iterative linear solvers supplied with SUNDIALS, SPFGMR is specifically designed to work with a changing preconditioner (e.g. from an iterative method).

To access the SUNLINSOL_SPFGMR module, include the header file **sunlinsol/sunlinsol_spfgmr.h**. We note that the SUNLINSOL_SPFGMR module is accessible from SUNDIALS packages *without* separately linking to the **libsundials_sunlinsolspfgmr** module library.

8.12.1 SUNLinearSolver_SPFGMR description

This solver is constructed to perform the following operations:

- During construction, the **xcor** and **vtemp** arrays are cloned from a template **NVECTOR** that is input, and default solver parameters are set.
- User-facing “set” routines may be called to modify default solver parameters.
- Additional “set” routines are called by the SUNDIALS solver that interfaces with SUNLINSOL_SPFGMR to supply the **ATimes**, **PSetup**, and **Psolve** function pointers and **s1** and **s2** scaling vectors.

- In the “initialize” call, the remaining solver data is allocated (`V`, `Hes`, `givens`, and `yg`)
- In the “setup” call, any non-NULL `PSetup` function is called. Typically, this is provided by the SUNDIALS solver itself, that translates between the generic `PSetup` function and the solver-specific routine (solver-supplied or user-supplied).
- In the “solve” call, the FGMRES iteration is performed. This will include scaling, preconditioning, and restarts if those options have been supplied.

8.12.2 SUNLinearSolver_SPFGMR functions

The `SUNLINSOL_SPFGMR` module provides the following user-callable constructor for creating a `SUNLinearSolver` object.

| |
|-------------------------------|
| <code>SUNLinSol_SPFGMR</code> |
|-------------------------------|

| | |
|--------------|---|
| Call | <code>LS = SUNLinSol_SPFGMR(y, pretype, maxl);</code> |
| Description | The function <code>SUNLinSol_SPFGMR</code> creates and allocates memory for a SPFGMR <code>SUNLinearSolver</code> object. |
| Arguments | <p><code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver</p> <p><code>pretype</code> (<code>int</code>) flag indicating the desired type of preconditioning, allowed values are:</p> <ul style="list-style-type: none"> • <code>PREC_NONE</code> (0) • <code>PREC_LEFT</code> (1) • <code>PREC_RIGHT</code> (2) • <code>PREC_BOTH</code> (3) <p>Any other integer input will result in the default (no preconditioning).</p> <p><code>maxl</code> (<code>int</code>) the number of Krylov basis vectors to use. Values ≤ 0 will result in the default value (5).</p> |
| Return value | This returns a <code>SUNLinearSolver</code> object. If either <code>y</code> is incompatible then this routine will return <code>NULL</code> . |
| Notes | <p>This routine will perform consistency checks to ensure that it is called with a consistent <code>NVECTOR</code> implementation (i.e. that it supplies the requisite vector operations). If <code>y</code> is incompatible, then this routine will return <code>NULL</code>.</p> <p>We note that some SUNDIALS solvers are designed to only work with left preconditioning (<code>IDA</code> and <code>IDAS</code>) and others with only right preconditioning (<code>KINSOL</code>). While it is possible to configure a <code>SUNLINSOL_SPFGMR</code> object to use any of the preconditioning options with these solvers, this use mode is not supported and may result in inferior performance.</p> |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPFGMR</code> when using the Fortran 2003 interface module. |

SUNSPFGMR The `SUNLINSOL_SPFGMR` module defines implementations of all “iterative” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_SPFGMR`
- `SUNLinSolInitialize_SPFGMR`
- `SUNLinSolSetATimes_SPFGMR`
- `SUNLinSolSetPreconditioner_SPFGMR`
- `SUNLinSolSetScalingVectors_SPFGMR`
- `SUNLinSolSetup_SPFGMR`

- SUNLinSolSolve_SPFGMR
- SUNLinSolNumIters_SPFGMR
- SUNLinSolResNorm_SPFGMR
- SUNLinSolResid_SPFGMR
- SUNLinSolLastFlag_SPFGMR
- SUNLinSolSpace_SPFGMR
- SUNLinSolFree_SPFGMR

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

The SUNLINSOL_SPFGMR module also defines the following additional user-callable functions.

SUNLinSol_SPFGMRSetPrecType

| | |
|-----------------|---|
| Call | <code>retval = SUNLinSol_SPFGMRSetPrecType(LS, pretype);</code> |
| Description | The function <code>SUNLinSol_SPFGMRSetPrecType</code> updates the type of preconditioning to use in the <code>SUNLINSOL_SPFGMR</code> object. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPFGMR</code> object to update <code>pretype</code> (<code>int</code>) flag indicating the desired type of preconditioning, allowed values match those discussed in <code>SUNLinSol_SPFGMR</code> . |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal <code>pretype</code>), <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPFGMRSetPrecType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPFGMRSetPrecType</code> when using the Fortran 2003 interface module. |

SUNLinSol_SPFGMRSetGSType

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_SPFGMRSetGSType(LS, gstype);</code> |
| Description | The function <code>SUNLinSol_SPFGMRSetGSType</code> sets the type of Gram-Schmidt orthogonalization to use in the <code>SUNLINSOL_SPFGMR</code> object. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPFGMR</code> object to update <code>gstype</code> (<code>int</code>) flag indicating the desired orthogonalization algorithm; allowed values are: <ul style="list-style-type: none"> • <code>MODIFIED_GS</code> (1) • <code>CLASSICAL_GS</code> (2) Any other integer input will result in a failure, returning error code <code>SUNLS_ILL_INPUT</code> . |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal <code>pretype</code>), <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPFGMRSetGSType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPFGMRSetGSType</code> when using the Fortran 2003 interface module. |

| | |
|---------------------------------------|--|
| SUNLinSol_SPFGMRSetMaxRestarts | |
| Call | <code>retval = SUNLinSol_SPFGMRSetMaxRestarts(LS, maxrs);</code> |
| Description | The function <code>SUNLinSol_SPFGMRSetMaxRestarts</code> sets the number of GMRES restarts to allow in the <code>SUNLINSOL_SPFGMR</code> object. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPFGMR</code> object to update <code>maxrs</code> (<code>int</code>) integer indicating number of restarts to allow. A negative input will result in the default of 0. |
| Return value | This routine will return with one of the error codes <code>SUNLS_MEM_NULL</code> (S is NULL) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPFGMRSetMaxRestarts</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPFGMRSetMaxRestarts</code> when using the Fortran 2003 interface module. |

8.12.3 SUNLinearSolver_SPFGMR Fortran interfaces

The `SUNLINSOL_SPFGMR` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `fsunlinsol_spfgmr_mod` FORTRAN module defines interfaces to all `SUNLINSOL_SPFGMR` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_SPFGMR` is interfaced as `FSUNLinSol_SPFGMR`.

The FORTRAN 2003 `SUNLINSOL_SPFGMR` interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_spfgmr_mod`, and linking to the library `libsundials_fsunlinsolspfgmr_mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_spfgmr_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunlinsolspfgmr_mod` library.

FORTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the `SUNLINSOL_SPFGMR` module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

| | |
|-----------------------|---|
| FSUNSPFGMRINIT | |
| Call | <code>FSUNSPFGMRINIT(code, pretype, maxl, ier)</code> |
| Description | The function <code>FSUNSPFGMRINIT</code> can be called for Fortran programs to create a <code>SUNLINSOL_SPFGMR</code> object. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <code>pretype</code> (<code>int*</code>) flag indicating desired preconditioning type <code>maxl</code> (<code>int*</code>) flag indicating Krylov subspace size |
| Return value | <code>ier</code> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the <code>NVECTOR</code> object has been initialized. Allowable values for <code>pretype</code> and <code>maxl</code> are the same as for the C function <code>SUNLinSol_SPFGMR</code> . |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_SPFGMR module includes a Fortran-callable function for creating a SUNLinearSolver mass matrix solver object.

FSUNMASSSPFGMRINIT

| | |
|--------------|---|
| Call | FSUNMASSSPFGMRINIT(<i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNMASSSPFGMRINIT can be called for Fortran programs to create a SUNLINSOL_SPFGMR object for mass matrix linear systems. |
| Arguments | <i>pretype</i> (<i>int*</i>) flag indicating desired preconditioning type <i>maxl</i> (<i>int*</i>) flag indicating Krylov subspace size |
| Return value | <i>ier</i> is a <i>int</i> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function SUNLinSol_SPFGMR. |

The SUNLinSol_SPFGMRSetPrecType, SUNLinSol_SPFGMRSetGStype and SUNLinSol_SPFGMRSetMaxRestarts routines also support Fortran interfaces for the system and mass matrix solvers.

FSUNSPFGMRSETGSTYPE

| | |
|--------------|--|
| Call | FSUNSPFGMRSETGSTYPE(<i>code</i> , <i>gstype</i> , <i>ier</i>) |
| Description | The function FSUNSPFGMRSETGSTYPE can be called for Fortran programs to change the Gram-Schmidt orthogonalization algorithm. |
| Arguments | <i>code</i> (<i>int*</i>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>gstype</i> (<i>int*</i>) flag indicating the desired orthogonalization algorithm. |
| Return value | <i>ier</i> is a <i>int</i> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPFGMRSetGStype for complete further documentation of this routine. |

FSUNMASSSPFGMRSETGSTYPE

| | |
|--------------|--|
| Call | FSUNMASSSPFGMRSETGSTYPE(<i>gstype</i> , <i>ier</i>) |
| Description | The function FSUNMASSSPFGMRSETGSTYPE can be called for Fortran programs to change the Gram-Schmidt orthogonalization algorithm for mass matrix linear systems. |
| Arguments | The arguments are identical to FSUNSPFGMRSETGSTYPE above, except that <i>code</i> is not needed since mass matrix linear systems only arise in ARKODE. |
| Return value | <i>ier</i> is a <i>int</i> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPFGMRSetGStype for complete further documentation of this routine. |

FSUNSPFGMRSETPRECTYPE

| | |
|-------------|--|
| Call | FSUNSPFGMRSETPRECTYPE(<i>code</i> , <i>pretype</i> , <i>ier</i>) |
| Description | The function FSUNSPFGMRSETPRECTYPE can be called for Fortran programs to change the type of preconditioning to use. |
| Arguments | <i>code</i> (<i>int*</i>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>pretype</i> (<i>int*</i>) flag indicating the type of preconditioning to use. |

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPFGMRSetPrecType` for complete further documentation of this routine.

FSUNMASSSPFGMRSETPRECTYPE

Call `FSUNMASSSPFGMRSETPRECTYPE(pretype, ier)`

Description The function `FSUNMASSSPFGMRSETPRECTYPE` can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems.

Arguments The arguments are identical to `FSUNSPFGMRSETPRECTYPE` above, except that **code** is not needed since mass matrix linear systems only arise in ARKODE.

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPFGMRSetPrecType` for complete further documentation of this routine.

FSUNSPFGMRSETMAXRS

Call `FSUNSPFGMRSETMAXRS(code, maxrs, ier)`

Description The function `FSUNSPFGMRSETMAXRS` can be called for Fortran programs to change the maximum number of restarts allowed for SPFGMR.

Arguments **code** (**int***) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).
maxrs (**int***) maximum allowed number of restarts.

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPFGMRSetMaxRestarts` for complete further documentation of this routine.

FSUNMASSSPFGMRSETMAXRS

Call `FSUNMASSSPFGMRSETMAXRS(maxrs, ier)`

Description The function `FSUNMASSSPFGMRSETMAXRS` can be called for Fortran programs to change the maximum number of restarts allowed for SPFGMR for mass matrix linear systems.

Arguments The arguments are identical to `FSUNSPFGMRSETMAXRS` above, except that **code** is not needed since mass matrix linear systems only arise in ARKODE.

Return value **ier** is a **int** return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPFGMRSetMaxRestarts` for complete further documentation of this routine.

8.12.4 SUNLinearSolver_SPFGMR content

The `SUNLINSOL_SPFGMR` module defines the *content* field of a `SUNLinearSolver` as the following structure:

```
struct _SUNLinearSolverContent_SPFGMR {
    int maxl;
    int pretype;
    int gstype;
    int max_restarts;
    int numiters;
```

```

realtype resnorm;
long int last_flag;
ATimesFn ATimes;
void* ATData;
PSetupFn Psetup;
PSolveFn Psolve;
void* PData;
N_Vector s1;
N_Vector s2;
N_Vector *V;
N_Vector *Z;
realtype **Hes;
realtype *givens;
N_Vector xcor;
realtype *yg;
N_Vector vtemp;
};

```

These entries of the *content* field contain the following information:

max1 - number of FGMRES basis vectors to use (default is 5),
pretype - flag for type of preconditioning to employ (default is none),
gstype - flag for type of Gram-Schmidt orthogonalization (default is modified Gram-Schmidt),
max_restarts - number of FGMRES restarts to allow (default is 0),
numiters - number of iterations from the most-recent solve,
resnorm - final linear residual norm from the most-recent solve,
last_flag - last error return flag from an internal function,
ATimes - function pointer to perform Av product,
ATData - pointer to structure for **ATimes**,
Psetup - function pointer to preconditioner setup routine,
Psolve - function pointer to preconditioner solve routine,
PData - pointer to structure for **Psetup** and **Psolve**,
s1, s2 - vector pointers for supplied scaling matrices (default is NULL),
V - the array of Krylov basis vectors $v_1, \dots, v_{\max1+1}$, stored in $V[0], \dots, V[\max1]$. Each v_i is a vector of type **NVECTOR**.,
Z - the array of preconditioned Krylov basis vectors $z_1, \dots, z_{\max1+1}$, stored in $Z[0], \dots, Z[\max1]$. Each z_i is a vector of type **NVECTOR**.,
Hes - the $(\max1 + 1) \times \max1$ Hessenberg matrix. It is stored row-wise so that the (i,j)th element is given by **Hes**[i][j].,
givens - a length $2*\max1$ array which represents the Givens rotation matrices that arise in the FGMRES algorithm. These matrices are F_0, F_1, \dots, F_j , where

$$F_i = \begin{bmatrix} 1 & & & & & & \\ & \ddots & & & & & \\ & & 1 & & & & \\ & & & c_i & -s_i & & \\ & & & s_i & c_i & & \\ & & & & & 1 & \\ & & & & & & \ddots & \\ & & & & & & & 1 \end{bmatrix},$$

are represented in the `givens` vector as `givens[0] = c0, givens[1] = s0, givens[2] = c1, givens[3] = s1, ... givens[2j] = cj, givens[2j+1] = sj.`

`xcor` - a vector which holds the scaled, preconditioned correction to the initial guess,

`yg` - a length `(maxl+1)` array of `realtype` values used to hold “short” vectors (e.g. *y* and *g*),

`vtemp` - temporary vector storage.

8.13 The SUNLinearSolver_SPBCGS implementation

This section describes the SUNLINSOL implementation of the SPBCGS (Scaled, Preconditioned, Bi-Conjugate Gradient, Stabilized [34]) iterative linear solver. The SUNLINSOL_SPBCGS module is designed to be compatible with any NVECTOR implementation that supports a minimal subset of operations (N_VClone, N_VDotProd, N_VScale, N_VLinearSum, N_VProd, N_VDiv, and N_VDestroy). Unlike the SPGMR and SPFGMR algorithms, SPBCGS requires a fixed amount of memory that does not increase with the number of allowed iterations.

To access the SUNLINSOL_SPBCGS module, include the header file `sunlinsol/sunlinsol_spbcgs.h`. We note that the SUNLINSOL_SPBCGS module is accessible from SUNDIALS packages *without* separately linking to the `libsundials_sunlinsolspbcgs` module library.

8.13.1 SUNLinearSolver_SPBCGS description

This solver is constructed to perform the following operations:

- During construction all NVECTOR solver data is allocated, with vectors cloned from a template NVECTOR that is input, and default solver parameters are set.
- User-facing “set” routines may be called to modify default solver parameters.
- Additional “set” routines are called by the SUNDIALS solver that interfaces with SUNLINSOL_SPBCGS to supply the `ATimes`, `PSetup`, and `Psolve` function pointers and `s1` and `s2` scaling vectors.
- In the “initialize” call, the solver parameters are checked for validity.
- In the “setup” call, any non-NULL `PSetup` function is called. Typically, this is provided by the SUNDIALS solver itself, that translates between the generic `PSetup` function and the solver-specific routine (solver-supplied or user-supplied).
- In the “solve” call the SPBCGS iteration is performed. This will include scaling and preconditioning if those options have been supplied.

8.13.2 SUNLinearSolver_SPBCGS functions

The SUNLINSOL_SPBCGS module provides the following user-callable constructor for creating a `SUNLinearSolver` object.

SUNLinSol_SPBCGS

| | |
|-------------|--|
| Call | <code>LS = SUNLinSol_SPBCGS(y, pretype, maxl);</code> |
| Description | The function <code>SUNLinSol_SPBCGS</code> creates and allocates memory for a SPBCGS <code>SUNLinearSolver</code> object. |
| Arguments | <p><code>y</code> (N_Vector) a template for cloning vectors needed within the solver</p> <p><code>pretype</code> (int) flag indicating the desired type of preconditioning, allowed values are:</p> <ul style="list-style-type: none"> • <code>PREC_NONE</code> (0) |

- `PREC_LEFT` (1)
- `PREC_RIGHT` (2)
- `PREC_BOTH` (3)

Any other integer input will result in the default (no preconditioning).

`maxl` (`int`) the number of linear iterations to allow. Values ≤ 0 will result in the default value (5).

Return value This returns a `SUNLinearSolver` object. If either `y` is incompatible then this routine will return `NULL`.

Notes This routine will perform consistency checks to ensure that it is called with a consistent `NVECTOR` implementation (i.e. that it supplies the requisite vector operations). If `y` is incompatible, then this routine will return `NULL`.

We note that some SUNDIALS solvers are designed to only work with left preconditioning (IDA and IDAS) and others with only right preconditioning (KINSOL). While it is possible to configure a `SUNLINSOL_SPBCGS` object to use any of the preconditioning options with these solvers, this use mode is not supported and may result in inferior performance.

Deprecated Name For backward compatibility, the wrapper function `SUNSPBCGS` with identical input and output arguments is also provided.

F2003 Name This function is callable as `FSUNLinSol_SPBCGS` when using the Fortran 2003 interface module.

The `SUNLINSOL_SPBCGS` module defines implementations of all “iterative” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- `SUNLinSolGetType_SPBCGS`
- `SUNLinSolInitialize_SPBCGS`
- `SUNLinSolSetATimes_SPBCGS`
- `SUNLinSolSetPreconditioner_SPBCGS`
- `SUNLinSolSetScalingVectors_SPBCGS`
- `SUNLinSolSetup_SPBCGS`
- `SUNLinSolSolve_SPBCGS`
- `SUNLinSolNumIters_SPBCGS`
- `SUNLinSolResNorm_SPBCGS`
- `SUNLinSolResid_SPBCGS`
- `SUNLinSolLastFlag_SPBCGS`
- `SUNLinSolSpace_SPBCGS`
- `SUNLinSolFree_SPBCGS`

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

The `SUNLINSOL_SPBCGS` module also defines the following additional user-callable functions.

SUNLinSol_SPBCGSSetPrecType

| | |
|-----------------|---|
| Call | <code>retval = SUNLinSol_SPBCGSSetPrecType(LS, pretype);</code> |
| Description | The function <code>SUNLinSol_SPBCGSSetPrecType</code> updates the type of preconditioning to use in the <code>SUNLINSOL_SPBCGS</code> object. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPBCGS</code> object to update <code>pretype</code> (<code>int</code>) flag indicating the desired type of preconditioning, allowed values match those discussed in <code>SUNLinSol_SPBCGS</code> . |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal <code>pretype</code>), <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPBCGSSetPrecType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPBCGSSetPrecType</code> when using the Fortran 2003 interface module. |

SUNLinSol_SPBCGSSetMax1

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_SPBCGSSetMax1(LS, max1);</code> |
| Description | The function <code>SUNLinSol_SPBCGSSetMax1</code> updates the number of linear solver iterations to allow. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPBCGS</code> object to update <code>max1</code> (<code>int</code>) flag indicating the number of iterations to allow. Values ≤ 0 will result in the default value (5). |
| Return value | This routine will return with one of the error codes <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPBCGSSetMax1</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPBCGSSetMax1</code> when using the Fortran 2003 interface module. |

8.13.3 SUNLinearSolver_SPBCGS Fortran interfaces

The `SUNLINSOL_SPBCGS` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTTRAN 2003 interface module

The `fsunlinsol_spgbcs_mod` FORTRAN module defines interfaces to all `SUNLINSOL_SPBCGS` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_SPBCGS` is interfaced as `FSUNLinSol_SPBCGS`.

The FORTRAN 2003 `SUNLINSOL_SPBCGS` interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_spgbcs_mod`, and linking to the library `libsundials_fsunlinsolspgbcs_mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_spgbcs_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunlinsolspgbcs_mod` library.

FORTTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the `SUNLINSOL_SPBCGS` module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNSPBCGSINIT

| | |
|--------------|---|
| Call | FSUNSPBCGSINIT(<i>code</i> , <i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNSPBCGSINIT can be called for Fortran programs to create a SUNLINSOL_SPBCGS object. |
| Arguments | <i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>pretype</i> (int*) flag indicating desired preconditioning type <i>maxl</i> (int*) flag indicating number of iterations to allow |
| Return value | <i>ier</i> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function SUNLinSol_SPBCGS. |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_SPBCGS module includes a Fortran-callable function for creating a SUNLinearSolver mass matrix solver object.

FSUNMASSSPBCGSINIT

| | |
|--------------|---|
| Call | FSUNMASSSPBCGSINIT(<i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNMASSSPBCGSINIT can be called for Fortran programs to create a SUNLINSOL_SPBCGS object for mass matrix linear systems. |
| Arguments | <i>pretype</i> (int*) flag indicating desired preconditioning type <i>maxl</i> (int*) flag indicating number of iterations to allow |
| Return value | <i>ier</i> is a int return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function SUNLinSol_SPBCGS. |

The SUNLinSol_SPBCGSSetPrecType and SUNLinSol_SPBCGSsetMaxl routines also support Fortran interfaces for the system and mass matrix solvers.

FSUNSPBCGSSETPRECTYPE

| | |
|--------------|--|
| Call | FSUNSPBCGSSETPRECTYPE(<i>code</i> , <i>pretype</i> , <i>ier</i>) |
| Description | The function FSUNSPBCGSSETPRECTYPE can be called for Fortran programs to change the type of preconditioning to use. |
| Arguments | <i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>pretype</i> (int*) flag indicating the type of preconditioning to use. |
| Return value | <i>ier</i> is a int return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPBCGSSetPrecType for complete further documentation of this routine. |

FSUNMASSSPBCGSSETPRECTYPE

| | |
|-------------|---|
| Call | FSUNMASSSPBCGSSETPRECTYPE(<i>pretype</i> , <i>ier</i>) |
| Description | The function FSUNMASSSPBCGSSETPRECTYPE can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems. |

| | |
|--------------|---|
| Arguments | The arguments are identical to FSUNSPBCGSSETPRECTYPE above, except that <code>code</code> is not needed since mass matrix linear systems only arise in ARKODE. |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPBCGSSetPrecType for complete further documentation of this routine. |

FSUNSPBCGSSETMAXL

| | |
|--------------|--|
| Call | FSUNSPBCGSSETMAXL(<code>code</code> , <code>maxl</code> , <code>ier</code>) |
| Description | The function FSUNSPBCGSSETMAXL can be called for Fortran programs to change the maximum number of iterations to allow. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <code>maxl</code> (<code>int*</code>) the number of iterations to allow. |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPBCGSSetMaxl for complete further documentation of this routine. |

FSUNMASSSPBCGSSETMAXL

| | |
|--------------|---|
| Call | FSUNMASSSPBCGSSETMAXL(<code>maxl</code> , <code>ier</code>) |
| Description | The function FSUNMASSSPBCGSSETMAXL can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems. |
| Arguments | The arguments are identical to FSUNSPBCGSSETMAXL above, except that <code>code</code> is not needed since mass matrix linear systems only arise in ARKODE. |
| Return value | <code>ier</code> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | See SUNLinSol_SPBCGSSetMaxl for complete further documentation of this routine. |

8.13.4 SUNLinearSolver_SPBCGS content

The SUNLINSOL_SPBCGS module defines the *content* field of a SUNLinearSolver as the following structure:

```
struct _SUNLinearSolverContent_SPBCGS {
    int maxl;
    int pretype;
    int numiters;
    realtype resnorm;
    long int last_flag;
    ATimesFn ATimes;
    void* ATData;
    PSetupFn Psetup;
    PSolveFn Psolve;
    void* PData;
    N_Vector s1;
    N_Vector s2;
    N_Vector r;
    N_Vector r_star;
    N_Vector p;
    N_Vector q;
    N_Vector u;
```

```

    N_Vector Ap;
    N_Vector vtemp;
};

```

These entries of the *content* field contain the following information:

maxl - number of SPBCGS iterations to allow (default is 5),
pretype - flag for type of preconditioning to employ (default is none),
numiters - number of iterations from the most-recent solve,
resnorm - final linear residual norm from the most-recent solve,
last_flag - last error return flag from an internal function,
ATimes - function pointer to perform Av product,
ATData - pointer to structure for **ATimes**,
Psetup - function pointer to preconditioner setup routine,
Psolve - function pointer to preconditioner solve routine,
PData - pointer to structure for **Psetup** and **Psolve**,
s1, s2 - vector pointers for supplied scaling matrices (default is NULL),
r - a NVECTOR which holds the current scaled, preconditioned linear system residual,
r_star - a NVECTOR which holds the initial scaled, preconditioned linear system residual,
p, q, u, Ap, vtemp - NVECTORS used for workspace by the SPBCGS algorithm.

8.14 The SUNLinearSolver_SPTFQMR implementation

This section describes the SUNLINSOL implementation of the SPTFQMR (Scaled, Preconditioned, Transpose-Free Quasi-Minimum Residual [20]) iterative linear solver. The SUNLINSOL_SPTFQMR module is designed to be compatible with any NVECTOR implementation that supports a minimal subset of operations (**N_VClone**, **N_VDotProd**, **N_VScale**, **N_VLinearSum**, **N_VProd**, **N_VConst**, **N_VDiv**, and **N_VDestroy**). Unlike the SPGMR and SPFGMR algorithms, SPTFQMR requires a fixed amount of memory that does not increase with the number of allowed iterations.

To access the SUNLINSOL_SPTFQMR module, include the header file `sunlinsol/sunlinsol_sptfqmr.h`. We note that the SUNLINSOL_SPTFQMR module is accessible from SUNDIALS packages *without* separately linking to the `libsundials_sunlinsolsptfqmr` module library.

8.14.1 SUNLinearSolver_SPTFQMR description

This solver is constructed to perform the following operations:

- During construction all NVECTOR solver data is allocated, with vectors cloned from a template NVECTOR that is input, and default solver parameters are set.
- User-facing “set” routines may be called to modify default solver parameters.
- Additional “set” routines are called by the SUNDIALS solver that interfaces with SUNLINSOL_SPTFQMR to supply the **ATimes**, **PSetup**, and **Psolve** function pointers and **s1** and **s2** scaling vectors.
- In the “initialize” call, the solver parameters are checked for validity.
- In the “setup” call, any non-NULL **PSetup** function is called. Typically, this is provided by the SUNDIALS solver itself, that translates between the generic **PSetup** function and the solver-specific routine (solver-supplied or user-supplied).
- In the “solve” call the TFQMR iteration is performed. This will include scaling and preconditioning if those options have been supplied.

8.14.2 SUNLinearSolver_SPTFQMR functions

The SUNLINSOL_SPTFQMR module provides the following user-callable constructor for creating a SUNLinearSolver object.

| SUNLinSol_SPTFQMR | |
|-------------------|---|
| Call | LS = SUNLinSol_SPTFQMR(y, pretype, maxl); |
| Description | The function SUNLinSol_SPTFQMR creates and allocates memory for a SPTFQMR SUNLinearSolver object. |
| Arguments | <p>y (N_Vector) a template for cloning vectors needed within the solver</p> <p>pretype (int) flag indicating the desired type of preconditioning, allowed values are:</p> <ul style="list-style-type: none"> • PREC_NONE (0) • PREC_LEFT (1) • PREC_RIGHT (2) • PREC_BOTH (3) <p>Any other integer input will result in the default (no preconditioning).</p> <p>maxl (int) the number of linear iterations to allow. Values ≤ 0 will result in the default value (5).</p> |
| Return value | This returns a SUNLinearSolver object. If either y is incompatible then this routine will return NULL. |
| Notes | <p>This routine will perform consistency checks to ensure that it is called with a consistent NVECTOR implementation (i.e. that it supplies the requisite vector operations). If y is incompatible, then this routine will return NULL.</p> <p>We note that some SUNDIALS solvers are designed to only work with left preconditioning (IDA and IDAS) and others with only right preconditioning (KINSOL). While it is possible to configure a SUNLINSOL_SPTFQMR object to use any of the preconditioning options with these solvers, this use mode is not supported and may result in inferior performance.</p> |
| Deprecated Name | For backward compatibility, the wrapper function SUNSPTFQMR with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as FSUNLinSol_SPTFQMR when using the Fortran 2003 interface module. |

The SUNLINSOL_SPTFQMR module defines implementations of all “iterative” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- SUNLinSolGetType_SPTFQMR
- SUNLinSolInitialize_SPTFQMR
- SUNLinSolSetATimes_SPTFQMR
- SUNLinSolSetPreconditioner_SPTFQMR
- SUNLinSolSetScalingVectors_SPTFQMR
- SUNLinSolSetup_SPTFQMR
- SUNLinSolSolve_SPTFQMR
- SUNLinSolNumIters_SPTFQMR
- SUNLinSolResNorm_SPTFQMR

- SUNLinSolResid_SPTFQMR
- SUNLinSolLastFlag_SPTFQMR
- SUNLinSolSpace_SPTFQMR
- SUNLinSolFree_SPTFQMR

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

The SUNLINSOL_SPTFQMR module also defines the following additional user-callable functions.

SUNLinSol_SPTFQMRSetPrecType

| | |
|-----------------|---|
| Call | <code>retval = SUNLinSol_SPTFQMRSetPrecType(LS, pretype);</code> |
| Description | The function <code>SUNLinSol_SPTFQMRSetPrecType</code> updates the type of preconditioning to use in the <code>SUNLINSOL_SPTFQMR</code> object. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPTFQMR</code> object to update <code>pretype</code> (<code>int</code>) flag indicating the desired type of preconditioning, allowed values match those discussed in <code>SUNLinSol_SPTFQMR</code> . |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal <code>pretype</code>), <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNSPTFQMRSetPrecType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPTFQMRSetPrecType</code> when using the Fortran 2003 interface module. |

SUNLinSol_SPTFQMRSetMaxl

| | |
|--------------|--|
| Call | <code>retval = SUNLinSol_SPTFQMRSetMaxl(LS, maxl);</code> |
| Description | The function <code>SUNLinSol_SPTFQMRSetMaxl</code> updates the number of linear solver iterations to allow. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_SPTFQMR</code> object to update <code>maxl</code> (<code>int</code>) flag indicating the number of iterations to allow; values ≤ 0 will result in the default value (5) |
| Return value | This routine will return with one of the error codes <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| F2003 Name | This function is callable as <code>FSUNLinSol_SPTFQMRSetMaxl</code> when using the Fortran 2003 interface module. |

`SUNSPTFQMRSetMaxl`

8.14.3 SUNLinearSolver_SPTFQMR Fortran interfaces

The `SUNLINSOL_SPTFQMR` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTTRAN 2003 interface module

The `fsunlinsol_sptfqmr_mod` FORTRAN module defines interfaces to all `SUNLINSOL_SPTFQMR` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_SPTFQMR` is interfaced as `FSUNLinSol_SPTFQMR`.

The FORTRAN 2003 SUNLINSOL_SPTFGMR interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_sptfqmr_mod`, and linking to the library `libsundials_fsunlinsolsptfqmr_mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_sptfqmr_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunlinsolsptfqmr_mod` library.

FORTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the SUNLINSOL_SPTFQMR module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNSPTFQMRINIT

| | |
|--------------|---|
| Call | FSUNSPTFQMRINIT(<i>code</i> , <i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNSPTFQMRINIT can be called for Fortran programs to create a SUNLINSOL_SPTFQMR object. |
| Arguments | <i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). <i>pretype</i> (int*) flag indicating desired preconditioning type <i>maxl</i> (int*) flag indicating number of iterations to allow |
| Return value | <i>ier</i> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function <code>SUNLinSol_SPTFQMR</code> . |

Additionally, when using ARKODE with a non-identity mass matrix, the SUNLINSOL_SPTFQMR module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

FSUNMASSSPTFQMRINIT

| | |
|--------------|--|
| Call | FSUNMASSSPTFQMRINIT(<i>pretype</i> , <i>maxl</i> , <i>ier</i>) |
| Description | The function FSUNMASSSPTFQMRINIT can be called for Fortran programs to create a SUNLINSOL_SPTFQMR object for mass matrix linear systems. |
| Arguments | <i>pretype</i> (int*) flag indicating desired preconditioning type <i>maxl</i> (int*) flag indicating number of iterations to allow |
| Return value | <i>ier</i> is a <code>int</code> return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |
| Notes | This routine must be called <i>after</i> the NVECTOR object has been initialized. Allowable values for <i>pretype</i> and <i>maxl</i> are the same as for the C function <code>SUNLinSol_SPTFQMR</code> . |

The `SUNLinSol_SPTFQMRSetPrecType` and `SUNLinSol_SPTFQMRSetMaxl` routines also support Fortran interfaces for the system and mass matrix solvers.

FSUNSPTFQMRSETPRECTYPE

| | |
|-------------|---|
| Call | FSUNSPTFQMRSETPRECTYPE(<i>code</i> , <i>pretype</i> , <i>ier</i>) |
| Description | The function FSUNSPTFQMRSETPRECTYPE can be called for Fortran programs to change the type of preconditioning to use. |
| Arguments | <i>code</i> (int*) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE). |

`pretype (int*)` flag indicating the type of preconditioning to use.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPTFQMRSetPrecType` for complete further documentation of this routine.

FSUNMASSSPTFQMRSETPRECTYPE

Call `FSUNMASSSPTFQMRSETPRECTYPE(pretype, ier)`

Description The function `FSUNMASSSPTFQMRSETPRECTYPE` can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems.

Arguments The arguments are identical to `FSUNSPTFQMRSETPRECTYPE` above, except that `code` is not needed since mass matrix linear systems only arise in `ARKODE`.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPTFQMRSetPrecType` for complete further documentation of this routine.

FSUNSPTFQMRSETMAXL

Call `FSUNSPTFQMRSETMAXL(code, maxl, ier)`

Description The function `FSUNSPTFQMRSETMAXL` can be called for Fortran programs to change the maximum number of iterations to allow.

Arguments `code (int*)` is an integer input specifying the solver id (1 for `CVODE`, 2 for `IDA`, 3 for `KINSOL`, and 4 for `ARKODE`).
`maxl (int*)` the number of iterations to allow.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPTFQMRSetMaxl` for complete further documentation of this routine.

FSUNMASSSPTFQMRSETMAXL

Call `FSUNMASSSPTFQMRSETMAXL(maxl, ier)`

Description The function `FSUNMASSSPTFQMRSETMAXL` can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems.

Arguments The arguments are identical to `FSUNSPTFQMRSETMAXL` above, except that `code` is not needed since mass matrix linear systems only arise in `ARKODE`.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See `SUNLinSol_SPTFQMRSetMaxl` for complete further documentation of this routine.

8.14.4 SUNLinearSolver_SPTFQMR content

The `SUNLINSOL_SPTFQMR` module defines the *content* field of a `SUNLinearSolver` as the following structure:

```
struct _SUNLinearSolverContent_SPTFQMR {
    int maxl;
    int pretype;
    int numiters;
    realtype resnorm;
```

```

long int last_flag;
ATimesFn ATimes;
void* ATData;
PSetupFn Psetup;
PSolveFn Psolve;
void* PData;
N_Vector s1;
N_Vector s2;
N_Vector r_star;
N_Vector q;
N_Vector d;
N_Vector v;
N_Vector p;
N_Vector *r;
N_Vector u;
N_Vector vtemp1;
N_Vector vtemp2;
N_Vector vtemp3;
};

```

These entries of the *content* field contain the following information:

maxl - number of TFQMR iterations to allow (default is 5),
pretype - flag for type of preconditioning to employ (default is none),
numiters - number of iterations from the most-recent solve,
resnorm - final linear residual norm from the most-recent solve,
last_flag - last error return flag from an internal function,
ATimes - function pointer to perform Av product,
ATData - pointer to structure for **ATimes**,
Psetup - function pointer to preconditioner setup routine,
Psolve - function pointer to preconditioner solve routine,
PData - pointer to structure for **Psetup** and **Psolve**,
s1, s2 - vector pointers for supplied scaling matrices (default is NULL),
r_star - a NVECTOR which holds the initial scaled, preconditioned linear system residual,
q, d, v, p, u - NVECTORS used for workspace by the SPTFQMR algorithm,
r - array of two NVECTORS used for workspace within the SPTFQMR algorithm,
vtemp1, vtemp2, vtemp3 - temporary vector storage.

8.15 The SUNLinearSolver_PCG implementation

This section describes the SUNLINSOL implementation of the PCG (Preconditioned Conjugate Gradient [21]) iterative linear solver. The SUNLINSOL_PCG module is designed to be compatible with any NVECTOR implementation that supports a minimal subset of operations (**N_VClone**, **N_VDotProd**, **N_VScale**, **N_VLinearSum**, **N_VProd**, and **N_VDestroy**). Unlike the SPGMR and SPFGMR algorithms, PCG requires a fixed amount of memory that does not increase with the number of allowed iterations.

To access the SUNLINSOL_PCG module, include the header file `sunlinsol/sunlinsol_pcg.h`. We note that the SUNLINSOL_PCG module is accessible from SUNDIALS packages *without* separately linking to the `libsundials_sunlinsolpcg` module library.

8.15.1 SUNLinearSolver_PCG description

Unlike all of the other iterative linear solvers supplied with SUNDIALS, PCG should only be used on *symmetric* linear systems (e.g. mass matrix linear systems encountered in ARKODE). As a result, the explanation of the role of scaling and preconditioning matrices given in general must be modified in this scenario. The PCG algorithm solves a linear system $Ax = b$ where A is a symmetric ($A^T = A$), real-valued matrix. Preconditioning is allowed, and is applied in a symmetric fashion on both the right and left. Scaling is also allowed and is applied symmetrically. We denote the preconditioner and scaling matrices as follows:

- P is the preconditioner (assumed symmetric),
- S is a diagonal matrix of scale factors.

The matrices A and P are not required explicitly; only routines that provide A and P^{-1} as operators are required. The diagonal of the matrix S is held in a single NVECTOR, supplied by the user.

In this notation, PCG applies the underlying CG algorithm to the equivalent transformed system

$$\tilde{A}\tilde{x} = \tilde{b} \quad (8.4)$$

where

$$\begin{aligned} \tilde{A} &= SP^{-1}AP^{-1}S, \\ \tilde{b} &= SP^{-1}b, \\ \tilde{x} &= S^{-1}Px. \end{aligned} \quad (8.5)$$

The scaling matrix must be chosen so that the vectors $SP^{-1}b$ and $S^{-1}Px$ have dimensionless components.

The stopping test for the PCG iterations is on the L2 norm of the scaled preconditioned residual:

$$\begin{aligned} &\|\tilde{b} - \tilde{A}\tilde{x}\|_2 < \delta \\ \Leftrightarrow & \\ &\|SP^{-1}b - SP^{-1}Ax\|_2 < \delta \\ \Leftrightarrow & \\ &\|P^{-1}b - P^{-1}Ax\|_S < \delta \end{aligned}$$

where $\|v\|_S = \sqrt{v^T S^T S v}$, with an input tolerance δ .

This solver is constructed to perform the following operations:

- During construction all NVECTOR solver data is allocated, with vectors cloned from a template NVECTOR that is input, and default solver parameters are set.
- User-facing “set” routines may be called to modify default solver parameters.
- Additional “set” routines are called by the SUNDIALS solver that interfaces with SUNLINSOL_PCG to supply the **ATimes**, **PSetup**, and **Psolve** function pointers and **s** scaling vector.
- In the “initialize” call, the solver parameters are checked for validity.
- In the “setup” call, any non-NULL **PSetup** function is called. Typically, this is provided by the SUNDIALS solver itself, that translates between the generic **PSetup** function and the solver-specific routine (solver-supplied or user-supplied).
- In the “solve” call the PCG iteration is performed. This will include scaling and preconditioning if those options have been supplied.

8.15.2 SUNLinearSolver_PCG functions

The SUNLINSOL_PCG module provides the following user-callable constructor for creating a SUNLinearSolver object.

SUNLinSol_PCG

| | |
|-----------------|---|
| Call | LS = SUNLinSol_PCG(y, pretype, maxl); |
| Description | The function SUNLinSol_PCG creates and allocates memory for a PCG SUNLinearSolver object. |
| Arguments | <p>y (N_Vector) a template for cloning vectors needed within the solver</p> <p>pretype (int) flag indicating whether to use preconditioning. Since the PCG algorithm is designed to only support symmetric preconditioning, then any of the pretype inputs PREC_LEFT (1), PREC_RIGHT (2), or PREC_BOTH (3) will result in use of the symmetric preconditioner; any other integer input will result in the default (no preconditioning).</p> <p>maxl (int) the number of linear iterations to allow; values ≤ 0 will result in the default value (5).</p> |
| Return value | This returns a SUNLinearSolver object. If either y is incompatible then this routine will return NULL. |
| Notes | <p>This routine will perform consistency checks to ensure that it is called with a consistent NVECTOR implementation (i.e. that it supplies the requisite vector operations). If y is incompatible, then this routine will return NULL.</p> <p>Although some SUNDIALS solvers are designed to only work with left preconditioning (IDA and IDAS) and others with only right preconditioning (KINSOL), PCG should <i>only</i> be used with these packages when the linear systems are known to be <i>symmetric</i>. Since the scaling of matrix rows and columns must be identical in a symmetric matrix, symmetric preconditioning should work appropriately even for packages designed with one-sided preconditioning in mind.</p> |
| Deprecated Name | For backward compatibility, the wrapper function SUNPCG with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as FSUNLinSol_PCG when using the Fortran 2003 interface module. |

The SUNLINSOL_PCG module defines implementations of all “iterative” linear solver operations listed in Sections 8.1.1 – 8.1.3:

- SUNLinSolGetType_PCG
- SUNLinSolInitialize_PCG
- SUNLinSolSetATimes_PCG
- SUNLinSolSetPreconditioner_PCG
- SUNLinSolSetScalingVectors_PCG – since PCG only supports symmetric scaling, the second NVECTOR argument to this function is ignored
- SUNLinSolSetup_PCG
- SUNLinSolSolve_PCG
- SUNLinSolNumIters_PCG
- SUNLinSolResNorm_PCG
- SUNLinSolResid_PCG

- SUNLinSolLastFlag_PCG
- SUNLinSolSpace_PCG
- SUNLinSolFree_PCG

All of the listed operations are callable via the FORTRAN 2003 interface module by prepending an ‘F’ to the function name.

The SUNLINSOL_PCG module also defines the following additional user-callable functions.

SUNLinSol_PCGSetPrecType

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_PCGSetPrecType(LS, pretype);</code> |
| Description | The function <code>SUNLinSol_PCGSetPrecType</code> updates the flag indicating use of preconditioning in the <code>SUNLINSOL_PCG</code> object. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_PCG</code> object to update <code>pretype</code> (<code>int</code>) flag indicating use of preconditioning, allowed values match those discussed in <code>SUNLinSol_PCG</code> . |
| Return value | This routine will return with one of the error codes <code>SUNLS_ILL_INPUT</code> (illegal <code>pretype</code>), <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNPCGSetPrecType</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_PCGSetPrecType</code> when using the Fortran 2003 interface module. |

SUNLinSol_PCGSetMax1

| | |
|-----------------|--|
| Call | <code>retval = SUNLinSol_PCGSetMax1(LS, max1);</code> |
| Description | The function <code>SUNLinSol_PCGSetMax1</code> updates the number of linear solver iterations to allow. |
| Arguments | <code>LS</code> (<code>SUNLinearSolver</code>) the <code>SUNLINSOL_PCG</code> object to update <code>max1</code> (<code>int</code>) flag indicating the number of iterations to allow; values ≤ 0 will result in the default value (5) |
| Return value | This routine will return with one of the error codes <code>SUNLS_MEM_NULL</code> (<code>S</code> is <code>NULL</code>) or <code>SUNLS_SUCCESS</code> . |
| Deprecated Name | For backward compatibility, the wrapper function <code>SUNPCGSetMax1</code> with identical input and output arguments is also provided. |
| F2003 Name | This function is callable as <code>FSUNLinSol_PCGSetMax1</code> when using the Fortran 2003 interface module. |

8.15.3 SUNLinearSolver_PCG Fortran interfaces

The `SUNLINSOL_PCG` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTTRAN 2003 interface module

The `fsunlinsol_pcg_mod` FORTRAN module defines interfaces to all `SUNLINSOL_PCG` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNLinSol_PCG` is interfaced as `FSUNLinSol_PCG`.

The FORTRAN 2003 SUNLINSOL_PCG interface module can be accessed with the `use` statement, i.e. `use fsunlinsol_pcg_mod`, and linking to the library `libsundials.fsunlinsolpcg_mod.lib` in addition to the C library. For details on where the library and module file `fsunlinsol_pcg_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials.fsunlinsolpcg_mod` library.

FORTRAN 77 interface functions

For solvers that include a FORTRAN 77 interface module, the SUNLINSOL_PCG module also includes a Fortran-callable function for creating a `SUNLinearSolver` object.

FSUNPCGINIT

Call `FSUNPCGINIT(code, pretype, maxl, ier)`

Description The function `FSUNPCGINIT` can be called for Fortran programs to create a `SUNLINSOL_PCG` object.

Arguments `code` (`int*`) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).
`pretype` (`int*`) flag indicating desired preconditioning type
`maxl` (`int*`) flag indicating number of iterations to allow

Return value `ier` is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes This routine must be called *after* the `NVECTOR` object has been initialized.
Allowable values for `pretype` and `maxl` are the same as for the C function `SUNLinSol_PCG`.
Additionally, when using ARKODE with a non-identity mass matrix, the `SUNLINSOL_PCG` module includes a Fortran-callable function for creating a `SUNLinearSolver` mass matrix solver object.

FSUNMASSPCGINIT

Call `FSUNMASSPCGINIT(pretype, maxl, ier)`

Description The function `FSUNMASSPCGINIT` can be called for Fortran programs to create a `SUNLINSOL_PCG` object for mass matrix linear systems.

Arguments `pretype` (`int*`) flag indicating desired preconditioning type
`maxl` (`int*`) flag indicating number of iterations to allow

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes This routine must be called *after* the `NVECTOR` object has been initialized.
Allowable values for `pretype` and `maxl` are the same as for the C function `SUNLinSol_PCG`.
The `SUNLinSol_PCGSetPrecType` and `SUNLinSol_PCGSetMaxl` routines also support Fortran interfaces for the system and mass matrix solvers.

FSUNPCGSETPRECTYPE

Call `FSUNPCGSETPRECTYPE(code, pretype, ier)`

Description The function `FSUNPCGSETPRECTYPE` can be called for Fortran programs to change the type of preconditioning to use.

Arguments `code` (`int*`) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).
`pretype` (`int*`) flag indicating the type of preconditioning to use.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See SUNLinSol_PCGSetPrecType for complete further documentation of this routine.

FSUNMASSPCGSETPRECTYPE

Call FSUNMASSPCGSETPRECTYPE(prettype, ier)

Description The function FSUNMASSPCGSETPRECTYPE can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems.

Arguments The arguments are identical to FSUNPCGSETPRECTYPE above, except that `code` is not needed since mass matrix linear systems only arise in ARKODE.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See SUNLinSol_PCGSetPrecType for complete further documentation of this routine.

FSUNPCGSETMAXL

Call FSUNPCGSETMAXL(code, maxl, ier)

Description The function FSUNPCGSETMAXL can be called for Fortran programs to change the maximum number of iterations to allow.

Arguments `code` (`int*`) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, 3 for KINSOL, and 4 for ARKODE).
`maxl` (`int*`) the number of iterations to allow.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See SUNLinSol_PCGSetMaxl for complete further documentation of this routine.

FSUNMASSPCGSETMAXL

Call FSUNMASSPCGSETMAXL(maxl, ier)

Description The function FSUNMASSPCGSETMAXL can be called for Fortran programs to change the type of preconditioning for mass matrix linear systems.

Arguments The arguments are identical to FSUNPCGSETMAXL above, except that `code` is not needed since mass matrix linear systems only arise in ARKODE.

Return value `ier` is a `int` return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure.

Notes See SUNLinSol_PCGSetMaxl for complete further documentation of this routine.

8.15.4 SUNLinearSolver_PCG content

The SUNLINSOL_PCG module defines the *content* field of a SUNLinearSolver as the following structure:

```
struct _SUNLinearSolverContent_PCG {
    int maxl;
    int prettype;
    int numiters;
    realtype resnorm;
    long int last_flag;
    ATimesFn ATimes;
    void* ATData;
    PSetupFn Psetup;
    PSolveFn Psolve;
    void* PData;
```

```

    N_Vector s;
    N_Vector r;
    N_Vector p;
    N_Vector z;
    N_Vector Ap;
};

```

These entries of the *content* field contain the following information:

```

maxl      - number of PCG iterations to allow (default is 5),
pretype   - flag for use of preconditioning (default is none),
numiters  - number of iterations from the most-recent solve,
resnorm   - final linear residual norm from the most-recent solve,
last_flag - last error return flag from an internal function,
ATimes    - function pointer to perform  $Av$  product,
ATData    - pointer to structure for ATimes,
Psetup    - function pointer to preconditioner setup routine,
Psolve    - function pointer to preconditioner solve routine,
PData     - pointer to structure for Psetup and Psolve,
s         - vector pointer for supplied scaling matrix (default is NULL),
r         - a NVECTOR which holds the preconditioned linear system residual,
p, z, Ap  - NVECTORS used for workspace by the PCG algorithm.

```

8.16 SUNLinearSolver Examples

There are `SUNLinearSolver` examples that may be installed for each implementation; these make use of the functions in `test_sunlinsol.c`. These example functions show simple usage of the `SUNLinearSolver` family of functions. The inputs to the examples depend on the linear solver type, and are output to `stdout` if the example is run without the appropriate number of command-line arguments.

The following is a list of the example functions in `test_sunlinsol.c`:

- `Test_SUNLinSolGetType`: Verifies the returned solver type against the value that should be returned.
- `Test_SUNLinSolInitialize`: Verifies that `SUNLinSolInitialize` can be called and returns successfully.
- `Test_SUNLinSolSetup`: Verifies that `SUNLinSolSetup` can be called and returns successfully.
- `Test_SUNLinSolSolve`: Given a `SUNMATRIX` object A , `NVECTOR` objects x and b (where $Ax = b$) and a desired solution tolerance `tol`, this routine clones x into a new vector y , calls `SUNLinSolSolve` to fill y as the solution to $Ay = b$ (to the input tolerance), verifies that each entry in x and y match to within $10 * tol$, and overwrites x with y prior to returning (in case the calling routine would like to investigate further).
- `Test_SUNLinSolSetATimes` (iterative solvers only): Verifies that `SUNLinSolSetATimes` can be called and returns successfully.
- `Test_SUNLinSolSetPreconditioner` (iterative solvers only): Verifies that `SUNLinSolSetPreconditioner` can be called and returns successfully.
- `Test_SUNLinSolSetScalingVectors` (iterative solvers only): Verifies that `SUNLinSolSetScalingVectors` can be called and returns successfully.

- `Test_SUNLinSolLastFlag`: Verifies that `SUNLinSolLastFlag` can be called, and outputs the result to `stdout`.
- `Test_SUNLinSolNumIters` (iterative solvers only): Verifies that `SUNLinSolNumIters` can be called, and outputs the result to `stdout`.
- `Test_SUNLinSolResNorm` (iterative solvers only): Verifies that `SUNLinSolResNorm` can be called, and that the result is non-negative.
- `Test_SUNLinSolResid` (iterative solvers only): Verifies that `SUNLinSolResid` can be called.
- `Test_SUNLinSolSpace` verifies that `SUNLinSolSpace` can be called, and outputs the results to `stdout`.

We'll note that these tests should be performed in a particular order. For either direct or iterative linear solvers, `Test_SUNLinSolInitialize` must be called before `Test_SUNLinSolSetup`, which must be called before `Test_SUNLinSolSolve`. Additionally, for iterative linear solvers `Test_SUNLinSolSetATimes`, `Test_SUNLinSolSetPreconditioner` and `Test_SUNLinSolSetScalingVectors` should be called before `Test_SUNLinSolInitialize`; similarly `Test_SUNLinSolNumIters`, `Test_SUNLinSolResNorm` and `Test_SUNLinSolResid` should be called after `Test_SUNLinSolSolve`. These are called in the appropriate order in all of the example problems.

Chapter 9

Description of the SUNNonlinearSolver module

SUNDIALS time integration packages are written in terms of generic nonlinear solver operations defined by the SUNNONLINSOL API and implemented by a particular SUNNONLINSOL module of type `SUNNonlinearSolver`. Users can supply their own SUNNONLINSOL module, or use one of the modules provided with SUNDIALS.

The time integrators in SUNDIALS specify a default nonlinear solver module and as such this chapter is intended for users that wish to use a non-default nonlinear solver module or would like to provide their own nonlinear solver implementation. Users interested in using a non-default solver module may skip the description of the SUNNONLINSOL API in section 9.1 and proceed to the subsequent sections in this chapter that describe the SUNNONLINSOL modules provided with SUNDIALS.

For users interested in providing their own SUNNONLINSOL module, the following section presents the SUNNONLINSOL API and its implementation beginning with the definition of SUNNONLINSOL functions in sections 9.1.1 – 9.1.3. This is followed by the definition of functions supplied to a nonlinear solver implementation in section 9.1.4. A table of nonlinear solver return codes is given in section 9.1.5. The `SUNNonlinearSolver` type and the generic SUNNONLINSOL module are defined in section 9.1.6. Section 9.1.7 describes how SUNNONLINSOL models interface with SUNDIALS integrators providing sensitivity analysis capabilities (CVODES and IDAS). Finally, section 9.1.8 lists the requirements for supplying a custom SUNNONLINSOL module. Users wishing to supply their own SUNNONLINSOL module are encouraged to use the SUNNONLINSOL implementations provided with SUNDIALS as a template for supplying custom nonlinear solver modules.

9.1 The SUNNonlinearSolver API

The SUNNONLINSOL API defines several nonlinear solver operations that enable SUNDIALS integrators to utilize any SUNNONLINSOL implementation that provides the required functions. These functions can be divided into three categories. The first are the core nonlinear solver functions. The second group of functions consists of set routines to supply the nonlinear solver with functions provided by the SUNDIALS time integrators and to modify solver parameters. The final group consists of get routines for retrieving nonlinear solver statistics. All of these functions are defined in the header file `sundials/sundials_nonlinearsolver.h`.

9.1.1 SUNNonlinearSolver core functions

The core nonlinear solver functions consist of two required functions to get the nonlinear solver type (`SUNNonlinSolGetType`) and solve the nonlinear system (`SUNNonlinSolSolve`). The remaining three functions for nonlinear solver initialization (`SUNNonlinSolInitialization`), setup (`SUNNonlinSolSetup`), and destruction (`SUNNonlinSolFree`) are optional.

SUNNonlinSolGetType

Call `type = SUNNonlinSolGetType(NLS);`

Description The *required* function `SUNNonlinSolGetType` returns nonlinear solver type.

Arguments `NLS` (`SUNNonlinearSolver`) a `SUNNONLINSOL` object.

Return value The return value `type` (of type `int`) will be one of the following:

`SUNNONLINEARSOLVER_ROOTFIND` 0, the `SUNNONLINSOL` module solves $F(y) = 0$.
`SUNNONLINEARSOLVER_FIXEDPOINT` 1, the `SUNNONLINSOL` module solves $G(y) = y$.

SUNNonlinSolInitialize

Call `retval = SUNNonlinSolInitialize(NLS);`

Description The *optional* function `SUNNonlinSolInitialize` performs nonlinear solver initialization and may perform any necessary memory allocations.

Arguments `NLS` (`SUNNonlinearSolver`) a `SUNNONLINSOL` object.

Return value The return value `retval` (of type `int`) is zero for a successful call and a negative value for a failure.

Notes It is assumed all solver-specific options have been set prior to calling `SUNNonlinSolInitialize`. `SUNNONLINSOL` implementations that do not require initialization may set this operation to `NULL`.

SUNNonlinSolSetup

Call `retval = SUNNonlinSolSetup(NLS, y, mem);`

Description The *optional* function `SUNNonlinSolSetup` performs any solver setup needed for a nonlinear solve.

Arguments `NLS` (`SUNNonlinearSolver`) a `SUNNONLINSOL` object.

`y` (`N_Vector`) the initial iteration passed to the nonlinear solver.

`mem` (`void *`) the SUNDIALS integrator memory structure.

Return value The return value `retval` (of type `int`) is zero for a successful call and a negative value for a failure.

Notes SUNDIALS integrators call `SUNNonlinSolSetup` before each step attempt. `SUNNONLINSOL` implementations that do not require setup may set this operation to `NULL`.

SUNNonlinSolSolve

Call `retval = SUNNonlinSolSolve(NLS, y0, y, w, tol, callLSetup, mem);`

Description The *required* function `SUNNonlinSolSolve` solves the nonlinear system $F(y) = 0$ or $G(y) = y$.

Arguments `NLS` (`SUNNonlinearSolver`) a `SUNNONLINSOL` object.

`y0` (`N_Vector`) the initial iterate for the nonlinear solve. This *must* remain unchanged throughout the solution process.

`y` (`N_Vector`) the solution to the nonlinear system.

`w` (`N_Vector`) the solution error weight vector used for computing weighted error norms.

`tol` (`realtype`) the requested solution tolerance in the weighted root-mean-squared norm.

`callLSetup` (`booleantype`) a flag indicating that the integrator recommends for the linear solver setup function to be called.

mem (void *) the SUNDIALS integrator memory structure.

Return value The return value **retval** (of type **int**) is zero for a successful solve, a positive value for a recoverable error, and a negative value for an unrecoverable error.

SUNNonlinSolFree

Call **retval** = SUNNonlinSolFree(NLS);

Description The *optional* function **SUNNonlinSolFree** frees any memory allocated by the nonlinear solver.

Arguments **NLS** (**SUNNonlinearSolver**) a SUNNONLINSOL object.

Return value The return value **retval** (of type **int**) should be zero for a successful call, and a negative value for a failure. SUNNONLINSOL implementations that do not allocate data may set this operation to **NULL**.

9.1.2 SUNNonlinearSolver set functions

The following set functions are used to supply nonlinear solver modules with functions defined by the SUNDIALS integrators and to modify solver parameters. Only the routine for setting the nonlinear system defining function (**SUNNonlinSolSetSysFn**) is required. All other set functions are optional.

SUNNonlinSolSetSysFn

Call **retval** = SUNNonlinSolSetSysFn(NLS, SysFn);

Description The *required* function **SUNNonlinSolSetSysFn** is used to provide the nonlinear solver with the function defining the nonlinear system. This is the function $F(y)$ in $F(y) = 0$ for **SUNNONLINEARSOLVER_ROOTFIND** modules or $G(y)$ in $G(y) = y$ for **SUNNONLINEARSOLVER_FIXEDPOINT** modules.

Arguments **NLS** (**SUNNonlinearSolver**) a SUNNONLINSOL object.

SysFn (**SUNNonlinSolSysFn**) the function defining the nonlinear system. See section 9.1.4 for the definition of **SUNNonlinSolSysFn**.

Return value The return value **retval** (of type **int**) should be zero for a successful call, and a negative value for a failure.

SUNNonlinSolSetLSetupFn

Call **retval** = SUNNonlinSolSetLSetupFn(NLS, LSetupFn);

Description The *optional* function **SUNNonlinSolLSetupFn** is called by SUNDIALS integrators to provide the nonlinear solver with access to its linear solver setup function.

Arguments **NLS** (**SUNNonlinearSolver**) a SUNNONLINSOL object.

LSetupFn (**SUNNonlinSolLSetupFn**) a wrapper function to the SUNDIALS integrator's linear solver setup function. See section 9.1.4 for the definition of **SUNNonlinLSetupFn**.

Return value The return value **retval** (of type **int**) should be zero for a successful call, and a negative value for a failure.

Notes The **SUNNonlinLSetupFn** function sets up the linear system $Ax = b$ where $A = \frac{\partial F}{\partial y}$ is the linearization of the nonlinear residual function $F(y) = 0$ (when using **SUNLINSOL** direct linear solvers) or calls the user-defined preconditioner setup function (when using **SUNLINSOL** iterative linear solvers). SUNNONLINSOL implementations that do not require solving this system, do not utilize **SUNLINSOL** linear solvers, or use **SUNLINSOL** linear solvers that do not require setup may set this operation to **NULL**.

SUNNonlinSolSetLSolveFn

| | |
|--------------|--|
| Call | <code>retval = SUNNonlinSolSetLSolveFn(NLS, LSolveFn);</code> |
| Description | The <i>optional</i> function <code>SUNNonlinSolSetLSolveFn</code> is called by SUNDIALS integrators to provide the nonlinear solver with access to its linear solver solve function. |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a SUNNONLINSOL object <code>LSolveFn</code> (<code>SUNNonlinSolLSolveFn</code>) a wrapper function to the SUNDIALS integrator's linear solver solve function. See section 9.1.4 for the definition of <code>SUNNonlinSolLSolveFn</code> . |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |
| Notes | The <code>SUNNonlinLSolveFn</code> function solves the linear system $Ax = b$ where $A = \frac{\partial F}{\partial y}$ is the linearization of the nonlinear residual function $F(y) = 0$. SUNNONLINSOL implementations that do not require solving this system or do not use SUNLINSOL linear solvers may set this operation to NULL. |

SUNNonlinSolSetConvTestFn

| | |
|--------------|--|
| Call | <code>retval = SUNNonlinSolSetConvTestFn(NLS, CTestFn);</code> |
| Description | The <i>optional</i> function <code>SUNNonlinSolSetConvTestFn</code> is used to provide the nonlinear solver with a function for determining if the nonlinear solver iteration has converged. This is typically called by SUNDIALS integrators to define their nonlinear convergence criteria, but may be replaced by the user. |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a SUNNONLINSOL object. <code>CTestFn</code> (<code>SUNNonlineSolConvTestFn</code>) a SUNDIALS integrator's nonlinear solver convergence test function. See section 9.1.4 for the definition of <code>SUNNonlinSolConvTestFn</code> . |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |
| Notes | SUNNONLINSOL implementations utilizing their own convergence test criteria may set this function to NULL. |

SUNNonlinSolSetMaxIters

| | |
|--------------|--|
| Call | <code>retval = SUNNonlinSolSetMaxIters(NLS, maxiters);</code> |
| Description | The <i>optional</i> function <code>SUNNonlinSolSetMaxIters</code> sets the maximum number of nonlinear solver iterations. This is typically called by SUNDIALS integrators to define their default iteration limit, but may be adjusted by the user. |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a SUNNONLINSOL object. <code>maxiters</code> (<code>int</code>) the maximum number of nonlinear iterations. |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure (e.g., <code>maxiters < 1</code>). |

9.1.3 SUNNonlinearSolver get functions

The following get functions allow SUNDIALS integrators to retrieve nonlinear solver statistics. The routines to get the current total number of iterations (`SUNNonlinSolGetNumIters`) and number of convergence failures (`SUNNonlinSolGetNumConvFails`) are optional. The routine to get the current nonlinear solver iteration (`SUNNonlinSolGetCurIter`) is required when using the convergence test provided by the SUNDIALS integrator or by the ARKODE and CVODE linear solver interfaces. Otherwise, `SUNNonlinSolGetCurIter` is optional.

SUNNonlinSolGetNumIters

| | |
|--------------|--|
| Call | <code>retval = SUNNonlinSolGetNumIters(NLS, numiters);</code> |
| Description | The <i>optional</i> function <code>SUNNonlinSolGetNumIters</code> returns the total number of nonlinear solver iterations. This is typically called by the SUNDIALS integrator to store the nonlinear solver statistics, but may also be called by the user. |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a <code>SUNNONLINSOL</code> object <code>numiters</code> (<code>long int*</code>) the total number of nonlinear solver iterations. |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |

SUNNonlinSolGetCurIter

| | |
|--------------|---|
| Call | <code>retval = SUNNonlinSolGetCurIter(NLS, iter);</code> |
| Description | The function <code>SUNNonlinSolGetCurIter</code> returns the iteration index of the current nonlinear solve. This function is <i>required</i> when using SUNDIALS integrator-provided convergence tests or when using a <code>SUNLINSOL</code> spils linear solver; otherwise it is <i>optional</i> . |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a <code>SUNNONLINSOL</code> object <code>iter</code> (<code>int*</code>) the nonlinear solver iteration in the current solve starting from zero. |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |

SUNNonlinSolGetNumConvFails

| | |
|--------------|--|
| Call | <code>retval = SUNNonlinSolGetNumConvFails(NLS, nconvfails);</code> |
| Description | The <i>optional</i> function <code>SUNNonlinSolGetNumConvFails</code> returns the total number of nonlinear solver convergence failures. This may be called by the SUNDIALS integrator to store the nonlinear solver statistics, but may also be called by the user. |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a <code>SUNNONLINSOL</code> object <code>nconvfails</code> (<code>long int*</code>) the total number of nonlinear solver convergence failures. |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |

9.1.4 Functions provided by SUNDIALS integrators

To interface with `SUNNONLINSOL` modules, the SUNDIALS integrators supply a variety of routines for evaluating the nonlinear system, calling the `SUNLINSOL` setup and solve functions, and testing the nonlinear iteration for convergence. These integrator-provided routines translate between the user-supplied ODE or DAE systems and the generic interfaces to the nonlinear or linear systems of equations that result in their solution. The types for functions provided to a `SUNNONLINSOL` module are defined in the header file `sundials/sundials_nonlinearsolver.h`, and are described below.

SUNNonlinSolSysFn

| | |
|------------|--|
| Definition | <code>typedef int (*SUNNonlinSolSysFn)(N_Vector y, N_Vector F, void* mem);</code> |
| Purpose | These functions evaluate the nonlinear system $F(y)$ for <code>SUNNONLINEARSOLVER_ROOTFIND</code> type modules or $G(y)$ for <code>SUNNONLINEARSOLVER_FIXEDPOINT</code> type modules. Memory for <code>F</code> must be allocated prior to calling this function. The vector <code>y</code> <i>must</i> be left unchanged. |
| Arguments | <code>y</code> is the state vector at which the nonlinear system should be evaluated. <code>F</code> is the output vector containing $F(y)$ or $G(y)$, depending on the solver type. |

`mem` is the SUNDIALS integrator memory structure.

Return value The return value `retval` (of type `int`) is zero for a successful solve, a positive value for a recoverable error, and a negative value for an unrecoverable error.

SUNNonlinSolSetupFn

Definition `typedef int (*SUNNonlinSolSetupFn)(N_Vector y, N_Vector F,
booleantype jbad,
booleantype* jcur, void* mem);`

Purpose These functions are wrappers to the SUNDIALS integrator's function for setting up linear solves with SUNLINSOL modules.

Arguments `y` is the state vector at which the linear system should be setup.
`F` is the value of the nonlinear system function at `y`.
`jbad` is an input indicating whether the nonlinear solver believes that A has gone stale (SUNTRUE) or not (SUNFALSE).
`jcur` is an output indicating whether the routine has updated the Jacobian A (SUNTRUE) or not (SUNFALSE).
`mem` is the SUNDIALS integrator memory structure.

Return value The return value `retval` (of type `int`) is zero for a successful solve, a positive value for a recoverable error, and a negative value for an unrecoverable error.

Notes The `SUNNonlinSolSetupFn` function sets up the linear system $Ax = b$ where $A = \frac{\partial F}{\partial y}$ is the linearization of the nonlinear residual function $F(y) = 0$ (when using SUNLINSOL direct linear solvers) or calls the user-defined preconditioner setup function (when using SUNLINSOL iterative linear solvers). SUNNONLINSOL implementations that do not require solving this system, do not utilize SUNLINSOL linear solvers, or use SUNLINSOL linear solvers that do not require setup may ignore these functions.

SUNNonlinSolSolveFn

Definition `typedef int (*SUNNonlinSolSolveFn)(N_Vector y, N_Vector b, void* mem);`

Purpose These functions are wrappers to the SUNDIALS integrator's function for solving linear systems with SUNLINSOL modules.

Arguments `y` is the input vector containing the current nonlinear iteration.
`b` contains the right-hand side vector for the linear solve on input and the solution to the linear system on output.
`mem` is the SUNDIALS integrator memory structure.

Return value The return value `retval` (of type `int`) is zero for a successful solve, a positive value for a recoverable error, and a negative value for an unrecoverable error.

Notes The `SUNNonlinSolSolveFn` function solves the linear system $Ax = b$ where $A = \frac{\partial F}{\partial y}$ is the linearization of the nonlinear residual function $F(y) = 0$. SUNNONLINSOL implementations that do not require solving this system or do not use SUNLINSOL linear solvers may ignore these functions.

SUNNonlinSolConvTestFn

Definition `typedef int (*SUNNonlinSolConvTestFn)(SUNNonlinearSolver NLS, N_Vector y,
N_Vector del, realtype tol,
N_Vector ewt, void* mem);`

Purpose These functions are SUNDIALS integrator-specific convergence tests for nonlinear solvers and are typically supplied by each SUNDIALS integrator, but users may supply custom problem-specific versions as desired.

- Arguments `NLS` is the `SUNNONLINSOL` object.
 `y` is the current nonlinear iterate.
 `del` is the difference between the current and prior nonlinear iterates.
 `tol` is the nonlinear solver tolerance.
 `ewt` is the weight vector used in computing weighted norms.
 `mem` is the SUNDIALS integrator memory structure.
- Return value The return value of this routine will be a negative value if an unrecoverable error occurred or one of the following:
- `SUN-NLS-SUCCESS` the iteration is converged.
 `SUN-NLS-CONTINUE` the iteration has not converged, keep iterating.
 `SUN-NLS-CONV-RECVR` the iteration appears to be diverging, try to recover.
- Notes The tolerance passed to this routine by SUNDIALS integrators is the tolerance in a weighted root-mean-squared norm with error weight vector `ewt`. `SUNNONLINSOL` modules utilizing their own convergence criteria may ignore these functions.

9.1.5 SUNNonlinearSolver return codes

The functions provided to `SUNNONLINSOL` modules by each SUNDIALS integrator, and functions within the SUNDIALS-provided `SUNNONLINSOL` implementations utilize a common set of return codes, shown below in Table 9.1. Here, negative values correspond to non-recoverable failures, positive values to recoverable failures, and zero to a successful call.

Table 9.1: Description of the `SUNNonlinearSolver` return codes

| Name | Value | Description |
|---------------------------------|-------|--|
| <code>SUN-NLS-SUCCESS</code> | 0 | successful call or converged solve |
| <code>SUN-NLS-CONTINUE</code> | 1 | the nonlinear solver is not converged, keep iterating |
| <code>SUN-NLS-CONV-RECVR</code> | 2 | the nonlinear solver appears to be diverging, try to recover |
| <code>SUN-NLS-MEM-NULL</code> | -1 | a memory argument is <code>NULL</code> |
| <code>SUN-NLS-MEM-FAIL</code> | -2 | a memory access or allocation failed |
| <code>SUN-NLS-ILL-INPUT</code> | -3 | an illegal input option was provided |

9.1.6 The generic SUNNonlinearSolver module

SUNDIALS integrators interact with specific `SUNNONLINSOL` implementations through the generic `SUNNONLINSOL` module on which all other `SUNNONLINSOL` implementations are built. The `SUNNonlinearSolver` type is a pointer to a structure containing an implementation-dependent *content* field and an *ops* field. The type `SUNNonlinearSolver` is defined as follows:

```
typedef struct _generic_SUNNonlinearSolver *SUNNonlinearSolver;

struct _generic_SUNNonlinearSolver {
    void *content;
    struct _generic_SUNNonlinearSolver_Ops *ops;
};
```

where the `_generic_SUNNonlinearSolver_Ops` structure is a list of pointers to the various actual nonlinear solver operations provided by a specific implementation. The `_generic_SUNNonlinearSolver_Ops` structure is defined as

```

struct _generic_SUNNonlinearSolver_Ops {
    SUNNonlinearSolver_Type (*gettype)(SUNNonlinearSolver);
    int (*initialize)(SUNNonlinearSolver);
    int (*setup)(SUNNonlinearSolver, N_Vector, void*);
    int (*solve)(SUNNonlinearSolver, N_Vector, N_Vector,
                 N_Vector, realtype, booleantype, void*);
    int (*free)(SUNNonlinearSolver);
    int (*setsysfn)(SUNNonlinearSolver, SUNNonlinSolSysFn);
    int (*setlsetupfn)(SUNNonlinearSolver, SUNNonlinSolLSetupFn);
    int (*setlsolvefn)(SUNNonlinearSolver, SUNNonlinSolLSolveFn);
    int (*setctestfn)(SUNNonlinearSolver, SUNNonlinSolConvTestFn);
    int (*setmaxiters)(SUNNonlinearSolver, int);
    int (*getnumiters)(SUNNonlinearSolver, long int*);
    int (*getcuriter)(SUNNonlinearSolver, int*);
    int (*getnumconvfails)(SUNNonlinearSolver, long int*);
};

```

The generic SUNNONLINSOL module defines and implements the nonlinear solver operations defined in Sections 9.1.1 – 9.1.3. These routines are in fact only wrappers to the nonlinear solver operations provided by a particular SUNNONLINSOL implementation, which are accessed through the ops field of the `SUNNonlinearSolver` structure. To illustrate this point we show below the implementation of a typical nonlinear solver operation from the generic SUNNONLINSOL module, namely `SUNNonlinSolSolve`, which solves the nonlinear system and returns a flag denoting a successful or failed solve:

```

int SUNNonlinSolSolve(SUNNonlinearSolver NLS,
                      N_Vector y0, N_Vector y,
                      N_Vector w, realtype tol,
                      booleantype callLSetup, void* mem)
{
    return((int) NLS->ops->solve(NLS, y0, y, w, tol, callLSetup, mem));
}

```

9.1.7 Usage with sensitivity enabled integrators

When used with SUNDIALS packages that support sensitivity analysis capabilities (e.g., CVODES and IDAS) a special NVECTOR module is used to interface with SUNNONLINSOL modules for solves involving sensitivity vectors stored in an NVECTOR array. As described below, the NVECTOR_SENSWRAPPER module is an NVECTOR implementation where the vector content is an NVECTOR array. This wrapper vector allows SUNNONLINSOL modules to operate on data stored as a collection of vectors.

For all SUNDIALS-provided SUNNONLINSOL modules a special constructor wrapper is provided so users do not need to interact directly with the NVECTOR_SENSWRAPPER module. These constructors follow the naming convention `SUNNonlinSol_***Sens(count,...)` where `***` is the name of the SUNNONLINSOL module, `count` is the size of the vector wrapper, and `...` are the module-specific constructor arguments.

The NVECTOR_SENSWRAPPER module

This section describes the NVECTOR_SENSWRAPPER implementation of an NVECTOR. To access the NVECTOR_SENSWRAPPER module, include the header file `sundials/sundials_nvector_senswrapper.h`.

The NVECTOR_SENSWRAPPER module defines an `N_Vector` implementing all of the standard vectors operations defined in Table 6.2 but with some changes to how operations are computed in order to accommodate operating on a collection of vectors.

1. Element-wise vector operations are computed on a vector-by-vector basis. For example, the linear sum of two wrappers containing n_v vectors of length n , `N_VLinearSum(a,x,b,y,z)`, is

computed as

$$z_{j,i} = ax_{j,i} + by_{j,i}, \quad i = 0, \dots, n-1, \quad j = 0, \dots, n_v - 1.$$

2. The dot product of two wrappers containing n_v vectors of length n is computed as if it were the dot product of two vectors of length nn_v . Thus $\mathbf{d} = \text{N_VDotProd}(\mathbf{x}, \mathbf{y})$ is

$$d = \sum_{j=0}^{n_v-1} \sum_{i=0}^{n-1} x_{j,i} y_{j,i}.$$

3. All norms are computed as the maximum of the individual norms of the n_v vectors in the wrapper. For example, the weighted root mean square norm $\mathbf{m} = \text{N_VWrmsNorm}(\mathbf{x}, \mathbf{w})$ is

$$m = \max_j \sqrt{\left(\frac{1}{n} \sum_{i=0}^{n-1} (x_{j,i} w_{j,i})^2 \right)}$$

To enable usage alongside other NVECTOR modules the NVECTOR_SENSWRAPPER functions implementing vector operations have `_SensWrapper` appended to the generic vector operation name.

The NVECTOR_SENSWRAPPER module provides the following constructors for creating an NVECTOR_SENSWRAPPER:

`N_VNewEmpty_SensWrapper`

Call `w = N_VNewEmpty_SensWrapper(count);`

Description The function `N_VNewEmpty_SensWrapper` creates an empty NVECTOR_SENSWRAPPER wrapper with space for `count` vectors.

Arguments `count` (int) the number of vectors the wrapper will contain.

Return value The return value `w` (of type `N_Vector`) will be a NVECTOR object if the constructor exits successfully, otherwise `w` will be `NULL`.

`N_VNew_SensWrapper`

Call `w = N_VNew_SensWrapper(count, y);`

Description The function `N_VNew_SensWrapper` creates an NVECTOR_SENSWRAPPER wrapper containing `count` vectors cloned from `y`.

Arguments `count` (int) the number of vectors the wrapper will contain.

`y` (`N_Vector`) the template vectors to use in creating the vector wrapper.

Return value The return value `w` (of type `N_Vector`) will be a NVECTOR object if the constructor exits successfully, otherwise `w` will be `NULL`.

The NVECTOR_SENSWRAPPER implementation of the NVECTOR module defines the *content* field of the `N_Vector` to be a structure containing an `N_Vector` array, the number of vectors in the vector array, and a boolean flag indicating ownership of the vectors in the vector array.

```
struct _N_VectorContent_SensWrapper {
    N_Vector* vecs;
    int nvecs;
    booleantype own_vecs;
};
```

The following macros are provided to access the content of an NVECTOR_SENSWRAPPER vector.

- `NV_CONTENT_SW(v)` - provides access to the content structure
- `NV_VECS_SW(v)` - provides access to the vector array

- `NV_NVECS_SW(v)` - provides access to the number of vectors
- `NV_OWN_VECS_SW(v)` - provides access to the ownership flag
- `NV_VEC_SW(v,i)` - provides access to the *i*-th vector in the vector array

9.1.8 Implementing a Custom SUNNonlinearSolver Module

A `SUNNONLINSOL` implementation *must* do the following:

1. Specify the content of the `SUNNONLINSOL` module.
2. Define and implement the required nonlinear solver operations defined in Sections 9.1.1 – 9.1.3. Note that the names of the module routines should be unique to that implementation in order to permit using more than one `SUNNONLINSOL` module (each with different `SUNNonlinearSolver` internal data representations) in the same code.
3. Define and implement a user-callable constructor to create a `SUNNonlinearSolver` object.

Additionally, a `SUNNonlinearSolver` implementation *may* do the following:

1. Define and implement additional user-callable “set” routines acting on the `SUNNonlinearSolver` object, e.g., for setting various configuration options to tune the performance of the nonlinear solve algorithm.
2. Provide additional user-callable “get” routines acting on the `SUNNonlinearSolver` object, e.g., for returning various solve statistics.

9.2 The SUNNonlinearSolver_Newton implementation

This section describes the `SUNNONLINSOL` implementation of Newton’s method. To access the `SUNNONLINSOL_NEWTON` module, include the header file `sunnonlinsol/sunnonlinsol_newton.h`. We note that the `SUNNONLINSOL_NEWTON` module is accessible from SUNDIALS integrators *without* separately linking to the `libsundials_sunnonlinsolnewton` module library.

9.2.1 SUNNonlinearSolver_Newton description

To find the solution to

$$F(y) = 0 \tag{9.1}$$

given an initial guess $y^{(0)}$, Newton’s method computes a series of approximate solutions

$$y^{(m+1)} = y^{(m)} + \delta^{(m+1)} \tag{9.2}$$

where m is the Newton iteration index, and the Newton update $\delta^{(m+1)}$ is the solution of the linear system

$$A(y^{(m)})\delta^{(m+1)} = -F(y^{(m)}), \tag{9.3}$$

in which A is the Jacobian matrix

$$A \equiv \partial F / \partial y. \tag{9.4}$$

Depending on the linear solver used, the `SUNNONLINSOL_NEWTON` module will employ either a Modified Newton method, or an Inexact Newton method [5, 9, 16, 18, 28]. When used with a direct linear solver, the Jacobian matrix A is held constant during the Newton iteration, resulting in a Modified Newton method. With a matrix-free iterative linear solver, the iteration is an Inexact Newton method.

In both cases, calls to the integrator-supplied `SUNNonlinSolSetupFn` function are made infrequently to amortize the increased cost of matrix operations (updating A and its factorization within direct linear solvers, or updating the preconditioner within iterative linear solvers). Specifically, `SUNNONLINSOL_NEWTON` will call the `SUNNonlinSolSetupFn` function in two instances:

- (a) when requested by the integrator (the input `callSetSetup` is `SUNTRUE`) before attempting the Newton iteration, or
- (b) when reattempting the nonlinear solve after a recoverable failure occurs in the Newton iteration with stale Jacobian information (`jcur` is `SUNFALSE`). In this case, `SUNNONLINSOL_NEWTON` will set `jbad` to `SUNTRUE` before calling the `SUNNonlinSolSetupFn` function.

Whether the Jacobian matrix A is fully or partially updated depends on logic unique to each integrator-supplied `SUNNonlinSolSetupFn` routine. We refer to the discussion of nonlinear solver strategies provided in Chapter 2 for details on this decision.

The default maximum number of iterations and the stopping criteria for the Newton iteration are supplied by the SUNDIALS integrator when `SUNNONLINSOL_NEWTON` is attached to it. Both the maximum number of iterations and the convergence test function may be modified by the user by calling the `SUNNonlinSolSetMaxIters` and/or `SUNNonlinSolSetConvTestFn` functions after attaching the `SUNNONLINSOL_NEWTON` object to the integrator.

9.2.2 SUNNonlinearSolver_Newton functions

The `SUNNONLINSOL_NEWTON` module provides the following constructors for creating a `SUNNonlinearSolver` object.

`SUNNonlinSol_Newton`

| | |
|--------------|---|
| Call | <code>NLS = SUNNonlinSol_Newton(y);</code> |
| Description | The function <code>SUNNonlinSol_Newton</code> creates a <code>SUNNonlinearSolver</code> object for use with SUNDIALS integrators to solve nonlinear systems of the form $F(y) = 0$ using Newton's method. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver. |
| Return value | The return value <code>NLS</code> (of type <code>SUNNonlinearSolver</code>) will be a <code>SUNNONLINSOL</code> object if the constructor exits successfully, otherwise <code>NLS</code> will be <code>NULL</code> . |
| F2003 Name | This function is callable as <code>FSUNNonlinSol_Newton</code> when using the Fortran 2003 interface module. |

`SUNNonlinSol_NewtonSens`

| | |
|--------------|---|
| Call | <code>NLS = SUNNonlinSol_NewtonSens(count, y);</code> |
| Description | The function <code>SUNNonlinSol_NewtonSens</code> creates a <code>SUNNonlinearSolver</code> object for use with SUNDIALS sensitivity enabled integrators (CVODES and IDAS) to solve nonlinear systems of the form $F(y) = 0$ using Newton's method. |
| Arguments | <p><code>count</code> (<code>int</code>) the number of vectors in the nonlinear solve. When integrating a system containing N_s sensitivities the value of <code>count</code> is:</p> <ul style="list-style-type: none"> • N_s+1 if using a <i>simultaneous</i> corrector approach. • N_s if using a <i>staggered</i> corrector approach. <p><code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver.</p> |
| Return value | The return value <code>NLS</code> (of type <code>SUNNonlinearSolver</code>) will be a <code>SUNNONLINSOL</code> object if the constructor exits successfully, otherwise <code>NLS</code> will be <code>NULL</code> . |
| F2003 Name | This function is callable as <code>FSUNNonlinSol_NewtonSens</code> when using the Fortran 2003 interface module. |

The `SUNNONLINSOL_NEWTON` module implements all of the functions defined in sections 9.1.1 – 9.1.3 except for the `SUNNonlinSolSetup` function. The `SUNNONLINSOL_NEWTON` functions have the same names as those defined by the generic `SUNNONLINSOL` API with `_Newton` appended to the function name. Unless using the `SUNNONLINSOL_NEWTON` module as a standalone nonlinear solver the generic

functions defined in sections 9.1.1 – 9.1.3 should be called in favor of the SUNNONLINSOL_NEWTON-specific implementations.

The SUNNONLINSOL_NEWTON module also defines the following additional user-callable function.

| |
|-----------------------------|
| SUNNonlinSolGetSysFn_Newton |
|-----------------------------|

| | |
|--------------|---|
| Call | <code>retval = SUNNonlinSolGetSysFn_Newton(NLS, SysFn);</code> |
| Description | The function <code>SUNNonlinSolGetSysFn_Newton</code> returns the residual function that defines the nonlinear system. |
| Arguments | <code>NLS</code> (<code>SUNNonlinearSolver</code>) a <code>SUNNONLINSOL</code> object <code>SysFn</code> (<code>SUNNonlinSolSysFn*</code>) the function defining the nonlinear system. |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |
| Notes | This function is intended for users that wish to evaluate the nonlinear residual in a custom convergence test function for the <code>SUNNONLINSOL_NEWTON</code> module. We note that <code>SUNNONLINSOL_NEWTON</code> will not leverage the results from any user calls to <code>SysFn</code> . |
| F2003 Name | This function is callable as <code>FSUNNonlinSolGetSysFn_Newton</code> when using the Fortran 2003 interface module. |

9.2.3 SUNNonlinearSolver_Newton Fortran interfaces

The `SUNNONLINSOL_NEWTON` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTRAN 2003 interface module

The `fsunnonlinSol_newton.mod` FORTRAN module defines interfaces to all `SUNNONLINSOL_NEWTON` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNNonlinSol_Newton` is interfaced as `FSUNNonlinSol_Newton`.

The FORTRAN 2003 `SUNNONLINSOL_NEWTON` interface module can be accessed with the `use` statement, i.e. `use fsunnonlinSol_newton.mod`, and linking to the library `libsundials_fsunnonlinSol_newton.mod.lib` in addition to the C library. For details on where the library and module file `fsunnonlinSol_newton.mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunnonlinSol_newton.mod` library.

FORTRAN 77 interface functions

For SUNDIALS integrators that include a FORTRAN 77 interface, the `SUNNONLINSOL_NEWTON` module also includes a Fortran-callable function for creating a `SUNNonlinearSolver` object.

| |
|----------------|
| FSUNNEWTONINIT |
|----------------|

| | |
|--------------|--|
| Call | <code>FSUNNEWTONINIT(code, ier);</code> |
| Description | The function <code>FSUNNEWTONINIT</code> can be called for Fortran programs to create a <code>SUNNonlinearSolver</code> object for use with SUNDIALS integrators to solve nonlinear systems of the form $F(y) = 0$ with Newton’s method. |
| Arguments | <code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, and 4 for ARKODE). |
| Return value | <code>ier</code> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |

9.2.4 SUNNonlinearSolver_Newton content

The SUNNONLINSOL_NEWTON module defines the *content* field of a SUNNonlinearSolver as the following structure:

```
struct _SUNNonlinearSolverContent_Newton {

    SUNNonlinSolSysFn      Sys;
    SUNNonlinSolLSetupFn   LSetup;
    SUNNonlinSolLSolveFn   LSolve;
    SUNNonlinSolConvTestFn CTest;

    N_Vector      delta;
    booleantype    jcur;
    int            curiter;
    int            maxiters;
    long int       niters;
    long int       nconvfails;
};
```

These entries of the *content* field contain the following information:

Sys - the function for evaluating the nonlinear system,
LSetup - the package-supplied function for setting up the linear solver,
LSolve - the package-supplied function for performing a linear solve,
CTest - the function for checking convergence of the Newton iteration,
delta - the Newton iteration update vector,
jcur - the Jacobian status (SUNTRUE = current, SUNFALSE = stale),
curiter - the current number of iterations in the solve attempt,
maxiters - the maximum number of Newton iterations allowed in a solve, and
niters - the total number of nonlinear iterations across all solves.
nconvfails - the total number of nonlinear convergence failures across all solves.

9.3 The SUNNonlinearSolver_FixedPoint implementation

This section describes the SUNNONLINSOL implementation of a fixed point (functional) iteration with optional Anderson acceleration. To access the SUNNONLINSOL_FIXEDPOINT module, include the header file `sunnonlinsol/sunnonlinsol.fixedpoint.h`. We note that the SUNNONLINSOL_FIXEDPOINT module is accessible from SUNDIALS integrators *without* separately linking to the `libsundials_sunnonlinsolfixedpoint` module library.

9.3.1 SUNNonlinearSolver_FixedPoint description

To find the solution to

$$G(y) = y \tag{9.5}$$

given an initial guess $y^{(0)}$, the fixed point iteration computes a series of approximate solutions

$$y^{(n+1)} = G(y^{(n)}) \tag{9.6}$$

where n is the iteration index. The convergence of this iteration may be accelerated using Anderson's method [3, 35, 19, 30]. With Anderson acceleration using subspace size m , the series of approximate solutions can be formulated as the linear combination

$$y^{(n+1)} = \sum_{i=0}^{m_n} \alpha_i^{(n)} G(y^{(n-m_n+i)}) \tag{9.7}$$

where $m_n = \min\{m, n\}$ and the factors

$$\alpha^{(n)} = (\alpha_0^{(n)}, \dots, \alpha_{m_n}^{(n)}) \quad (9.8)$$

solve the minimization problem $\min_{\alpha} \|F_n \alpha^T\|_2$ under the constraint that $\sum_{i=0}^{m_n} \alpha_i = 1$ where

$$F_n = (f_{n-m_n}, \dots, f_n) \quad (9.9)$$

with $f_i = G(y^{(i)}) - y^{(i)}$. Due to this constraint, in the limit of $m = 0$ the accelerated fixed point iteration formula (9.7) simplifies to the standard fixed point iteration (9.6).

Following the recommendations made in [35], the SUNNONLINSOL_FIXEDPOINT implementation computes the series of approximate solutions as

$$y^{(n+1)} = G(y^{(n)}) - \sum_{i=0}^{m_n-1} \gamma_i^{(n)} \Delta g_{n-m_n+i} \quad (9.10)$$

with $\Delta g_i = G(y^{(i+1)}) - G(y^{(i)})$ and where the factors

$$\gamma^{(n)} = (\gamma_0^{(n)}, \dots, \gamma_{m_n-1}^{(n)}) \quad (9.11)$$

solve the unconstrained minimization problem $\min_{\gamma} \|f_n - \Delta F_n \gamma^T\|_2$ where

$$\Delta F_n = (\Delta f_{n-m_n}, \dots, \Delta f_{n-1}), \quad (9.12)$$

with $\Delta f_i = f_{i+1} - f_i$. The least-squares problem is solved by applying a QR factorization to $\Delta F_n = Q_n R_n$ and solving $R_n \gamma = Q_n^T f_n$.

The acceleration subspace size m is required when constructing the SUNNONLINSOL_FIXEDPOINT object. The default maximum number of iterations and the stopping criteria for the fixed point iteration are supplied by the SUNDIALS integrator when SUNNONLINSOL_FIXEDPOINT is attached to it. Both the maximum number of iterations and the convergence test function may be modified by the user by calling `SUNNonlinSolSetMaxIters` and `SUNNonlinSolSetConvTestFn` functions after attaching the SUNNONLINSOL_FIXEDPOINT object to the integrator.

9.3.2 SUNNonlinearSolver_FixedPoint functions

The SUNNONLINSOL_FIXEDPOINT module provides the following constructors for creating a `SUNNonlinearSolver` object.

| <code>SUNNonlinSol_FixedPoint</code> | |
|--------------------------------------|---|
| Call | <code>NLS = SUNNonlinSol_FixedPoint(y, m);</code> |
| Description | The function <code>SUNNonlinSol_FixedPoint</code> creates a <code>SUNNonlinearSolver</code> object for use with SUNDIALS integrators to solve nonlinear systems of the form $G(y) = y$. |
| Arguments | <code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver <code>m</code> (<code>int</code>) the number of acceleration vectors to use |
| Return value | The return value <code>NLS</code> (of type <code>SUNNonlinearSolver</code>) will be a <code>SUNNONLINSOL</code> object if the constructor exits successfully, otherwise <code>NLS</code> will be <code>NULL</code> . |
| F2003 Name | This function is callable as <code>FSUNNonlinSol_FixedPoint</code> when using the Fortran 2003 interface module. |

SUNNonlinSol_FixedPointSens

| | |
|--------------|--|
| Call | <code>NLS = SUNNonlinSol_FixedPointSens(count, y, m);</code> |
| Description | The function <code>SUNNonlinSol_FixedPointSens</code> creates a <code>SUNNonlinearSolver</code> object for use with SUNDIALS sensitivity enabled integrators (CVODES and IDAS) to solve nonlinear systems of the form $G(y) = y$. |
| Arguments | <p><code>count</code> (<code>int</code>) the number of vectors in the nonlinear solve. When integrating a system containing <code>Ns</code> sensitivities the value of <code>count</code> is:</p> <ul style="list-style-type: none"> • <code>Ns+1</code> if using a <i>simultaneous</i> corrector approach. • <code>Ns</code> if using a <i>staggered</i> corrector approach. <p><code>y</code> (<code>N_Vector</code>) a template for cloning vectors needed within the solver.</p> <p><code>m</code> (<code>int</code>) the number of acceleration vectors to use.</p> |
| Return value | The return value <code>NLS</code> (of type <code>SUNNonlinearSolver</code>) will be a <code>SUNNONLINSOL</code> object if the constructor exits successfully, otherwise <code>NLS</code> will be <code>NULL</code> . |
| F2003 Name | This function is callable as <code>FSUNNonlinSol_FixedPointSens</code> when using the Fortran 2003 interface module. |

Since the accelerated fixed point iteration (9.6) does not require the setup or solution of any linear systems, the `SUNNONLINSOL_FIXEDPOINT` module implements all of the functions defined in sections 9.1.1 – 9.1.3 except for the `SUNNonlinSolSetup`, `SUNNonlinSolSetLSetupFn`, and `SUNNonlinSolSetLSolveFn` functions, that are set to `NULL`. The `SUNNONLINSOL_FIXEDPOINT` functions have the same names as those defined by the generic `SUNNONLINSOL` API with `_FixedPoint` appended to the function name. Unless using the `SUNNONLINSOL_FIXEDPOINT` module as a standalone nonlinear solver the generic functions defined in sections 9.1.1 – 9.1.3 should be called in favor of the `SUNNONLINSOL_FIXEDPOINT`-specific implementations.

The `SUNNONLINSOL_FIXEDPOINT` module also defines the following additional user-callable function.

SUNNonlinSolGetSysFn_FixedPoint

| | |
|--------------|---|
| Call | <code>retval = SUNNonlinSolGetSysFn_FixedPoint(NLS, SysFn);</code> |
| Description | The function <code>SUNNonlinSolGetSysFn_FixedPoint</code> returns the fixed-point function that defines the nonlinear system. |
| Arguments | <p><code>NLS</code> (<code>SUNNonlinearSolver</code>) a <code>SUNNONLINSOL</code> object</p> <p><code>SysFn</code> (<code>SUNNonlinSolSysFn*</code>) the function defining the nonlinear system.</p> |
| Return value | The return value <code>retval</code> (of type <code>int</code>) should be zero for a successful call, and a negative value for a failure. |
| Notes | This function is intended for users that wish to evaluate the fixed-point function in a custom convergence test function for the <code>SUNNONLINSOL_FIXEDPOINT</code> module. We note that <code>SUNNONLINSOL_FIXEDPOINT</code> will not leverage the results from any user calls to <code>SysFn</code> . |
| F2003 Name | This function is callable as <code>FSUNNonlinSolGetSysFn_FixedPoint</code> when using the Fortran 2003 interface module. |

9.3.3 SUNNonlinearSolver_FixedPoint Fortran interfaces

The `SUNNONLINSOL_FIXEDPOINT` module provides a FORTRAN 2003 module as well as FORTRAN 77 style interface functions for use from FORTRAN applications.

FORTTRAN 2003 interface module

The `fsunnonlinsol_fixedpoint_mod` FORTRAN module defines interfaces to all `SUNNONLINSOL_FIXEDPOINT` C functions using the intrinsic `iso_c_binding` module which provides a standardized mechanism for interoperating with C. As noted in the C function descriptions above, the interface functions are named after the corresponding C function, but with a leading ‘F’. For example, the function `SUNNonlinSol_FixedPoint` is interfaced as `FSUNNonlinSol_FixedPoint`.

The FORTRAN 2003 `SUNNONLINSOL_FIXEDPOINT` interface module can be accessed with the `use` statement, i.e. `use fsunnonlinsol_fixedpoint_mod`, and linking to the library `libsundials_fsunnonlinsolfixedpoint_mod.lib` in addition to the C library. For details on where the library and module file `fsunnonlinsol_fixedpoint_mod.mod` are installed see Appendix A. We note that the module is accessible from the FORTRAN 2003 SUNDIALS integrators *without* separately linking to the `libsundials_fsunnonlinsolfixedpoint_mod` library.

FORTTRAN 77 interface functions

For SUNDIALS integrators that include a FORTRAN 77 interface, the `SUNNONLINSOL_FIXEDPOINT` module also includes a Fortran-callable function for creating a `SUNNonlinearSolver` object.

FSUNFIXEDPOINTINIT

| | |
|--------------|--|
| Call | <code>FSUNFIXEDPOINTINIT(code, m, ier);</code> |
| Description | The function <code>FSUNFIXEDPOINTINIT</code> can be called for Fortran programs to create a <code>SUNNonlinearSolver</code> object for use with SUNDIALS integrators to solve nonlinear systems of the form $G(y) = y$. |
| Arguments | <p><code>code</code> (<code>int*</code>) is an integer input specifying the solver id (1 for CVODE, 2 for IDA, and 4 for ARKODE).</p> <p><code>m</code> (<code>int*</code>) is an integer input specifying the number of acceleration vectors.</p> |
| Return value | <code>ier</code> is a return completion flag equal to 0 for a success return and -1 otherwise. See printed message for details in case of failure. |

9.3.4 SUNNonlinearSolver_FixedPoint content

The `SUNNONLINSOL_FIXEDPOINT` module defines the *content* field of a `SUNNonlinearSolver` as the following structure:

```
struct _SUNNonlinearSolverContent_FixedPoint {

    SUNNonlinSolSysFn      Sys;
    SUNNonlinSolConvTestFn CTest;

    int      m;
    int      *imap;
    realtype *R;
    realtype *gamma;
    realtype *cvals;
    N_Vector *df;
    N_Vector *dg;
    N_Vector *q;
    N_Vector *Xvecs;
    N_Vector yprev;
    N_Vector gy;
    N_Vector fold;
    N_Vector gold;
    N_Vector delta;
```

```

    int      curiter;
    int      maxiters;
    long int  niters;
    long int  nconvfails;
};

```

The following entries of the *content* field are always allocated:

Sys - function for evaluating the nonlinear system,
CTest - function for checking convergence of the fixed point iteration,
yprev - **N_Vector** used to store previous fixed-point iterate,
gy - **N_Vector** used to store $G(y)$ in fixed-point algorithm,
delta - **N_Vector** used to store difference between successive fixed-point iterates,
curiter - the current number of iterations in the solve attempt,
maxiters - the maximum number of fixed-point iterations allowed in a solve, and
niters - the total number of nonlinear iterations across all solves.
nconvfails - the total number of nonlinear convergence failures across all solves.
m - number of acceleration vectors,

If Anderson acceleration is requested (i.e., $m > 0$ in the call to **SUNNonlinSol_FixedPoint**), then the following items are also allocated within the *content* field:

imap - index array used in acceleration algorithm (length **m**)
R - small matrix used in acceleration algorithm (length **m*m**)
gamma - small vector used in acceleration algorithm (length **m**)
cvals - small vector used in acceleration algorithm (length **m+1**)
df - array of **N_Vectors** used in acceleration algorithm (length **m**)
dg - array of **N_Vectors** used in acceleration algorithm (length **m**)
q - array of **N_Vectors** used in acceleration algorithm (length **m**)
Xvecs - **N_Vector** pointer array used in acceleration algorithm (length **m+1**)
fold - **N_Vector** used in acceleration algorithm
gold - **N_Vector** used in acceleration algorithm

Appendix A

SUNDIALS Package Installation Procedure

The installation of any SUNDIALS package is accomplished by installing the SUNDIALS suite as a whole, according to the instructions that follow. The same procedure applies whether or not the downloaded file contains one or all solvers in SUNDIALS.

The SUNDIALS suite (or individual solvers) are distributed as compressed archives (`.tar.gz`). The name of the distribution archive is of the form `solver-x.y.z.tar.gz`, where *solver* is one of: `sundials`, `cvode`, `cvodes`, `arkode`, `ida`, `idas`, or `kinsol`, and `x.y.z` represents the version number (of the SUNDIALS suite or of the individual solver). To begin the installation, first uncompress and expand the sources, by issuing

```
% tar xzf solver-x.y.z.tar.gz
```

This will extract source files under a directory `solver-x.y.z`.

Starting with version 2.6.0 of SUNDIALS, CMake is the only supported method of installation. The explanations of the installation procedure begins with a few common observations:

- The remainder of this chapter will follow these conventions:

solverdir is the directory `solver-x.y.z` created above; i.e., the directory containing the SUNDIALS sources.

builddir is the (temporary) directory under which SUNDIALS is built.

instdir is the directory under which the SUNDIALS exported header files and libraries will be installed. Typically, header files are exported under a directory `instdir/include` while libraries are installed under `instdir/CMAKE_INSTALL_LIBDIR`, with *instdir* and `CMAKE_INSTALL_LIBDIR` specified at configuration time.

- For SUNDIALS CMake-based installation, in-source builds are prohibited; in other words, the build directory *builddir* can **not** be the same as *solverdir* and such an attempt will lead to an error. This prevents “polluting” the source tree and allows efficient builds for different configurations and/or options.
- The installation directory *instdir* can **not** be the same as the source directory *solverdir*.
- By default, only the libraries and header files are exported to the installation directory *instdir*. If enabled by the user (with the appropriate toggle for CMake), the examples distributed with SUNDIALS will be built together with the solver libraries but the installation step will result in exporting (by default in a subdirectory of the installation directory) the example sources and sample outputs together with automatically generated configuration files that reference the *installed* SUNDIALS headers and libraries. As such, these configuration files for the SUNDIALS examples can be used as “templates” for your own problems. CMake installs `CMakeLists.txt` files



and also (as an option available only under Unix/Linux) **Makefile** files. Note this installation approach also allows the option of building the SUNDIALS examples without having to install them. (This can be used as a sanity check for the freshly built libraries.)

- Even if generation of shared libraries is enabled, only static libraries are created for the FCMIX modules. (Because of the use of fixed names for the Fortran user-provided subroutines, FCMIX shared libraries would result in “undefined symbol” errors at link time.)

A.1 CMake-based installation

CMake-based installation provides a platform-independent build system. CMake can generate Unix and Linux Makefiles, as well as KDevelop, Visual Studio, and (Apple) XCode project files from the same configuration file. In addition, CMake also provides a GUI front end and which allows an interactive build and installation process.

The SUNDIALS build process requires CMake version 3.1.3 or higher and a working C compiler. On Unix-like operating systems, it also requires Make (and **curses**, including its development libraries, for the GUI front end to CMake, **ccmake**), while on Windows it requires Visual Studio. CMake is continually adding new features, and the latest version can be downloaded from <http://www.cmake.org>. Build instructions for CMake (only necessary for Unix-like systems) can be found on the CMake website. Once CMake is installed, Linux/Unix users will be able to use **ccmake**, while Windows users will be able to use **CMakeSetup**.

As previously noted, when using CMake to configure, build and install SUNDIALS, it is always required to use a separate build directory. While in-source builds are possible, they are explicitly prohibited by the SUNDIALS CMake scripts (one of the reasons being that, unlike autotools, CMake does not provide a **make distclean** procedure and it is therefore difficult to clean-up the source tree after an in-source build). By ensuring a separate build directory, it is an easy task for the user to clean-up all traces of the build by simply removing the build directory. CMake does generate a **make clean** which will remove files generated by the compiler and linker.

A.1.1 Configuring, building, and installing on Unix-like systems

The default CMake configuration will build all included solvers and associated examples and will build static and shared libraries. The *instdir* defaults to **/usr/local** and can be changed by setting the **CMAKE_INSTALL_PREFIX** variable. Support for FORTRAN and all other options are disabled.

CMake can be used from the command line with the **cmake** command, or from a **curses**-based GUI by using the **ccmake** command. Examples for using both methods will be presented. For the examples shown it is assumed that there is a top level SUNDIALS directory with appropriate source, build and install directories:

```
% mkdir (...)sundials/instdir
% mkdir (...)sundials/builddir
% cd (...)sundials/builddir
```

Building with the GUI

Using CMake with the GUI follows this general process:

- Select and modify values, run configure (c key)
- New values are denoted with an asterisk
- To set a variable, move the cursor to the variable and press enter
 - If it is a boolean (ON/OFF) it will toggle the value
 - If it is string or file, it will allow editing of the string

- For file and directories, the <tab> key can be used to complete
- Repeat until all values are set as desired and the generate option is available (g key)
- Some variables (advanced variables) are not visible right away
- To see advanced variables, toggle to advanced mode (t key)
- To search for a variable press / key, and to repeat the search, press the n key

To build the default configuration using the GUI, from the *builddir* enter the *ccmake* command and point to the *solverdir*:

```
% ccmake ../solverdir
```

The default configuration screen is shown in Figure A.1.




Figure A.1: Default configuration screen. Note: Initial screen is empty. To get this default configuration, press 'c' repeatedly (accepting default values denoted with asterisk) until the 'g' option is available.

The default *instdir* for both SUNDIALS and corresponding examples can be changed by setting the *CMAKE.INSTALL_PREFIX* and the *EXAMPLES.INSTALL_PATH* as shown in figure A.2.

Pressing the (g key) will generate makefiles including all dependencies and all rules to build SUNDIALS on this system. Back at the command prompt, you can now run:

```

Page 1 of 1
BLAS_ENABLE OFF
BUILD_ARKODE ON
BUILD_CVODE ON
BUILD_CVODES ON
BUILD_IDA ON
BUILD_IDAS ON
BUILD_KINSOL ON
BUILD_SHARED_LIBS ON
BUILD_STATIC_LIBS ON
BUILD_TESTING ON
CMAKE_BUILD_TYPE
CMAKE_C_COMPILER /usr/bin/cc
CMAKE_C_FLAGS
CMAKE_INSTALL_LIBDIR lib64
CMAKE_INSTALL_PREFIX /usr/casc/sundials/instdir
CUDA_ENABLE OFF
EXAMPLES_ENABLE_C ON
EXAMPLES_ENABLE_CXX OFF
EXAMPLES_INSTALL ON
EXAMPLES_INSTALL_PATH /usr/casc/sundials/instdir/examples
F2003_INTERFACE_ENABLE OFF
F77_INTERFACE_ENABLE OFF
HYPRE_ENABLE OFF
KLU_ENABLE OFF
LAPACK_ENABLE OFF
MPI_ENABLE OFF
OPENMP_DEVICE_ENABLE OFF
OPENMP_ENABLE OFF
PETSC_ENABLE OFF
PTHREAD_ENABLE OFF
RAJA_ENABLE OFF
SUNDIALS_INDEX_SIZE 64
SUNDIALS_PRECISION double
SUPERLUMT_ENABLE OFF
USE_GENERIC_MATH ON
USE_XSDK_DEFAULTS OFF

CMAKE_INSTALL_PREFIX: Install path prefix, prepended onto install directories.
Press [enter] to edit option
Press [c] to configure Press [g] to generate and exit
Press [h] for help Press [q] to quit without generating
Press [t] to toggle advanced mode (Currently Off)
CMake Version 3.1.3

```

Figure A.2: Changing the *instdir* for SUNDIALS and corresponding examples

```
% make
```

To install SUNDIALS in the installation directory specified in the configuration, simply run:

```
% make install
```

Building from the command line

Using CMake from the command line is simply a matter of specifying CMake variable settings with the `cmake` command. The following will build the default configuration:

```

% cmake -DCMAKE_INSTALL_PREFIX=/home/myname/sundials/instdir \
> -DEXAMPLES_INSTALL_PATH=/home/myname/sundials/instdir/examples \
> ../solverdir
% make
% make install

```

A.1.2 Configuration options (Unix/Linux)

A complete list of all available options for a CMake-based SUNDIALS configuration is provide below. Note that the default values shown are for a typical configuration on a Linux system and are provided as illustration only.

BLAS_ENABLE - Enable BLAS support

Default: OFF

Note: Setting this option to ON will trigger additional CMake options. See additional information on building with BLAS enabled in [A.1.4](#).

BLAS_LIBRARIES - BLAS library

Default: /usr/lib/libblas.so

Note: CMake will search for libraries in your LD_LIBRARY_PATH prior to searching default system paths.

BUILD_ARKODE - Build the ARKODE library

Default: ON

BUILD_CVODE - Build the CVODE library

Default: ON

BUILD_CVODES - Build the CVODES library

Default: ON

BUILD_IDA - Build the IDA library

Default: ON

BUILD_IDAS - Build the IDAS library

Default: ON

BUILD_KINSOL - Build the KINSOL library

Default: ON

BUILD_SHARED_LIBS - Build shared libraries

Default: ON

BUILD_STATIC_LIBS - Build static libraries

Default: ON

CMAKE_BUILD_TYPE - Choose the type of build, options are: **None** (CMAKE_C_FLAGS used), **Debug**, **Release**, **RelWithDebInfo**, and **MinSizeRel**

Default:

Note: Specifying a build type will trigger the corresponding build type specific compiler flag options below which will be appended to the flags set by CMAKE_<language>_FLAGS.

CMAKE_C_COMPILER - C compiler

Default: /usr/bin/cc

CMAKE_C_FLAGS - Flags for C compiler

Default:

CMAKE_C_FLAGS_DEBUG - Flags used by the C compiler during debug builds

Default: -g

CMAKE_C_FLAGS_MINSIZEREL - Flags used by the C compiler during release minsize builds

Default: -Os -DNDEBUG

CMAKE_C_FLAGS_RELEASE - Flags used by the C compiler during release builds

Default: -O3 -DNDEBUG

CMAKE_CXX_COMPILER - C++ compiler

Default: /usr/bin/c++

Note: A C++ compiler (and all related options) are only triggered if C++ examples are enabled (EXAMPLES_ENABLE_CXX is ON). All SUNDIALS solvers can be used from C++ applications by default without setting any additional configuration options.

CMAKE_CXX_FLAGS - Flags for C++ compiler

Default:

CMAKE_CXX_FLAGS_DEBUG - Flags used by the C++ compiler during debug builds

Default: -g

CMAKE_CXX_FLAGS_MINSIZEREL - Flags used by the C++ compiler during release minsize builds

Default: -Os -DNDEBUG

CMAKE_CXX_FLAGS_RELEASE - Flags used by the C++ compiler during release builds

Default: -O3 -DNDEBUG

CMAKE_Fortran_COMPILER - Fortran compiler

Default: /usr/bin/gfortran

Note: Fortran support (and all related options) are triggered only if either Fortran-C support is enabled (**FCMIX_ENABLE** is ON) or BLAS/LAPACK support is enabled (**BLAS_ENABLE** or **LAPACK_ENABLE** is ON).

CMAKE_Fortran_FLAGS - Flags for Fortran compiler

Default:

CMAKE_Fortran_FLAGS_DEBUG - Flags used by the Fortran compiler during debug builds

Default: -g

CMAKE_Fortran_FLAGS_MINSIZEREL - Flags used by the Fortran compiler during release minsize builds

Default: -Os

CMAKE_Fortran_FLAGS_RELEASE - Flags used by the Fortran compiler during release builds

Default: -O3

CMAKE_INSTALL_PREFIX - Install path prefix, prepended onto install directories

Default: /usr/local

Note: The user must have write access to the location specified through this option. Exported SUNDIALS header files and libraries will be installed under subdirectories **include** and **CMAKE_INSTALL_LIBDIR** of **CMAKE_INSTALL_PREFIX**, respectively.

CMAKE_INSTALL_LIBDIR - Library installation directory

Default:

Note: This is the directory within **CMAKE_INSTALL_PREFIX** that the SUNDIALS libraries will be installed under. The default is automatically set based on the operating system using the GNUInstallDirs CMake module.

Fortran_INSTALL_MOODIR - Fortran module installation directory

Default: fortran

CUDA_ENABLE - Build the SUNDIALS CUDA vector module.

Default: OFF

EXAMPLES_ENABLE_C - Build the SUNDIALS C examples

Default: ON

EXAMPLES_ENABLE_CUDA - Build the SUNDIALS CUDA examples

Default: OFF

Note: You need to enable CUDA support to build these examples.

EXAMPLES_ENABLE_CXX - Build the SUNDIALS C++ examples

Default: OFF

EXAMPLES_ENABLE_RAJA - Build the SUNDIALS RAJA examples

Default: OFF

Note: You need to enable CUDA and RAJA support to build these examples.

EXAMPLES_ENABLE_F77 - Build the SUNDIALS Fortran77 examples

Default: ON (if **F77_INTERFACE_ENABLE** is ON)

EXAMPLES_ENABLE_F90 - Build the SUNDIALS Fortran90/Fortran2003 examples

Default: ON (if **F77_INTERFACE_ENABLE** or **F2003_INTERFACE_ENABLE** is ON)

EXAMPLES_INSTALL - Install example files

Default: ON

Note: This option is triggered when any of the SUNDIALS example programs are enabled (**EXAMPLES_ENABLE_<language>** is ON). If the user requires installation of example programs then the sources and sample output files for all SUNDIALS modules that are currently enabled will be exported to the directory specified by **EXAMPLES_INSTALL_PATH**. A CMake configuration script will also be automatically generated and exported to the same directory. Additionally, if the configuration is done under a Unix-like system, makefiles for the compilation of the example programs (using the installed SUNDIALS libraries) will be automatically generated and exported to the directory specified by **EXAMPLES_INSTALL_PATH**.

EXAMPLES_INSTALL_PATH - Output directory for installing example files

Default: /usr/local/examples

Note: The actual default value for this option will be an **examples** subdirectory created under **CMAKE_INSTALL_PREFIX**.

F77_INTERFACE_ENABLE - Enable Fortran-C support via the Fortran 77 interfaces

Default: OFF

F2003_INTERFACE_ENABLE - Enable Fortran-C support via the Fortran 2003 interfaces

Default: OFF

HYPRE_ENABLE - Enable *hypre* support

Default: OFF

Note: See additional information on building with *hypre* enabled in [A.1.4](#).

HYPRE_INCLUDE_DIR - Path to *hypre* header files

HYPRE_LIBRARY_DIR - Path to *hypre* installed library files

KLU_ENABLE - Enable KLU support

Default: OFF

Note: See additional information on building with KLU enabled in [A.1.4](#).

KLU_INCLUDE_DIR - Path to SuiteSparse header files

KLU_LIBRARY_DIR - Path to SuiteSparse installed library files

LAPACK_ENABLE - Enable LAPACK support

Default: OFF

Note: Setting this option to ON will trigger additional CMake options. See additional information on building with LAPACK enabled in [A.1.4](#).

LAPACK_LIBRARIES - LAPACK (and BLAS) libraries

Default: /usr/lib/liblapack.so;/usr/lib/libblas.so

Note: CMake will search for libraries in your **LD_LIBRARY_PATH** prior to searching default system paths.

MPI_ENABLE - Enable MPI support (build the parallel nvector).

Default: OFF

Note: Setting this option to ON will trigger several additional options related to MPI.

MPI_C_COMPILER - mpicc program

Default:

MPI_CXX_COMPILER - mpicxx program

Default:

Note: This option is triggered only if MPI is enabled (**MPI_ENABLE** is ON) and C++ examples are enabled (**EXAMPLES_ENABLE_CXX** is ON). All SUNDIALS solvers can be used from C++ MPI applications by default without setting any additional configuration options other than **MPI_ENABLE**.

MPI_Fortran_COMPILER - mpif77 or mpif90 program

Default:

Note: This option is triggered only if MPI is enabled (**MPI_ENABLE** is ON) and Fortran-C support is enabled (**F77_INTERFACE_ENABLE** or **F2003_INTERFACE_ENABLE** is ON).

MPIEXEC_EXECUTABLE - Specify the executable for running MPI programs

Default: mpirun

Note: This option is triggered only if MPI is enabled (**MPI_ENABLE** is ON).

OPENMP_ENABLE - Enable OpenMP support (build the OpenMP nvector).

Default: OFF

OPENMP_DEVICE_ENABLE - Enable OpenMP device offloading (build the OpenMPDEV nvector) if supported by the provided compiler.

Default: OFF

SKIP_OPENMP_DEVICE_CHECK - **advanced option** - Skip the check done to see if the OpenMP provided by the compiler supports OpenMP device offloading.

Default: OFF

PETSC_ENABLE - Enable PETSc support

Default: OFF

Note: See additional information on building with PETSc enabled in [A.1.4](#).

PETSC_INCLUDE_DIR - Path to PETSc header files

PETSC_LIBRARY_DIR - Path to PETSc installed library files

PTHREAD_ENABLE - Enable Pthreads support (build the Pthreads nvector).

Default: OFF

RAJA_ENABLE - Enable RAJA support (build the RAJA nvector).

Default: OFF

Note: You need to enable CUDA in order to build the RAJA vector module.

SUNDIALS_F77_FUNC_CASE - **advanced option** - Specify the case to use in the Fortran name-mangling scheme, options are: **lower** or **upper**

Default:

Note: The build system will attempt to infer the Fortran name-mangling scheme using the Fortran compiler. This option should only be used if a Fortran compiler is not available or to override the inferred or default (**lower**) scheme if one can not be determined. If used, **SUNDIALS_F77_FUNC_UNDERSCORES** must also be set.

SUNDIALS_F77_FUNC_UNDERSCORES - **advanced option** - Specify the number of underscores to append in the Fortran name-mangling scheme, options are: **none**, **one**, or **two**

Default:

Note: The build system will attempt to infer the Fortran name-mangling scheme using the Fortran compiler. This option should only be used if a Fortran compiler is not available or to override the inferred or default (**one**) scheme if one can not be determined. If used, `SUNDIALS_F77_FUNC_CASE` must also be set.

SUNDIALS_INDEX_TYPE - **advanced option** - Integer type used for SUNDIALS indices. The size must match the size provided for the **SUNDIALS_INDEX_SIZE** option.

Default:

Note: In past SUNDIALS versions, a user could set this option to `INT64_T` to use 64-bit integers, or `INT32_T` to use 32-bit integers. Starting in SUNDIALS 3.2.0, these special values are deprecated. For SUNDIALS 3.2.0 and up, a user will only need to use the **SUNDIALS_INDEX_SIZE** option in most cases.

SUNDIALS_INDEX_SIZE - Integer size (in bits) used for indices in SUNDIALS, options are: 32 or 64

Default: 64

Note: The build system tries to find an integer type of appropriate size. Candidate 64-bit integer types are (in order of preference): `int64_t`, `__int64`, `long long`, and `long`. Candidate 32-bit integers are (in order of preference): `int32_t`, `int`, and `long`. The advanced option, **SUNDIALS_INDEX_TYPE** can be used to provide a type not listed here.

SUNDIALS_PRECISION - Precision used in SUNDIALS, options are: **double**, **single**, or **extended**

Default: **double**

SUPERLUMT_ENABLE - Enable SuperLU_MT support

Default: OFF

Note: See additional information on building with SuperLU_MT enabled in [A.1.4](#).

SUPERLUMT_INCLUDE_DIR - Path to SuperLU_MT header files (typically SRC directory)

SUPERLUMT_LIBRARY_DIR - Path to SuperLU_MT installed library files

SUPERLUMT_THREAD_TYPE - Must be set to Pthread or OpenMP

Default: Pthread

USE_GENERIC_MATH - Use generic (stdc) math libraries

Default: ON

xSDK Configuration Options

SUNDIALS supports CMake configuration options defined by the Extreme-scale Scientific Software Development Kit (xSDK) community policies (see <https://xsdk.info> for more information). xSDK CMake options are unused by default but may be activated by setting **USE_XSDK_DEFAULTS** to ON.

When xSDK options are active, they will overwrite the corresponding SUNDIALS option and may have different default values (see details below). As such the equivalent SUNDIALS options should not be used when configuring with xSDK options. In the GUI front end to CMake (**ccmake**), setting **USE_XSDK_DEFAULTS** to ON will hide the corresponding SUNDIALS options as advanced CMake variables. During configuration, messages are output detailing which xSDK flags are active and the equivalent SUNDIALS options that are replaced. Below is a complete list xSDK options and the corresponding SUNDIALS options if applicable.



TPL_BLAS_LIBRARIES - BLAS library

Default: `/usr/lib/libblas.so`

SUNDIALS equivalent: **BLAS_LIBRARIES**

Note: CMake will search for libraries in your **LD_LIBRARY_PATH** prior to searching default system paths.

TPL_ENABLE_BLAS - Enable BLAS support
Default: OFF
SUNDIALS equivalent: BLAS_ENABLE

TPL_ENABLE_HYPRE - Enable *hypre* support
Default: OFF
SUNDIALS equivalent: HYPRE_ENABLE

TPL_ENABLE_KLU - Enable KLU support
Default: OFF
SUNDIALS equivalent: KLU_ENABLE

TPL_ENABLE_PETSC - Enable PETSc support
Default: OFF
SUNDIALS equivalent: PETSC_ENABLE

TPL_ENABLE_LAPACK - Enable LAPACK support
Default: OFF
SUNDIALS equivalent: LAPACK_ENABLE

TPL_ENABLE_SUPERLUMT - Enable SuperLU_MT support
Default: OFF
SUNDIALS equivalent: SUPERLUMT_ENABLE

TPL_HYPRE_INCLUDE_DIRS - Path to *hypre* header files
SUNDIALS equivalent: HYPRE_INCLUDE_DIR

TPL_HYPRE_LIBRARIES - *hypre* library
SUNDIALS equivalent: N/A

TPL_KLU_INCLUDE_DIRS - Path to KLU header files
SUNDIALS equivalent: KLU_INCLUDE_DIR

TPL_KLU_LIBRARIES - KLU library
SUNDIALS equivalent: N/A

TPL_LAPACK_LIBRARIES - LAPACK (and BLAS) libraries
Default: /usr/lib/liblapack.so;/usr/lib/libblas.so
SUNDIALS equivalent: LAPACK_LIBRARIES
Note: CMake will search for libraries in your LD_LIBRARY_PATH prior to searching default system paths.

TPL_PETSC_INCLUDE_DIRS - Path to PETSc header files
SUNDIALS equivalent: PETSC_INCLUDE_DIR

TPL_PETSC_LIBRARIES - PETSc library
SUNDIALS equivalent: N/A

TPL_SUPERLUMT_INCLUDE_DIRS - Path to SuperLU_MT header files
SUNDIALS equivalent: SUPERLUMT_INCLUDE_DIR

TPL_SUPERLUMT_LIBRARIES - SuperLU_MT library
SUNDIALS equivalent: N/A

TPL_SUPERLUMT_THREAD_TYPE - SuperLU_MT library thread type
SUNDIALS equivalent: SUPERLUMT_THREAD_TYPE

USE_XSDK_DEFAULTS - Enable xSDK default configuration settings
Default: OFF
SUNDIALS equivalent: N/A
Note: Enabling xSDK defaults also sets CMAKE_BUILD_TYPE to Debug

XSDK_ENABLE_FORTRAN - Enable SUNDIALS Fortran interfaces

Default: OFF

SUNDIALS equivalent: F77_INTERFACE_ENABLE/F2003_INTERFACE_ENABLE

XSDK_INDEX_SIZE - Integer size (bits) used for indices in SUNDIALS, options are: 32 or 64

Default: 32

SUNDIALS equivalent: SUNDIALS_INDEX_SIZE

XSDK_PRECISION - Precision used in SUNDIALS, options are: double, single, or quad

Default: double

SUNDIALS equivalent: SUNDIALS_PRECISION

A.1.3 Configuration examples

The following examples will help demonstrate usage of the CMake configure options.

To configure SUNDIALS using the default C and Fortran compilers, and default mpicc and mpif77 parallel compilers, enable compilation of examples, and install libraries, headers, and example sources under subdirectories of /home/myname/sundials/, use:

```
% cmake \
> -DCMAKE_INSTALL_PREFIX=/home/myname/sundials/instdir \
> -DEXAMPLES_INSTALL_PATH=/home/myname/sundials/instdir/examples \
> -DMPI_ENABLE=ON \
> -DFCMIX_ENABLE=ON \
> /home/myname/sundials/solverdir
%
% make install
%
```

To disable installation of the examples, use:

```
% cmake \
> -DCMAKE_INSTALL_PREFIX=/home/myname/sundials/instdir \
> -DEXAMPLES_INSTALL_PATH=/home/myname/sundials/instdir/examples \
> -DMPI_ENABLE=ON \
> -DFCMIX_ENABLE=ON \
> -DEXAMPLES_INSTALL=OFF \
> /home/myname/sundials/solverdir
%
% make install
%
```

A.1.4 Working with external Libraries

The SUNDIALS suite contains many options to enable implementation flexibility when developing solutions. The following are some notes addressing specific configurations when using the supported third party libraries. When building SUNDIALS as a shared library external libraries any used with SUNDIALS must also be build as a shared library or as a static library compiled with the -fPIC flag.



Building with BLAS

SUNDIALS does not utilize BLAS directly but it may be needed by other external libraries that SUNDIALS can be built with (e.g. LAPACK, PETSc, SuperLU_MT, etc.). To enable BLAS, set the BLAS_ENABLE option to ON. If the directory containing the BLAS library is in the LD_LIBRARY_PATH environment variable, CMake will set the BLAS_LIBRARIES variable accordingly, otherwise CMake will attempt to find the BLAS library in standard system locations. To explicitly tell CMake what libraries to use, the BLAS_LIBRARIES variable can be set to the desired library. Example:

```
% cmake \
> -DCMAKE_INSTALL_PREFIX=/home/myname/sundials/instdir \
> -DEXAMPLES_INSTALL_PATH=/home/myname/sundials/instdir/examples \
> -DBLAS_ENABLE=ON \
> -DBLAS_LIBRARIES=/myblaspath/lib/libblas.so \
> -DSUPERLUMT_ENABLE=ON \
> -DSUPERLUMT_INCLUDE_DIR=/mysuperlumtpath/SRC
> -DSUPERLUMT_LIBRARY_DIR=/mysuperlumtpath/lib
> /home/myname/sundials/solverdir
%
% make install
%
```



When allowing CMake to automatically locate the LAPACK library, CMake *may* also locate the corresponding BLAS library.

If a working Fortran compiler is not available to infer the Fortran name-mangling scheme, the options `SUNDIALS_F77_FUNC.CASE` and `SUNDIALS_F77_FUNC.UNDERSCORES` *must* be set in order to bypass the check for a Fortran compiler and define the name-mangling scheme. The defaults for these options in earlier versions of SUNDIALS were `lower` and `one` respectively.

Building with LAPACK

To enable LAPACK, set the `LAPACK_ENABLE` option to `ON`. If the directory containing the LAPACK library is in the `LD_LIBRARY_PATH` environment variable, CMake will set the `LAPACK_LIBRARIES` variable accordingly, otherwise CMake will attempt to find the LAPACK library in standard system locations. To explicitly tell CMake what library to use, the `LAPACK_LIBRARIES` variable can be set to the desired libraries. When setting the LAPACK location explicitly the location of the corresponding BLAS library will also need to be set. Example:

```
% cmake \
> -DCMAKE_INSTALL_PREFIX=/home/myname/sundials/instdir \
> -DEXAMPLES_INSTALL_PATH=/home/myname/sundials/instdir/examples \
> -DBLAS_ENABLE=ON \
> -DBLAS_LIBRARIES=/mylapackpath/lib/libblas.so \
> -DLAPACK_ENABLE=ON \
> -DLAPACK_LIBRARIES=/mylapackpath/lib/liblapack.so \
> /home/myname/sundials/solverdir
%
% make install
%
```



When allowing CMake to automatically locate the LAPACK library, CMake *may* also locate the corresponding BLAS library.

If a working Fortran compiler is not available to infer the Fortran name-mangling scheme, the options `SUNDIALS_F77_FUNC.CASE` and `SUNDIALS_F77_FUNC.UNDERSCORES` *must* be set in order to bypass the check for a Fortran compiler and define the name-mangling scheme. The defaults for these options in earlier versions of SUNDIALS were `lower` and `one` respectively.

Building with KLU

The KLU libraries are part of SuiteSparse, a suite of sparse matrix software, available from the Texas A&M University website: <http://faculty.cse.tamu.edu/davis/suitesparse.html>. SUNDIALS has been tested with SuiteSparse version 4.5.3. To enable KLU, set `KLU_ENABLE` to `ON`, set `KLU_INCLUDE_DIR` to the `include` path of the KLU installation and set `KLU_LIBRARY_DIR` to the `lib` path of the KLU installation. The CMake configure will result in populating the following variables: `AMD_LIBRARY`, `AMD_LIBRARY_DIR`, `BTF_LIBRARY`, `BTF_LIBRARY_DIR`, `COLAMD_LIBRARY`, `COLAMD_LIBRARY_DIR`, and `KLU_LIBRARY`.

Building with SuperLU_MT

The SuperLU_MT libraries are available for download from the Lawrence Berkeley National Laboratory website: http://crd-legacy.lbl.gov/~xiaoye/SuperLU/#superlu_mt. SUNDIALS has been tested with SuperLU_MT version 3.1. To enable SuperLU_MT, set `SUPERLUMT_ENABLE` to `ON`, set `SUPERLUMT_INCLUDE_DIR` to the `SRC` path of the SuperLU_MT installation, and set the variable `SUPERLUMT_LIBRARY_DIR` to the `lib` path of the SuperLU_MT installation. At the same time, the variable `SUPERLUMT_THREAD_TYPE` must be set to either `Pthread` or `OpenMP`.

Do not mix thread types when building SUNDIALS solvers. If threading is enabled for SUNDIALS by having either `OPENMP_ENABLE` or `PTHREAD_ENABLE` set to `ON` then SuperLU_MT should be set to use the same threading type.



Building with PETSc

The PETSc libraries are available for download from the Argonne National Laboratory website: <http://www.mcs.anl.gov/petsc>. SUNDIALS has been tested with PETSc version 3.7.2. To enable PETSc, set `PETSC_ENABLE` to `ON`, set `PETSC_INCLUDE_DIR` to the `include` path of the PETSc installation, and set the variable `PETSC_LIBRARY_DIR` to the `lib` path of the PETSc installation.

Building with *hypre*

The *hypre* libraries are available for download from the Lawrence Livermore National Laboratory website: <http://computation.llnl.gov/projects/hypre>. SUNDIALS has been tested with *hypre* version 2.11.1. To enable *hypre*, set `HYPRE_ENABLE` to `ON`, set `HYPRE_INCLUDE_DIR` to the `include` path of the *hypre* installation, and set the variable `HYPRE_LIBRARY_DIR` to the `lib` path of the *hypre* installation.

Building with CUDA

SUNDIALS CUDA modules and examples have been tested with version 8.0 of the CUDA toolkit. To build them, you need to install the Toolkit and compatible NVIDIA drivers. Both are available for download from the NVIDIA website: <https://developer.nvidia.com/cuda-downloads>. To enable CUDA, set `CUDA_ENABLE` to `ON`. If CUDA is installed in a nonstandard location, you may be prompted to set the variable `CUDA_TOOLKIT_ROOT_DIR` with your CUDA Toolkit installation path. To enable CUDA examples, set `EXAMPLES_ENABLE_CUDA` to `ON`.

Building with RAJA

RAJA is a performance portability layer developed by Lawrence Livermore National Laboratory and can be obtained from <https://github.com/LLNL/RAJA>. SUNDIALS RAJA modules and examples have been tested with RAJA version 0.3. Building SUNDIALS RAJA modules requires a CUDA-enabled RAJA installation. To enable RAJA, set `CUDA_ENABLE` and `RAJA_ENABLE` to `ON`. If RAJA is installed in a nonstandard location you will be prompted to set the variable `RAJA_DIR` with the path to the RAJA CMake configuration file. To enable building the RAJA examples set `EXAMPLES_ENABLE_RAJA` to `ON`.

A.1.5 Testing the build and installation

If SUNDIALS was configured with `EXAMPLES_ENABLE_<language>` options to `ON`, then a set of regression tests can be run after building with the `make` command by running:

```
% make test
```

Additionally, if `EXAMPLES_INSTALL` was also set to `ON`, then a set of smoke tests can be run after installing with the `make install` command by running:

```
% make test_install
```

A.2 Building and Running Examples

Each of the SUNDIALS solvers is distributed with a set of examples demonstrating basic usage. To build and install the examples, set at least of the `EXAMPLES_ENABLE_<language>` options to `ON`, and set `EXAMPLES_INSTALL` to `ON`. Specify the installation path for the examples with the variable `EXAMPLES_INSTALL_PATH`. CMake will generate `CMakeLists.txt` configuration files (and `Makefile` files if on Linux/Unix) that reference the *installed* SUNDIALS headers and libraries.

Either the `CMakeLists.txt` file or the traditional `Makefile` may be used to build the examples as well as serve as a template for creating user developed solutions. To use the supplied `Makefile` simply run `make` to compile and generate the executables. To use CMake from within the installed example directory, run `cmake` (or `ccmake` to use the GUI) followed by `make` to compile the example code. Note that if CMake is used, it will overwrite the traditional `Makefile` with a new CMake-generated `Makefile`. The resulting output from running the examples can be compared with example output bundled in the SUNDIALS distribution.



NOTE: There will potentially be differences in the output due to machine architecture, compiler versions, use of third party libraries etc.

A.3 Configuring, building, and installing on Windows

CMake can also be used to build SUNDIALS on Windows. To build SUNDIALS for use with Visual Studio the following steps should be performed:

1. Unzip the downloaded tar file(s) into a directory. This will be the *solverdir*
2. Create a separate *builddir*
3. Open a Visual Studio Command Prompt and `cd` to *builddir*
4. Run `cmake-gui ../solverdir`
 - (a) Hit Configure
 - (b) Check/Uncheck solvers to be built
 - (c) Change `CMAKE_INSTALL_PREFIX` to *instdir*
 - (d) Set other options as desired
 - (e) Hit Generate
5. Back in the VS Command Window:
 - (a) Run `msbuild ALL_BUILD.vcxproj`
 - (b) Run `msbuild INSTALL.vcxproj`

The resulting libraries will be in the *instdir*. The SUNDIALS project can also now be opened in Visual Studio. Double click on the `ALL_BUILD.vcxproj` file to open the project. Build the whole *solution* to create the SUNDIALS libraries. To use the SUNDIALS libraries in your own projects, you must set the include directories for your project, add the SUNDIALS libraries to your project solution, and set the SUNDIALS libraries as dependencies for your project.

A.4 Installed libraries and exported header files

Using the CMake SUNDIALS build system, the command

```
% make install
```

will install the libraries under *libdir* and the public header files under *includedir*. The values for these directories are *instdir*/`CMAKE_INSTALL_LIBDIR` and *instdir*/`include`, respectively. The location can be changed by setting the CMake variable `CMAKE_INSTALL_PREFIX`. Although all installed libraries reside under *libdir*/`CMAKE_INSTALL_LIBDIR`, the public header files are further organized into subdirectories under *includedir*/`include`.

The installed libraries and exported header files are listed for reference in Table [A.1](#). The file extension *.lib* is typically *.so* for shared libraries and *.a* for static libraries. Note that, in the Tables, names are relative to *libdir* for libraries and to *includedir* for header files.

A typical user program need not explicitly include any of the shared SUNDIALS header files from under the *includedir*/`include/sundials` directory since they are explicitly included by the appropriate solver header files (*e.g.*, `cvode_dense.h` includes `sundials_dense.h`). However, it is both legal and safe to do so, and would be useful, for example, if the functions declared in `sundials_dense.h` are to be used in building a preconditioner.

Table A.1: SUNDIALS libraries and header files

| | | |
|------------------------|--------------|--|
| SHARED | Libraries | n/a |
| | Header files | sundials/sundials_config.h sundials/sundials_fconfig.h sundials/sundials_types.h sundials/sundials_math.h sundials/sundials_nvector.h sundials/sundials_fnvector.h sundials/sundials_matrix.h sundials/sundials_linearsolver.h sundials/sundials_iterative.h sundials/sundials_direct.h sundials/sundials_dense.h sundials/sundials_band.h sundials/sundials_nonlinearsolver.h sundials/sundials_version.h sundials/sundials_mpi_types.h |
| NVECTOR_SERIAL | Libraries | libsundials_nvecserial. <i>lib</i> libsundials_fnvecserial_mod. <i>lib</i> libsundials_fnvecserial.a |
| | Header files | nvector/nvector_serial.h |
| | Module files | fnvector_serial_mod.mod |
| NVECTOR_PARALLEL | Libraries | libsundials_nvecparallel. <i>lib</i> libsundials_fnvecparallel.a |
| | Header files | nvector/nvector_parallel.h |
| NVECTOR_OPENMP | Libraries | libsundials_nvecopenmp. <i>lib</i> libsundials_fnvecopenmp_mod. <i>lib</i> libsundials_fnvecopenmp.a |
| | Header files | nvector/nvector_openmp.h |
| | Module files | fnvector_openmp_mod.mod |
| NVECTOR_OPENMPDEV | Libraries | libsundials_nvecopenmpdev. <i>lib</i> |
| | Header files | nvector/nvector_openmpdev.h |
| NVECTOR_PTHREADS | Libraries | libsundials_nvecpthreads. <i>lib</i> libsundials_fnvecpthreads_mod. <i>lib</i> libsundials_fnvecpthreads.a |
| | Header files | nvector/nvector_pthreads.h |
| | Module files | fnvector_pthreads_mod.mod |
| NVECTOR_PARHYP | Libraries | libsundials_nvecparhyp. <i>lib</i> |
| | Header files | nvector/nvector_parhyp.h |
| continued on next page | | |

| | | |
|-------------------------------------|--------------------------------|--|
| continued from last page | | |
| NVECTOR_PETSC | Libraries | libsundials_nvecpetsc. <i>lib</i> |
| | Header files | nvector/nvector_petsc.h |
| NVECTOR_CUDA | Libraries | libsundials_nveccuda. <i>lib</i> |
| | Libraries | libsundials_nvecmpicuda. <i>lib</i> |
| | Header files | nvector/nvector_cuda.h |
| | | nvector/nvector_mpicuda.h |
| nvector/cuda/ThreadPartitioning.hpp | | |
| nvector/cuda/Vector.hpp | | |
| NVECTOR_RAJA | nvector/cuda/VectorKernels.cuh | |
| | Libraries | libsundials_nveccudaraja. <i>lib</i> |
| | Libraries | libsundials_nveccudampiraja. <i>lib</i> |
| | Header files | nvector/nvector_rajah.h |
| nvector/nvector_mpiraja.h | | |
| nvector/rajah/Vector.hpp | | |
| SUNMATRIX_BAND | Libraries | libsundials_sunmatrixband. <i>lib</i> |
| | | libsundials_fsunmatrixband_mod. <i>lib</i> |
| | | libsundials_fsunmatrixband.a |
| | Header files | sunmatrix/sunmatrix_band.h |
| SUNMATRIX_DENSE | Module files | fsunmatrix_band_mod.mod |
| | Libraries | libsundials_sunmatrixdense. <i>lib</i> |
| | | libsundials_fsunmatrixdense_mod. <i>lib</i> |
| SUNMATRIX_DENSE | | libsundials_fsunmatrixdense.a |
| | Header files | sunmatrix/sunmatrix_dense.h |
| | Module files | fsunmatrix_dense_mod.mod |
| | | |
| SUNMATRIX_SPARSE | Libraries | libsundials_sunmatrixsparse. <i>lib</i> |
| | | libsundials_fsunmatrixsparse_mod. <i>lib</i> |
| | | libsundials_fsunmatrixsparse.a |
| | Header files | sunmatrix/sunmatrix_sparse.h |
| SUNLINSOL_BAND | Module files | fsunmatrix_sparse_mod.mod |
| | Libraries | libsundials_sunlinsolband. <i>lib</i> |
| | | libsundials_fsunlinsolband_mod. <i>lib</i> |
| SUNLINSOL_BAND | | libsundials_fsunlinsolband.a |
| | Header files | sunlinsol/sunlinsol_band.h |
| | Module files | fsunlinsol_band_mod.mod |
| | | |
| SUNLINSOL_DENSE | Libraries | libsundials_sunlinsoldense. <i>lib</i> |
| | | libsundials_fsunlinsoldense_mod. <i>lib</i> |
| | | libsundials_fsunlinsoldense.a |
| | Header files | sunlinsol/sunlinsol_dense.h |
| continued on next page | | |

| | | |
|---------------------------------|--------------|--|
| <i>continued from last page</i> | | |
| | Module files | fsunlinsol_dense.mod.mod |
| SUNLINSOL_KLU | Libraries | libsundials_sunlinsolklu. <i>lib</i> libsundials_fsunlinsolklu_mod. <i>lib</i> libsundials_fsunlinsolklu.a |
| | Header files | sunlinsol/sunlinsol_klu.h |
| | Module files | fsunlinsol_klu.mod.mod |
| SUNLINSOL_LAPACKBAND | Libraries | libsundials_sunlinsollapackband. <i>lib</i> libsundials_fsunlinsollapackband.a |
| | Header files | sunlinsol/sunlinsol_lapackband.h |
| SUNLINSOL_LAPACKDENSE | Libraries | libsundials_sunlinsollapackdense. <i>lib</i> libsundials_fsunlinsollapackdense.a |
| | Header files | sunlinsol/sunlinsol_lapackdense.h |
| SUNLINSOL_PCG | Libraries | libsundials_sunlinsolpcg. <i>lib</i> libsundials_fsunlinsolpcg_mod. <i>lib</i> libsundials_fsunlinsolpcg.a |
| | Header files | sunlinsol/sunlinsol_pcg.h |
| | Module files | fsunlinsol_pcg.mod.mod |
| SUNLINSOL_SPCGGS | Libraries | libsundials_sunlinsolspbcgs. <i>lib</i> libsundials_fsunlinsolspbcgs_mod. <i>lib</i> libsundials_fsunlinsolspbcgs.a |
| | Header files | sunlinsol/sunlinsol_spbcgs.h |
| | Module files | fsunlinsol_spbcgs.mod.mod |
| SUNLINSOL_SPFGMR | Libraries | libsundials_sunlinsolspfgmr. <i>lib</i> libsundials_fsunlinsolspfgmr_mod. <i>lib</i> libsundials_fsunlinsolspfgmr.a |
| | Header files | sunlinsol/sunlinsol_spfgmr.h |
| | Module files | fsunlinsol_spfgmr.mod.mod |
| SUNLINSOL_SPGMR | Libraries | libsundials_sunlinsolspgmr. <i>lib</i> libsundials_fsunlinsolspgmr_mod. <i>lib</i> libsundials_fsunlinsolspgmr.a |
| | Header files | sunlinsol/sunlinsol_spgmr.h |
| | Module files | fsunlinsol_spgmr.mod.mod |
| SUNLINSOL_SPTFQMR | Libraries | libsundials_sunlinsolsptfqmr. <i>lib</i> libsundials_fsunlinsolsptfqmr_mod. <i>lib</i> libsundials_fsunlinsolsptfqmr.a |
| | Header files | sunlinsol/sunlinsol_sptfqmr.h |
| <i>continued on next page</i> | | |

| | | | |
|---------------------------------|--------------|--|-------------------------|
| <i>continued from last page</i> | | | |
| | Module files | fsunlinsol_sptfqmr_mod.mod | |
| SUNLINSOL_SUPERLUMT | Libraries | libsundials_sunlinsolsuperlumt. <i>lib</i> libsundials_fsunlinsolsuperlumt.a | |
| | Header files | sunlinsol/sunlinsol_superlumt.h | |
| SUNNONLINSOL_NEWTON | Libraries | libsundials_sunnonlinsolnewton. <i>lib</i> libsundials_fsunnonlinsolnewton_mod. <i>lib</i> libsundials_fsunnonlinsolnewton.a | |
| | Header files | sunnonlinsol/sunnonlinsol_newton.h | |
| | Module files | fsunnonlinsol_newton_mod.mod | |
| SUNNONLINSOL_FIXEDPOINT | Libraries | libsundials_sunnonlinsolfixedpoint. <i>lib</i> libsundials_fsunnonlinsolfixedpoint.a libsundials_fsunnonlinsolfixedpoint_mod. <i>lib</i> | |
| | Header files | sunnonlinsol/sunnonlinsol_fixedpoint.h | |
| | Module files | fsunnonlinsol_fixedpoint_mod.mod | |
| CVODE | Libraries | libsundials_cvode. <i>lib</i> | libsundials_fcvcde.a |
| | Header files | cvode/cvode.h | cvode/cvode_impl.h |
| | | cvode/cvode_direct.h | cvode/cvode_ls.h |
| | | cvode/cvode_spils.h | cvode/cvode_bandpre.h |
| | Module files | fcvode_mod.mod | |
| CVODES | Libraries | libsundials_cvodes. <i>lib</i> | |
| | Header files | cvodes/cvodes.h | cvodes/cvodes_impl.h |
| | | cvodes/cvodes_direct.h | cvodes/cvodes_ls.h |
| | | cvodes/cvodes_spils.h | cvodes/cvodes_bandpre.h |
| | | cvodes/cvodes_bbdpre.h | |
| ARKODE | Libraries | libsundials_arkode. <i>lib</i> | libsundials_farkode.a |
| | Header files | arkode/arkode.h | arkode/arkode_impl.h |
| | | arkode/arkode_ls.h | arkode/arkode_bandpre.h |
| | | arkode/arkode_bbdpre.h | |
| IDA | Libraries | libsundials_ida. <i>lib</i> | libsundials_fida.a |
| | Header files | ida/ida.h | ida/ida_impl.h |
| | | ida/ida_direct.h | ida/ida_ls.h |
| | | ida/ida_spils.h | ida/ida_bbdpre.h |
| IDAS | Libraries | libsundials_idas. <i>lib</i> | |
| | Header files | idas/idas.h | idas/idas_impl.h |
| | | idas/idas_direct.h | idas/idas_ls.h |
| | | idas/idas_spils.h | idas/idas_bbdpre.h |
| KINSOL | Libraries | libsundials_kinsol. <i>lib</i> | libsundials_fkinsol.a |
| <i>continued on next page</i> | | | |

| | | | |
|---------------------------------|--------------|------------------------|------------------------|
| <i>continued from last page</i> | | | |
| | Header files | kinsol/kinsol.h | kinsol/kinsol_impl.h |
| | | kinsol/kinsol_direct.h | kinsol/kinsol_ls.h |
| | | kinsol/kinsol_spils.h | kinsol/kinsol_bbdpre.h |

Appendix B

IDA Constants

Below we list all input and output constants used by the main solver and linear solver modules, together with their numerical values and a short description of their meaning.

B.1 IDA input constants

| IDA main solver module | | |
|--------------------------------|---|---|
| IDA_NORMAL | 1 | Solver returns at specified output time. |
| IDA_ONE_STEP | 2 | Solver returns after each successful step. |
| IDA_YA_YDP_INIT | 1 | Compute y_a and \dot{y}_d , given y_d . |
| IDA_Y_INIT | 2 | Compute y , given \dot{y} . |
| Iterative linear solver module | | |
| PREC_NONE | 0 | No preconditioning |
| PREC_LEFT | 1 | Preconditioning on the left. |
| MODIFIED_GS | 1 | Use modified Gram-Schmidt procedure. |
| CLASSICAL_GS | 2 | Use classical Gram-Schmidt procedure. |

B.2 IDA output constants

| IDA main solver module | | |
|-------------------------------|----|---|
| IDA_SUCCESS | 0 | Successful function return. |
| IDA_TSTOP_RETURN | 1 | IDASolve succeeded by reaching the specified stopping point. |
| IDA_ROOT_RETURN | 2 | IDASolve succeeded and found one or more roots. |
| IDA_WARNING | 99 | IDASolve succeeded but an unusual situation occurred. |
| IDA_TOO_MUCH_WORK | -1 | The solver took <code>mxstep</code> internal steps but could not reach tout. |
| IDA_TOO_MUCH_ACC | -2 | The solver could not satisfy the accuracy demanded by the user for some internal step. |
| IDA_ERR_FAIL | -3 | Error test failures occurred too many times during one internal time step or minimum step size was reached. |

| | | |
|---------------------|-----|--|
| IDA_CONV_FAIL | -4 | Convergence test failures occurred too many times during one internal time step or minimum step size was reached. |
| IDA_LINIT_FAIL | -5 | The linear solver's initialization function failed. |
| IDA_LSETUP_FAIL | -6 | The linear solver's setup function failed in an unrecoverable manner. |
| IDA_LSOLVE_FAIL | -7 | The linear solver's solve function failed in an unrecoverable manner. |
| IDA_RES_FAIL | -8 | The user-provided residual function failed in an unrecoverable manner. |
| IDA_REP_RES_FAIL | -9 | The user-provided residual function repeatedly returned a recoverable error flag, but the solver was unable to recover. |
| IDA_RTFUNC_FAIL | -10 | The rootfinding function failed in an unrecoverable manner. |
| IDA_CONSTR_FAIL | -11 | The inequality constraints were violated and the solver was unable to recover. |
| IDA_FIRST_RES_FAIL | -12 | The user-provided residual function failed recoverably on the first call. |
| IDA_LINESEARCH_FAIL | -13 | The line search failed. |
| IDA_NO_RECOVERY | -14 | The residual function, linear solver setup function, or linear solver solve function had a recoverable failure, but IDACalcIC could not recover. |
| IDA_NLS_INIT_FAIL | -15 | The nonlinear solver's init routine failed. |
| IDA_NLS_SETUP_FAIL | -16 | The nonlinear solver's setup routine failed. |
| IDA_MEM_NULL | -20 | The <code>ida_mem</code> argument was NULL. |
| IDA_MEM_FAIL | -21 | A memory allocation failed. |
| IDA_ILL_INPUT | -22 | One of the function inputs is illegal. |
| IDA_NO_MALLOC | -23 | The IDA memory was not allocated by a call to <code>IDAInit</code> . |
| IDA_BAD_EWT | -24 | Zero value of some error weight component. |
| IDA_BAD_K | -25 | The k -th derivative is not available. |
| IDA_BAD_T | -26 | The time t is outside the last step taken. |
| IDA_BAD_DKY | -27 | The vector argument where derivative should be stored is NULL. |

IDALS linear solver interface

| | | |
|----------------------|----|---|
| IDALS_SUCCESS | 0 | Successful function return. |
| IDALS_MEM_NULL | -1 | The <code>ida_mem</code> argument was NULL. |
| IDALS_LMEM_NULL | -2 | The IDALS linear solver has not been initialized. |
| IDALS_ILL_INPUT | -3 | The IDALS solver is not compatible with the current NVECTOR module. |
| IDALS_MEM_FAIL | -4 | A memory allocation request failed. |
| IDALS_PMEM_NULL | -5 | The preconditioner module has not been initialized. |
| IDALS_JACFUNC_UNRECV | -6 | The Jacobian function failed in an unrecoverable manner. |
| IDALS_JACFUNC_RECVR | -7 | The Jacobian function had a recoverable error. |
| IDALS_SUNMAT_FAIL | -8 | An error occurred with the current SUNMATRIX module. |
| IDALS_SUNLS_FAIL | -9 | An error occurred with the current SUNLINSOL module. |

Bibliography

- [1] KLU Sparse Matrix Factorization Library. <http://faculty.cse.tamu.edu/davis/suitesparse.html>.
- [2] SuperLU_MT Threaded Sparse Matrix Factorization Library. <http://crd-legacy.lbl.gov/~xiaoye/-SuperLU/>.
- [3] D. G. Anderson. Iterative procedures for nonlinear integral equations. *J. Assoc. Comput. Machinery*, 12:547–560, 1965.
- [4] K. E. Brenan, S. L. Campbell, and L. R. Petzold. *Numerical Solution of Initial-Value Problems in Differential-Algebraic Equations*. SIAM, Philadelphia, Pa, 1996.
- [5] P. N. Brown. A local convergence theory for combined inexact-Newton/finite difference projection methods. *SIAM J. Numer. Anal.*, 24(2):407–434, 1987.
- [6] P. N. Brown and A. C. Hindmarsh. Reduced Storage Matrix Methods in Stiff ODE Systems. *J. Appl. Math. & Comp.*, 31:49–91, 1989.
- [7] P. N. Brown, A. C. Hindmarsh, and L. R. Petzold. Using Krylov Methods in the Solution of Large-Scale Differential-Algebraic Systems. *SIAM J. Sci. Comput.*, 15:1467–1488, 1994.
- [8] P. N. Brown, A. C. Hindmarsh, and L. R. Petzold. Consistent Initial Condition Calculation for Differential-Algebraic Systems. *SIAM J. Sci. Comput.*, 19:1495–1512, 1998.
- [9] P. N. Brown and Y. Saad. Hybrid Krylov Methods for Nonlinear Systems of Equations. *SIAM J. Sci. Stat. Comput.*, 11:450–481, 1990.
- [10] G. D. Byrne. Pragmatic Experiments with Krylov Methods in the Stiff ODE Setting. In J.R. Cash and I. Gladwell, editors, *Computational Ordinary Differential Equations*, pages 323–356, Oxford, 1992. Oxford University Press.
- [11] G. D. Byrne and A. C. Hindmarsh. User Documentation for PODE, An ODE Solver for Parallel Computers. Technical Report UCRL-ID-130884, LLNL, May 1998.
- [12] G. D. Byrne and A. C. Hindmarsh. PODE, An ODE Solver for Parallel Computers. *Intl. J. High Perf. Comput. Apps.*, 13(4):254–365, 1999.
- [13] S. D. Cohen and A. C. Hindmarsh. CPODE, a Stiff/Nonstiff ODE Solver in C. *Computers in Physics*, 10(2):138–143, 1996.
- [14] A. M. Collier, A. C. Hindmarsh, R. Serban, and C.S. Woodward. User Documentation for KINSOL v4.0.2. Technical Report UCRL-SM-208116, LLNL, 2019.
- [15] T. A. Davis and P. N. Ekanathan. Algorithm 907: KLU, a direct sparse solver for circuit simulation problems. *ACM Trans. Math. Softw.*, 37(3), 2010.
- [16] R. S. Dembo, S. C. Eisenstat, and T. Steihaug. Inexact Newton Methods. *SIAM J. Numer. Anal.*, 19:400–408, 1982.

- [17] J. W. Demmel, J. R. Gilbert, and X. S. Li. An asynchronous parallel supernodal algorithm for sparse gaussian elimination. *SIAM J. Matrix Analysis and Applications*, 20(4):915–952, 1999.
- [18] J. E. Dennis and R. B. Schnabel. *Numerical Methods for Unconstrained Optimization and Nonlinear Equations*. SIAM, Philadelphia, 1996.
- [19] H. Fang and Y. Saad. Two classes of secant methods for nonlinear acceleration. *Numer. Linear Algebra Appl.*, 16:197–221, 2009.
- [20] R. W. Freund. A Transpose-Free Quasi-Minimal Residual Algorithm for Non-Hermitian Linear Systems. *SIAM J. Sci. Comp.*, 14:470–482, 1993.
- [21] M. R. Hestenes and E. Stiefel. Methods of Conjugate Gradients for Solving Linear Systems. *J. Research of the National Bureau of Standards*, 49(6):409–436, 1952.
- [22] K. L. Hiebert and L. F. Shampine. Implicitly Defined Output Points for Solutions of ODEs. Technical Report SAND80-0180, Sandia National Laboratories, February 1980.
- [23] A. C. Hindmarsh, P. N. Brown, K. E. Grant, S. L. Lee, R. Serban, D. E. Shumaker, and C. S. Woodward. SUNDIALS, suite of nonlinear and differential/algebraic equation solvers. *ACM Trans. Math. Softw.*, (31):363–396, 2005.
- [24] A. C. Hindmarsh and R. Serban. User Documentation for CVODE v4.0.2. Technical Report UCRL-SM-208108, LLNL, 2019.
- [25] A. C. Hindmarsh, R. Serban, and A. Collier. Example Programs for IDA v4.0.2. Technical Report UCRL-SM-208113, LLNL, 2019.
- [26] A. C. Hindmarsh, R. Serban, and D. R. Reynolds. Example Programs for CVODE v4.0.2. Technical report, LLNL, 2019. UCRL-SM-208110.
- [27] A. C. Hindmarsh and A. G. Taylor. PVODE and KINSOL: Parallel Software for Differential and Nonlinear Systems. Technical Report UCRL-ID-129739, LLNL, February 1998.
- [28] C. T. Kelley. *Iterative Methods for Solving Linear and Nonlinear Equations*. SIAM, Philadelphia, 1995.
- [29] X. S. Li. An overview of SuperLU: Algorithms, implementation, and user interface. *ACM Trans. Math. Softw.*, 31(3):302–325, September 2005.
- [30] P. A. Lott, H. F. Walker, C. S. Woodward, and U. M. Yang. An accelerated Picard method for nonlinear systems related to variably saturated flow. *Adv. Wat. Resour.*, 38:92–101, 2012.
- [31] Daniel R. Reynolds. Example Programs for ARKODE v3.0.2. Technical report, Southern Methodist University, 2019.
- [32] Y. Saad. A flexible inner-outer preconditioned GMRES algorithm. *SIAM J. Sci. Comput.*, 14(2):461–469, 1993.
- [33] Y. Saad and M. H. Schultz. GMRES: A Generalized Minimal Residual Algorithm for Solving Nonsymmetric Linear Systems. *SIAM J. Sci. Stat. Comp.*, 7:856–869, 1986.
- [34] H. A. Van Der Vorst. Bi-CGSTAB: A Fast and Smoothly Converging Variant of Bi-CG for the Solution of Nonsymmetric Linear Systems. *SIAM J. Sci. Stat. Comp.*, 13:631–644, 1992.
- [35] H. F. Walker and P. Ni. Anderson acceleration for fixed-point iterations. *SIAM Jour. Num. Anal.*, 49(4):1715–1735, 2011.

Index

- BIG_REAL, [26](#), [103](#)
- boolean type, [26](#)
- CONSTR_VEC, [90](#)
- data types
 - Fortran, [79](#)
- eh_data, [67](#)
- error messages, [39](#)
 - redirecting, [39](#)
 - user-defined handler, [41](#), [66](#)
- FIDA interface module
 - interface to the IDABBDPRE module, [93–94](#)
 - optional input and output, [89](#)
 - rootfinding, [92](#)
 - usage, [82–89](#)
 - user-callable functions, [80–81](#)
 - user-supplied functions, [81](#)
- FIDABANDSETJAC, [85](#)
- FIDABBDINIT, [93](#)
- FIDABBDOPT, [94](#)
- FIDABBDSREINIT, [94](#)
- FIDABJAC, [85](#)
- FIDACOMMFN, [94](#)
- FIDADENSESETJAC, [85](#)
- FIDADJAC, [84](#)
- FIDADLSINIT, [84](#)
- FIDAWE, [84](#)
- FIDAWESET, [84](#)
- FIDAFREE, [89](#)
- FIDAGETDKY, [88](#)
- FIDAGETERRWEIGHTS, [89](#)
- FIDAGETESTLOCALERR, [92](#)
- FIDAGLOCFN, [94](#)
- FIDAJTIMES, [86](#), [95](#)
- FIDAJTSETUP, [86](#), [95](#)
- FIDALSINIT, [84](#)
- FIDALSSETJAC, [86](#)
- FIDALSSETPREC, [87](#)
- FIDAMALLOC, [84](#)
- FIDAMALLOC, [83](#)
- FIDAPSET, [87](#)
- FIDAPSOL, [87](#)
- FIDAREINIT, [88](#)
- FIDARESFUN, [82](#)
- FIDASETIIN, [89](#)
- FIDASETRIN, [89](#)
- FIDASETVIN, [89](#)
- FIDASOLVE, [88](#)
- FIDAPARSESETJAC, [86](#)
- FIDASPILSETJAC, [87](#)
- FIDASPILSETPREC, [88](#)
- FIDASPILSINIT, [84](#)
- FIDATOLREINIT, [89](#)
- fnvector_serial_mod, [112](#)
- FSUNBANDLINSOLINIT, [191](#)
- FSUNDENSELINSOLINIT, [189](#)
- FSUNFIXEDPOINTINIT, [254](#)
- FSUNKLUINIT, [200](#)
- FSUNKLUREINIT, [201](#)
- FSUNKLUSETORDERING, [202](#)
- FSUNLAPACKBANDINIT, [196](#)
- FSUNLAPACKDENSEINIT, [194](#)
- fsunlinsol_band_mod, [191](#)
- fsunlinsol_dense_mod, [189](#)
- fsunlinsol_klu_mod, [200](#)
- fsunlinsol_pcg_mod, [234](#)
- fsunlinsol_spgmrs_mod, [222](#)
- fsunlinsol_spgmrs_mod, [216](#)
- fsunlinsol_spgmrs_mod, [210](#)
- fsunlinsol_sptfqmr_mod, [228](#)
- FSUNMASSBANDLINSOLINIT, [192](#)
- FSUNMASSDENSELINSOLINIT, [189](#)
- FSUNMASSKLUNIT, [201](#)
- FSUNMASSKLUREINIT, [201](#)
- FSUNMASSKLUSEORDERING, [202](#)
- FSUNMASSLAPACKBANDINIT, [197](#)
- FSUNMASSLAPACKDENSEINIT, [194](#)
- FSUNMASSPCGINIT, [234](#)
- FSUNMASSPCGSETMAXL, [235](#)
- FSUNMASSPCGSETPRECTYPE, [235](#)
- FSUNMASSSPBCGSINIT, [223](#)
- FSUNMASSSPBCGSSETMAXL, [224](#)
- FSUNMASSSPBCGSSETPRECTYPE, [224](#)
- FSUNMASSSPFGMRINIT, [217](#)

- FSUNMASSSPFGMRSETGSTYPE, 217
- FSUNMASSSPFGMRSETMAXRS, 218
- FSUNMASSSPFGMRSETPRECTYPE, 218
- FSUNMASSSPGMRINIT, 210
- FSUNMASSSPGMRSETGSTYPE, 211
- FSUNMASSSPGMRSETMAXRS, 212
- FSUNMASSSPGMRSETPRECTYPE, 211
- FSUNMASSSPTFQMRINIT, 228
- FSUNMASSSPTFQMRSETMAXL, 229
- FSUNMASSSPTFQMRSETPRECTYPE, 229
- FSUNMASSSUPERLUMTINIT, 205
- FSUNMASSUPERLUMTSETORDERING, 206
- fsunmatrix_band_mod, 165
- fsunmatrix_dense_mod, 160
- fsunmatrix_sparse_mod, 173
- FSUNNEWTONINIT, 250
- fsunnonlinsol_fixedpoint_mod, 254
- fsunnonlinsol_newton_mod, 250
- FSUNPCGINIT, 234
- FSUNPCGSETMAXL, 235
- FSUNPCGSETPRECTYPE, 235
- FSUNSPBCGSINIT, 223
- FSUNSPBCGSSETMAXL, 224
- FSUNSPBCGSSETPRECTYPE, 223
- FSUNSPFGMRINIT, 216
- FSUNSPFGMRSETGSTYPE, 217
- FSUNSPFGMRSETMAXRS, 218
- FSUNSPFGMRSETPRECTYPE, 218
- FSUNSPGMRINIT, 210
- FSUNSPGMRSETGSTYPE, 211
- FSUNSPGMRSETMAXRS, 212
- FSUNSPGMRSETPRECTYPE, 211
- FSUNSPTFQMRINIT, 228
- FSUNSPTFQMRSETMAXL, 229
- FSUNSPTFQMRSETPRECTYPE, 229
- FSUNSUPERLUMTINIT, 205
- FSUNSUPERLUMTSETORDERING, 205
- half-bandwidths, 76
- header files, 27, 75
- ID_VEC, 90
- IDA
 - motivation for writing in C, 1
 - package structure, 19
- IDA linear solver interface
 - IDALS, 35
- IDA linear solver interfaces, 19
- IDA linear solvers
 - header files, 27
 - implementation details, 20
 - NVECTOR compatibility, 25
 - selecting one, 35
- ida/ida.h, 27
- ida/ida_ls.h, 27
- IDA_BAD_DKY, 52
- IDA_BAD_EWT, 37
- IDA_BAD_K, 52
- IDA_BAD_T, 52
- IDA_CONSTR_FAIL, 37, 39
- IDA_CONV_FAIL, 37, 39
- IDA_ERR_FAIL, 39
- IDA_FIRST_RES_FAIL, 37
- IDA_ILL_INPUT, 32, 33, 36–38, 42–45, 49–51, 60, 65
- IDA_LINESEARCH_FAIL, 37
- IDA_LINIT_FAIL, 37, 39
- IDA_LSETUP_FAIL, 37, 39
- IDA_LSOLVE_FAIL, 37, 39
- IDA_MEM_FAIL, 32, 43, 59
- IDA_MEM_NULL, 32, 33, 36–38, 41–45, 48–52, 54–60, 65
- IDA_NO_MALLOC, 33, 37, 65
- IDA_NO_RECOVERY, 37
- IDA_NORMAL, 38
- IDA_ONE_STEP, 38
- IDA_REP_RES_ERR, 39
- IDA_RES_FAIL, 37, 39
- IDA_ROOT_RETURN, 38
- IDA_RTFUNC_FAIL, 39, 68
- IDA_SUCCESS, 32, 33, 36–38, 41–45, 48–52, 60, 65
- IDA_TOO_MUCH_ACC, 39
- IDA_TOO_MUCH_WORK, 39
- IDA_TSTOP_RETURN, 38
- IDA_WARNING, 67
- IDA_Y_INIT, 36
- IDA_YA_YDP_INIT, 36
- IDABBDPRE preconditioner
 - description, 73–74
 - optional output, 77–78
 - usage, 75–76
 - user-callable functions, 76–77
 - user-supplied functions, 74–75
- IDABBDPrecGetNumGfnEvals, 78
- IDABBDPrecGetWorkSpace, 77
- IDABBDPrecInit, 76
- IDABBDPrecReInit, 77
- IDACalcIC, 36
- IDACreate, 32
- IDADlsGetLastFlag, 64
- IDADlsGetNumJacEvals, 61
- IDADlsGetNumRhsEvals, 62
- IDADlsGetReturnFlagName, 65
- IDADlsGetWorkspace, 61
- IDADlsJacFn, 69
- IDADlsSetJacFn, 46
- IDADlsSetLinearSolver, 35
- IDAErrorHandlerFn, 66

- IDAEwtFn, 67
- IDAFree, 31, 32
- IDAGetActualInitStep, 57
- IDAGetConsistentIC, 60
- IDAGetCurrentOrder, 56
- IDAGetCurrentStep, 56
- IDAGetCurrentTime, 57
- IDAGetDky, 51
- IDAGetErrWeights, 57
- IDAGetEstLocalErrors, 58
- IDAGetIntegratorStats, 58
- IDAGetLastLinFlag, 64
- IDAGetLastOrder, 56
- IDAGetLastStep, 56
- IDAGetLinReturnFlagName, 64
- IDAGetLinWorkspace, 61
- IDAGetNonlinSolvStats, 59
- IDAGetNumBacktrackOps, 59
- IDAGetNumErrTestFails, 55
- IDAGetNumGEvals, 60
- IDAGetNumJacEvals, 61
- IDAGetNumJtimesEvals, 64
- IDAGetNumJTSetupEvals, 63
- IDAGetNumLinConvFails, 62
- IDAGetNumLinIters, 62
- IDAGetNumLinResEvals, 62
- IDAGetNumLinSolvSetups, 55
- IDAGetNumNonlinSolvConvFails, 59
- IDAGetNumNonlinSolvIters, 58
- IDAGetNumPrecEvals, 63
- IDAGetNumPrecSolves, 63
- IDAGetNumResEvals, 55
- IDAGetNumSteps, 55
- IDAGetReturnFlagName, 59
- IDAGetRootInfo, 60
- IDAGetTolScaleFactor, 57
- IDAGetWorkspace, 54
- IDAInit, 32, 65
- IDALS linear solver interface
 - convergence test, 48
 - Jacobian approximation used by, 45, 46
 - memory requirements, 61
 - optional input, 45–48
 - optional output, 61–65
 - preconditioner setup function, 47, 72
 - preconditioner solve function, 47, 71
- IDALS_ILL_INPUT, 35, 47, 48, 77
- IDALS_LMEM_NULL, 45–48, 61–64, 76, 77
- IDALS_MEM_FAIL, 35, 76
- IDALS_MEM_NULL, 35, 45–48, 61–64
- IDALS_PMEM_NULL, 77, 78
- IDALS_SUCCESS, 35, 45–48, 61–64
- IDALS_SUNLS_FAIL, 35, 46, 48
- IDALsJacFn, 68
- IDALsJacTimesSetupFn, 70
- IDALsJacTimesVecFn, 70
- IDALsPrecSetupFn, 72
- IDALsPrecSolveFn, 71
- IDAreInit, 65
- IDAResFn, 32, 66
- IDARootFn, 67
- IDARootInit, 37
- IDASetConstraints, 45
- IDASetEpsLin, 48
- IDASetErrFile, 39
- IDASetErrHandlerFn, 41
- IDASetId, 44
- IDASetIncrementFactor, 46, 47
- IDASetInitStep, 42
- IDASetJacFn, 45
- IDASetJacTimes, 46
- IDASetLinearSolver, 30, 35, 68, 156
- IDASetLineSearchOffIC, 50
- IDASetMaxBacksIC, 50
- IDASetMaxConvFails, 43
- IDASetMaxErrTestFails, 43
- IDASetMaxNonlinIters, 43
- IDASetMaxNumItersIC, 49
- IDASetMaxNumJacsIC, 49
- IDASetMaxNumSteps, 42
- IDASetMaxNumStepsIC, 49
- IDASetMaxOrd, 41
- IDASetMaxStep, 42
- IDASetNoInactiveRootWarn, 51
- IDASetNonlinConvCoef, 44
- IDASetNonlinConvCoefIC, 48
- IDASetNonLinearSolver, 36
- IDASetNonlinearSolver, 30, 36
- IDASetPreconditioner, 47
- IDASetRootDirection, 51
- IDASetStepToleranceIC, 50
- IDASetStopTime, 43
- IDASetSuppressAlg, 44
- IDASetUserData, 41
- IDASolve, 30, 38
- IDASpilsGetLastFlag, 64
- IDASpilsGetNumConvFails, 62
- IDASpilsGetNumJtimesEvals, 64
- IDASpilsGetNumJTSetupEvals, 63
- IDASpilsGetNumLinIters, 62
- IDASpilsGetNumPrecEvals, 63
- IDASpilsGetNumPrecSolves, 63
- IDASpilsGetNumRhsEvals, 62
- IDASpilsGetReturnFlagName, 65
- IDASpilsGetWorkspace, 61
- IDASpilsJacTimesSetupFn, 71
- IDASpilsJacTimesVecFn, 70
- IDASpilsPrecSetupFn, 73

- IDASpilsPrecSolveFn, 72
- IDASpilsSetEpsLin, 48
- IDASpilsSetIncrementFactor, 47
- IDASpilsSetJacTimes, 46
- IDASpilsSetLinearSolver, 35
- IDASpilsSetPreconditioner, 48
- IDASStolerances, 33
- IDASVtolerances, 33
- IDAWFtolerances, 33
- INIT_STEP, 90
- IOUT, 89, 91
- itask, 38
- Jacobian approximation function
 - band
 - use in FIDA, 85
 - dense
 - use in FIDA, 84
 - difference quotient, 45
 - Jacobian times vector
 - difference quotient, 46
 - use in FIDA, 86
 - user-supplied, 46, 70
 - Jacobian-vector setup
 - user-supplied, 70–71
 - sparse
 - use in FIDA, 85
 - user-supplied, 45, 68–69
- LS_OFF_IC, 90
- MAX_CONVFAIL, 90
- MAX_ERRFAIL, 90
- MAX_NITERS, 90
- MAX_NITERS_IC, 90
- MAX_NJE_IC, 90
- MAX_NSTEPS, 90
- MAX_NSTEPS_IC, 90
- MAX_ORD, 90
- MAX_STEP, 90
- maxord, 65
- memory requirements
 - IDA solver, 54
 - IDABBDPRE preconditioner, 77
 - IDALS linear solver interface, 61
- N_VCloneVectorArray, 98
- N_VCloneVectorArray_OpenMP, 119
- N_VCloneVectorArray_OpenMPDEV, 146
- N_VCloneVectorArray_Parallel, 114
- N_VCloneVectorArray_ParHyp, 128
- N_VCloneVectorArray_Petsc, 132
- N_VCloneVectorArray_Pthreads, 124
- N_VCloneVectorArray_Serial, 109
- N_VCloneVectorArray_Empty, 98
- N_VCloneVectorArray_Empty_OpenMP, 119
- N_VCloneVectorArray_Empty_OpenMPDEV, 146
- N_VCloneVectorArray_Empty_Parallel, 114
- N_VCloneVectorArray_Empty_ParHyp, 129
- N_VCloneVectorArray_Empty_Petsc, 132
- N_VCloneVectorArray_Empty_Pthreads, 124
- N_VCloneVectorArray_Empty_Serial, 109
- N_VCopyFromDevice_Cuda, 138
- N_VCopyFromDevice_OpenMPDEV, 147
- N_VCopyFromDevice_Raja, 143
- N_VCopyToDevice_Cuda, 138
- N_VCopyToDevice_OpenMPDEV, 147
- N_VCopyToDevice_Raja, 143
- N_VDestroyVectorArray, 98
- N_VDestroyVectorArray_OpenMP, 119
- N_VDestroyVectorArray_OpenMPDEV, 146
- N_VDestroyVectorArray_Parallel, 114
- N_VDestroyVectorArray_ParHyp, 129
- N_VDestroyVectorArray_Petsc, 132
- N_VDestroyVectorArray_Pthreads, 124
- N_VDestroyVectorArray_Serial, 110
- N_Vector, 27, 97
- N_VEnableConstVectorArray_Cuda, 139
- N_VEnableConstVectorArray_OpenMP, 121
- N_VEnableConstVectorArray_OpenMPDEV, 148
- N_VEnableConstVectorArray_Parallel, 116
- N_VEnableConstVectorArray_ParHyp, 130
- N_VEnableConstVectorArray_Petsc, 133
- N_VEnableConstVectorArray_Pthreads, 126
- N_VEnableConstVectorArray_Raja, 144
- N_VEnableConstVectorArray_Serial, 111
- N_VEnableDotProdMulti_Cuda, 139
- N_VEnableDotProdMulti_OpenMP, 120
- N_VEnableDotProdMulti_OpenMPDEV, 148
- N_VEnableDotProdMulti_Parallel, 116
- N_VEnableDotProdMulti_ParHyp, 130
- N_VEnableDotProdMulti_Petsc, 133
- N_VEnableDotProdMulti_Pthreads, 126
- N_VEnableDotProdMulti_Serial, 111
- N_VEnableFusedOps_Cuda, 139
- N_VEnableFusedOps_OpenMP, 120
- N_VEnableFusedOps_OpenMPDEV, 147
- N_VEnableFusedOps_Parallel, 115
- N_VEnableFusedOps_ParHyp, 129
- N_VEnableFusedOps_Petsc, 133
- N_VEnableFusedOps_Pthreads, 125
- N_VEnableFusedOps_Raja, 143
- N_VEnableFusedOps_Serial, 110
- N_VEnableLinearCombination_Cuda, 139
- N_VEnableLinearCombination_OpenMP, 120
- N_VEnableLinearCombination_OpenMPDEV, 147
- N_VEnableLinearCombination_Parallel, 115
- N_VEnableLinearCombination_ParHyp, 129
- N_VEnableLinearCombination_Petsc, 133

- N_VEnableLinearCombination_Pthreads, 125
- N_VEnableLinearCombination_Raja, 143
- N_VEnableLinearCombination_Serial, 110
- N_VEnableLinearCombinationVectorArray_Cuda, 140
- N_VEnableLinearCombinationVectorArray_OpenMP, 121
- N_VEnableLinearCombinationVectorArray_OpenMPDEV, 149
- N_VEnableLinearCombinationVectorArray_Parallel, 117
- N_VEnableLinearCombinationVectorArray_ParHyp, 131
- N_VEnableLinearCombinationVectorArray_Petsc, 134
- N_VEnableLinearCombinationVectorArray_Pthreads, 127
- N_VEnableLinearCombinationVectorArray_Raja, 144
- N_VEnableLinearCombinationVectorArray_Serial, 112
- N_VEnableLinearSumVectorArray_Cuda, 139
- N_VEnableLinearSumVectorArray_OpenMP, 121
- N_VEnableLinearSumVectorArray_OpenMPDEV, 148
- N_VEnableLinearSumVectorArray_Parallel, 116
- N_VEnableLinearSumVectorArray_ParHyp, 130
- N_VEnableLinearSumVectorArray_Petsc, 133
- N_VEnableLinearSumVectorArray_Pthreads, 126
- N_VEnableLinearSumVectorArray_Raja, 144
- N_VEnableLinearSumVectorArray_Serial, 111
- N_VEnableScaleAddMulti_Cuda, 139
- N_VEnableScaleAddMulti_OpenMP, 120
- N_VEnableScaleAddMulti_OpenMPDEV, 147
- N_VEnableScaleAddMulti_Parallel, 115
- N_VEnableScaleAddMulti_ParHyp, 129
- N_VEnableScaleAddMulti_Petsc, 133
- N_VEnableScaleAddMulti_Pthreads, 125
- N_VEnableScaleAddMulti_Raja, 143
- N_VEnableScaleAddMulti_Serial, 111
- N_VEnableScaleAddMultiVectorArray_Cuda, 140
- N_VEnableScaleAddMultiVectorArray_OpenMP, 121
- N_VEnableScaleAddMultiVectorArray_OpenMPDEV, 148
- N_VEnableScaleAddMultiVectorArray_Parallel, 116
- N_VEnableScaleAddMultiVectorArray_ParHyp, 130
- N_VEnableScaleAddMultiVectorArray_Petsc, 134
- N_VEnableScaleAddMultiVectorArray_Pthreads, 126
- N_VEnableScaleAddMultiVectorArray_Raja, 144
- N_VEnableScaleAddMultiVectorArray_Serial, 112
- N_VEnableScaleVectorArray_Cuda, 139
- N_VEnableScaleVectorArray_OpenMP, 121
- N_VEnableScaleVectorArray_OpenMPDEV, 148
- N_VEnableScaleVectorArray_Parallel, 116
- N_VEnableScaleVectorArray_ParHyp, 130
- N_VEnableScaleVectorArray_Petsc, 133
- N_VEnableScaleVectorArray_Pthreads, 126
- N_VEnableScaleVectorArray_Raja, 144
- N_VEnableScaleVectorArray_Serial, 111
- N_VEnableWrmsNormMaskVectorArray_Cuda, 140
- N_VEnableWrmsNormMaskVectorArray_OpenMP, 121
- N_VEnableWrmsNormMaskVectorArray_OpenMPDEV, 148
- N_VEnableWrmsNormMaskVectorArray_Parallel, 116
- N_VEnableWrmsNormMaskVectorArray_ParHyp, 130
- N_VEnableWrmsNormMaskVectorArray_Petsc, 134
- N_VEnableWrmsNormMaskVectorArray_Pthreads, 126
- N_VEnableWrmsNormMaskVectorArray_Serial, 111
- N_VEnableWrmsNormVectorArray_Cuda, 140
- N_VEnableWrmsNormVectorArray_OpenMP, 121
- N_VEnableWrmsNormVectorArray_OpenMPDEV, 148
- N_VEnableWrmsNormVectorArray_Parallel, 116
- N_VEnableWrmsNormVectorArray_ParHyp, 130
- N_VEnableWrmsNormVectorArray_Petsc, 134
- N_VEnableWrmsNormVectorArray_Pthreads, 126
- N_VEnableWrmsNormVectorArray_Serial, 111
- N_VGetDeviceArrayPointer_Cuda, 136
- N_VGetDeviceArrayPointer_OpenMPDEV, 146
- N_VGetDeviceArrayPointer_Raja, 141
- N_VGetHostArrayPointer_Cuda, 136
- N_VGetHostArrayPointer_OpenMPDEV, 146
- N_VGetHostArrayPointer_Raja, 141
- N_VGetLength_Cuda, 135
- N_VGetLength_OpenMP, 119
- N_VGetLength_OpenMPDEV, 146
- N_VGetLength_Parallel, 115
- N_VGetLength_Pthreads, 125
- N_VGetLength_Raja, 141
- N_VGetLength_Serial, 110
- N_VGetLocalLength_Cuda, 135
- N_VGetLocalLength_Parallel, 115
- N_VGetLocalLength_Raja, 141
- N_VGetMPIComm_Cuda, 136
- N_VGetMPIComm_Raja, 142
- N_VGetVector_ParHyp, 128
- N_VGetVector_Petsc, 132
- N_VIsManagedMemory_Cuda, 136
- N_VMake_Cuda, 137
- N_VMake_OpenMP, 119
- N_VMake_OpenMPDEV, 146
- N_VMake_Parallel, 114
- N_VMake_ParHyp, 128
- N_VMake_Petsc, 132
- N_VMake_Pthreads, 124
- N_VMake_Raja, 142
- N_VMake_Serial, 109
- N_VMakeManaged_Cuda, 137

- N_VNew_Cuda, 136
- N_VNew_OpenMP, 119
- N_VNew_OpenMPDEV, 146
- N_VNew_Parallel, 114
- N_VNew_Pthreads, 124
- N_VNew_Raja, 142
- N_VNew_SensWrapper, 247
- N_VNew_Serial, 109
- N_VNewEmpty_Cuda, 137
- N_VNewEmpty_OpenMP, 119
- N_VNewEmpty_OpenMPDEV, 146
- N_VNewEmpty_Parallel, 114
- N_VNewEmpty_ParHyp, 128
- N_VNewEmpty_Petsc, 132
- N_VNewEmpty_Pthreads, 124
- N_VNewEmpty_Raja, 142
- N_VNewEmpty_SensWrapper, 247
- N_VNewEmpty_Serial, 109
- N_VNewManaged_Cuda, 137
- N_VPrint_Cuda, 138
- N_VPrint_OpenMP, 120
- N_VPrint_OpenMPDEV, 147
- N_VPrint_Parallel, 115
- N_VPrint_ParHyp, 129
- N_VPrint_Petsc, 132
- N_VPrint_Pthreads, 125
- N_VPrint_Raja, 143
- N_VPrint_Serial, 110
- N_VPrintFile_Cuda, 138
- N_VPrintFile_OpenMP, 120
- N_VPrintFile_OpenMPDEV, 147
- N_VPrintFile_Parallel, 115
- N_VPrintFile_ParHyp, 129
- N_VPrintFile_Petsc, 132
- N_VPrintFile_Pthreads, 125
- N_VPrintFile_Raja, 143
- N_VPrintFile_Serial, 110
- N_VSetCudaStream_Cuda, 138
- NLCONV_COEF, 90
- NLCONV_COEF_IC, 90
- NV_COMM_P, 113
- NV_CONTENT_OMP, 118
- NV_CONTENT_OMPDEV, 145
- NV_CONTENT_P, 113
- NV_CONTENT_PT, 123
- NV_CONTENT_S, 108
- NV_DATA_DEV_OMPDEV, 145
- NV_DATA_HOST_OMPDEV, 145
- NV_DATA_OMP, 118
- NV_DATA_P, 113
- NV_DATA_PT, 123
- NV_DATA_S, 108
- NV_GLOBLLENGTH_P, 113
- NV_Ith_OMP, 118
- NV_Ith_P, 114
- NV_Ith_PT, 123
- NV_Ith_S, 109
- NV_LENGTH_OMP, 118
- NV_LENGTH_OMPDEV, 145
- NV_LENGTH_PT, 123
- NV_LENGTH_S, 108
- NV_LOCLENGTH_P, 113
- NV_NUM_THREADS_OMP, 118
- NV_NUM_THREADS_PT, 123
- NV_OWN_DATA_OMP, 118
- NV_OWN_DATA_OMPDEV, 145
- NV_OWN_DATA_P, 113
- NV_OWN_DATA_PT, 123
- NV_OWN_DATA_S, 108
- NVECTOR module, 97
- nvector_openmp_mod, 122
- nvector_pthreads_mod, 127
- optional input
 - generic linear solver interface, 45–48
 - initial condition calculation, 48–50
 - iterative linear solver, 47–48
 - matrix-based linear solver, 45–46
 - matrix-free linear solver, 46–47
 - rootfinding, 50–51
 - solver, 39–45
- optional output
 - band-block-diagonal preconditioner, 77–78
 - generic linear solver interface, 61–65
 - initial condition calculation, 59–60
 - interpolated solution, 51
 - solver, 54–59
 - version, 52–54
- portability, 26
 - Fortran, 79
- Preconditioner setup routine
 - use in FIDA, 87
- Preconditioner solve routine
 - use in FIDA, 87
- preconditioning
 - advice on, 17, 20
 - band-block diagonal, 73
 - setup and solve phases, 20
 - user-supplied, 47–48, 71, 72
- RCONST, 26
- realtype, 26
- reinitialization, 65
- residual function, 66
- Rootfinding, 17, 30, 37, 92
- ROUT, 89, 91
- SM_COLS_B, 162

- SM_COLS_D, 157
- SM_COLUMN_B, 69, 162
- SM_COLUMN_D, 69, 158
- SM_COLUMN_ELEMENT_B, 69, 162
- SM_COLUMNS_B, 162
- SM_COLUMNS_D, 157
- SM_COLUMNS_S, 169
- SM_CONTENT_B, 162
- SM_CONTENT_D, 157
- SM_CONTENT_S, 169
- SM_DATA_B, 162
- SM_DATA_D, 157
- SM_DATA_S, 169
- SM_ELEMENT_B, 69, 162
- SM_ELEMENT_D, 69, 158
- SM_INDEXPTRS_S, 169
- SM_INDEXVALS_S, 169
- SM_LBAND_B, 162
- SM_LDATA_B, 162
- SM_LDATA_D, 157
- SM_LDIM_B, 162
- SM_NNZ_S, 69, 169
- SM_NP_S, 169
- SM_ROWS_B, 162
- SM_ROWS_D, 157
- SM_ROWS_S, 169
- SM_SPARSETYPE_S, 169
- SM_SUBAND_B, 162
- SM_UBAND_B, 162
- SMALL_REAL, 26
- step size bounds, 42
- STEP_TOL_IC, 90
- STOP_TIME, 90
- SUNBandMatrix, 29, 163
- SUNBandMatrix_Cols, 165
- SUNBandMatrix_Column, 165
- SUNBandMatrix_Columns, 164
- SUNBandMatrix_Data, 165
- SUNBandMatrix_LDim, 164
- SUNBandMatrix_LowerBandwidth, 164
- SUNBandMatrix_Print, 164
- SUNBandMatrix_Rows, 164
- SUNBandMatrix_StoredUpperBandwidth, 164
- SUNBandMatrix_UpperBandwidth, 164
- SUNBandMatrix_Storage, 163
- SUNDenseMatrix, 29, 158
- SUNDenseMatrix_Cols, 159
- SUNDenseMatrix_Column, 159
- SUNDenseMatrix_Columns, 158
- SUNDenseMatrix_Data, 159
- SUNDenseMatrix_LData, 159
- SUNDenseMatrix_Print, 158
- SUNDenseMatrix_Rows, 158
- sundials/sundials_linearsolver.h, 175
- sundials_nonlinearsolver.h, 27
- sundials_nvector.h, 27
- sundials_types.h, 26, 27
- SUNDIALSGetVersion, 52
- SUNDIALSGetVersionNumber, 52
- sunindextype, 26
- SUNLinearSolver, 175, 182
- SUNLinearSolver module, 175
- SUNLINEARSOLVER_DIRECT, 177, 184
- SUNLINEARSOLVER_ITERATIVE, 177, 185
- SUNLINEARSOLVER_MATRIX_ITERATIVE, 177, 185
- sunlinsol/sunlinsol_band.h, 27
- sunlinsol/sunlinsol_dense.h, 27
- sunlinsol/sunlinsol_klu.h, 27
- sunlinsol/sunlinsol_lapackband.h, 27
- sunlinsol/sunlinsol_lapackdense.h, 27
- sunlinsol/sunlinsol_pcg.h, 28
- sunlinsol/sunlinsol_spgmr.h, 27
- sunlinsol/sunlinsol_sptfqmr.h, 28
- sunlinsol/sunlinsol_superlumt.h, 27
- SUNLinSol_Band, 35, 190
- SUNLinSol_Dense, 35, 188
- SUNLinSol_KLU, 35, 198
- SUNLinSol_KLUReInit, 199
- SUNLinSol_KLUSetOrdering, 201
- SUNLinSol_LapackBand, 35, 195
- SUNLinSol_LapackDense, 35, 193
- SUNLinSol_PCG, 35, 232, 234
- SUNLinSol_PCGSetMaxl, 233
- SUNLinSol_PCGSetPrecType, 233
- SUNLinSol_SPBCGS, 35, 221, 223
- SUNLinSol_SPBCGSSetMaxl, 222
- SUNLinSol_SPBCGSSetPrecType, 222
- SUNLinSol_SPGMR, 35, 214, 217
- SUNLinSol_SPGMRSetMaxRestarts, 216
- SUNLinSol_SPGMRSetPrecType, 215
- SUNLinSol_SPGMR, 35, 207, 210
- SUNLinSol_SPGMRSetMaxRestarts, 209
- SUNLinSol_SPGMRSetPrecType, 209
- SUNLinSol_SPTFQMR, 35, 226, 228
- SUNLinSol_SPTFQMRSetMaxl, 227
- SUNLinSol_SPTFQMRSetPrecType, 227
- SUNLinSol_SuperLUMT, 35, 203
- SUNLinSol_SuperLUMTSetOrdering, 205
- SUNLinSolFree, 31, 176, 178
- SUNLinSolGetType, 176
- SUNLinSolInitialize, 176, 177
- SUNLinSolLastFlag, 180
- SUNLinSolNumIters, 179
- SUNLinSolResNorm, 179
- SUNLinSolSetATimes, 177, 178, 185
- SUNLinSolSetPreconditioner, 179

- SUNLinSolSetScalingVectors, 179
- SUNLinSolSetup, 176, 177, 185
- SUNLinSolSolve, 176, 177
- SUNLinSolSpace, 180
- SUNMatDestroy, 31
- SUNMatrix, 153
- SUNMatrix module, 153
- SUNNonlinearSolver, 27, 239
- SUNNonlinearSolver module, 239
- SUNNONLINEARSOLVER_FIXEDPOINT, 240
- SUNNONLINEARSOLVER_ROOTFIND, 240
- SUNNonlinSol.FixedPoint, 252, 255
- SUNNonlinSol.FixedPointSens, 253
- SUNNonlinSol.Newton, 249
- SUNNonlinSol.NewtonSens, 249
- SUNNonlinSolFree, 31, 241
- SUNNonlinSolGetCurIter, 243
- SUNNonlinSolGetNumConvFails, 243
- SUNNonlinSolGetNumIters, 243
- SUNNonlinSolGetSysFn.FixedPoint, 253
- SUNNonlinSolGetSysFn.Newton, 250
- SUNNonlinSolGetType, 240
- SUNNonlinSolInitialize, 240
- SUNNonlinSolLSetupFn, 241
- SUNNonlinSolSetConvTestFn, 242
- SUNNonlinSolSetLSolveFn, 242
- SUNNonlinSolSetMaxIters, 242
- SUNNonlinSolSetSysFn, 241
- SUNNonlinSolSetup, 240
- SUNNonlinSolSolve, 240
- SUNSparseFromBandMatrix, 170
- SUNSparseFromDenseMatrix, 170
- SUNSparseMatrix, 29, 170
- SUNSparseMatrix.Columns, 171
- SUNSparseMatrix.Data, 172
- SUNSparseMatrix.IndexPointers, 172
- SUNSparseMatrix.IndexValues, 172
- SUNSparseMatrix.NNZ, 69, 171
- SUNSparseMatrix.NP, 172
- SUNSparseMatrix.Print, 171
- SUNSparseMatrix.Realloc, 171
- SUNSparseMatrix.Reallocate, 171
- SUNSparseMatrix.Rows, 171
- SUNSparseMatrix.SparseType, 172
- SUPPRESS_ALG, 90

- tolerances, 14, 33, 34, 67

- UNIT_ROUNDOff, 26
- User main program
 - FIDA usage, 82
 - FIDABBD usage, 93
 - IDA usage, 28
 - IDABBDPRE usage, 75
- user_data, 41, 66–68, 74, 75
- weighted root-mean-square norm, 14